ACT-R 7.13⁺ Reference Manual

Dan Bothell

Includes material adapted from the ACT-R 4.0 manual by Christian Lebiere, documentation on the perceptual motor components by Mike Byrne and the Introduction is a shortened version of the ACT-R description written by Raluca Budiu for the ACT-R web site.

Notice

ACT-R 7.6 represents a significant rewrite of the core software, but does not include any changes to the underlying cognitive architecture. As noted by the version number, it is not guaranteed to be backwards compatible with prior versions of the ACT-R 7 architecture software. The purpose of this document is to describe the current software. It does not generally describe the differences from prior versions, but in places where such changes are significant some additional information will be provided.

Table of Contents

Notice	3
Table of Contents	4
Preface	18
Introduction	19
Document Overview	21
General Software Description	22
Licensing	23
Case sensitivity	23
Functions vs. Macros	23
Compatibility issues	24
Notations in the Documentation	25
Command Syntax	25
Examples	26
Remote commands	26
Embedded Strings	26
Transmission Protocol	27
ACT-R Software Distribution	28
Distribution Contents	29
Subdirectories	29
commands	29
core-modules	
dev-tools	29
devices	29
docs	
environment	
examples	
extras	31
framework	
modules	31
other-files	
support	32
test-models	
tools	32
tutorial	
user-loads	
Loading and Running the ACT-R System	33
Single-threaded mode	33
ACT-R version details	33
Component and Module versions	
User Load files	
Compiler Optimizations	
Logical Host	
actr-load	
load-act-r-model/load-act-r-code	
Load order	
Recompiling	39

Packaging	39
Clean	40
Packaged	40
Requiring files	40
require-compiled	40
Overall Software Design	42
Model files	44
Commands & Signals	46
ACT-R Output	47
Commands & Signals	47
general-trace	47
model-trace	47
command-trace	47
warning-trace	48
echo-act-r-output	48
turn-off-act-r-output	49
suppress-act-r-output	49
Software Operation	51
Meta-process	52
Commands & Signals	52
clear-all	52
clear-all-start	53
reset	53
reset-start	54
reload	
mp-time	56
mp-time-ms	
mp-print-versions	
Events	
Commands	
mp-show-queue	
mp-queue-count	
mp-show-waiting	
mp-modules-events	
Component	
Module	
Commands	
all-module-names	
Buffers	
Commands	
buffers	
buffer-chunk	
printed-buffer-chunk	
buffer-status	
printed-buffer-status	
Models	
Commands	
define-model	
delete-model	77

Chunks & Chunk-types	78
Default Chunk-types	
chunk	
constant-chunks	
query-slots	79
clear	
Default Chunks	
Commands	80
Chunk-type Commands	80
chunk-type	80
pprint-chunk-type	82
chunk-type-p	84
all-chunk-type-names	84
chunk-type-possible-slot-names-fct	85
Chunk Commands	
define-chunks	87
pprint-chunks & pprint-chunks-plus	89
chunk-p	92
chunk-documentation	93
chunk-slot-value	93
set-chunk-slot-value	94
mod-chunk	96
copy-chunk	97
chunk-copied-from	98
chunks	100
chunk-slot-equal	101
equal-chunks	102
eq-chunks	103
delete-chunk	104
purge-chunk	105
merge-chunks	106
create-chunk-alias	
true-chunk-name	109
normalize-chunk-names	110
chunk-filled-slots-list	112
General Parameters	114
Commands	
sgp	
get-parameter-default-value	
with-parameters	
get-parameter-value	119
set-parameter-value	
System Parameters	
Commands	
ssp	
get-system-parameter-value	
set-system-parameter-value	
Parameters	
:high-performance	125

Generating Output	
Model Output	.126
Command Output	.126
Warnings	.126
Other Output	.127
Commands	.127
model-output	.127
meta-p-output	.128
command-output	.129
no-output	
print-warning	
model-warning	
one-time-model-warning	
Running the system	
Commands & signals	
run-start	
run-stop	
run	
run-full-time	
run-until-time.	
run-until-condition	
run-until-action	
run-n-events	
run-step	
Scheduling Events	
Details of events	
time	
priority	
action	
parameters	
model	
module	
destinationdestination	
details	
output	
Event Implementation	
Event Accessors	
General Event Commands	
event-displayed-p	
format-event	
Scheduling Commands	
schedule-event, schedule-event-relative, schedule-event-now	
schedule-event-after-module	
schedule-event-after-change	
schedule-periodic-event	
schedule-break, schedule-break-relative	
schedule-break-after-module	
schedule-break-after-all	
delete-eventdelete-event	.169

Event Hooks	
add-pre-event-hook, add-post-event-hook	170
delete-event-hook	
About the Included Modules and Components	174
Printing module	175
Parameters	175
:cbct	175
:cmdt	175
:model-warnings	176
:trace-detail	176
:trace-filter	176
:v	177
Naming Module and Component	178
Parameters	178
:ncnar	179
Commands	180
new-name	180
release-name	182
new-symbol	183
Random module	185
Parameters	185
:randomize-time	185
:seed	185
Commands	186
act-r-random	186
act-r-noise	187
randomize-time, randomize-time-ms	188
History Recorder	191
Commands	191
define-history	191
define-history-constituent	193
define-history-processor	195
history-data-available	196
record-history	197
stop-recording-history	198
get-history-dataget-history-data	199
process-history-data	201
save-history-data	202
start-incremental-history-data, get-incremental-history-data	203
Buffer trace module	205
Commands	206
add-buffer-trace-notes	206
Central Parameters Module	208
Parameters	208
:er	208
:esc	209
:ol	209
System Parameters	209
:starting-parameters	209

Commands	210
register-subsymbolic-parameters	210
The Procedural System	211
Procedural Module	212
Conflict Resolution	212
Parameters	213
:crt	214
:cst	214
:cycle-hook	214
:dat	214
:do-not-harvest	215
:lhst	215
:ppm	215
:ppm-hook	216
:rhst	216
:style-warnings	
:use-tree	217
:vpft	
Production buffer	
Commands	
p/define-p	218
all-productions	
pp	
pbreak/punbreak	
pdisable/penable	
whynot	243
production-firing-only	246
un-delay-conflict-resolution	
clear-productions	
declare-buffer-usage	248
Utility module	250
Parameters	250
:alpha	250
:egs	250
:iu	
:nu	
:reward-hook	251
:ul	252
:ult	
:ut	
:utility-hook	
:utility-offsets	
Commands.	
trigger-reward	
spp	
Production Compilation Module	
Parameters	
:epl	
:pct	
.	

:tt	262
Commands	262
show-compilation-buffer-types	263
compilation-buffer-type	
specify-compilation-buffer-type	
Goal ModuleGoal Module	
Goal buffer	
Queries	
Requests	
Modification Requests	
Commands	
goal-focus	
mod-focus.	
Imaginal Module	
Parameters	
:imaginal-delay	
:vidt	
Chunk-types & Chunks	
Imaginal buffer	
Requests	
Modification requests	
Imaginal-action buffer	
Requests	
Commands	277
set-imaginal-free	277
set-imaginal-error	277
Declarative module	279
Activation	280
Base-level	280
Spreading Activation	
Partial Matching	
Noise	
Retrieval time	
Declarative finsts	
Parameters	
:act	
:activation-offsets	
:ans	
:bl-hook	
:blc	
:bll	
:cache-sim-hook-results	
:chunk-add-hook	
:chunk-merge-hook	
:declarative-finst-span	
:declarative-num-finsts	289
:declarative-stuffing	289
:le	289
:lf	290

:mas	290
:md	290
:mp	290
:ms	290
:noise-hook	290
:nsji	290
:partial-matching-hook	
:pas	
:retrieval-request-hook	
:retrieval-set-hook	
:retrieved-chunk-hook	
:rt	
:sact	
:sim-hook.	
:sji-hook	
:spreading-hook	
:w-hook	
Retrieval buffer	
Queries	
Requests	
History Stream	
retrieval-history	
Commands	
add-dm	
dm	
sdm	
print-dm-finsts	
1	
sdp	
sji/add-sji	
similarity/set-similarities	
get-base-level/set-base-levels/set-all-base-levels	
clear-dm	
reset-declarative-finsts	
merge-dm	
print-activation-trace	
print-chunk-activation-trace	
saved-activation-history	
whynot-dm	
simulate-retrieval-request	
add-dm-chunks	
merge-dm-chunks	
Perceptual & Motor modules	
Devices	
Device Module	
Parameters	
:cursor-fitts-coeff	
:default-target-width	338
:key-closure-time	338
:needs-mouse	338

:pixels-per-inch	339
:process-cursor	339
:stable-loc-names	339
:viewing-distance	339
Commands	339
install-device	339
remove-device	340
current-devices	341
defined-devices	342
defined-interfaces	343
notify-device	343
Vision module	345
The model's visual world	345
The Where System	345
Finsts	346
The What System	346
Re-encoding	347
Scene change	347
Tracking	348
Interface & Devices	348
History Stream	349
visicon-history	349
Parameters	349
:auto-attend	349
:delete-visicon-chunks	350
:optimize-visual	350
:overstuff-visual-location	350
:scene-change-threshold	350
:tracking-clear	350
:unstuff-visaul-location	351
:visual-attention-latency	351
:visual-finst-span	351
:visual-movement-tolerance	351
:visual-num-finsts	351
:visual-onset-span	351
:visual-encoding-hook	352
Visual-location buffer	352
Queries	352
Requests	
Visual buffer	357
Queries	357
Requests	358
Chunks & Chunk-types	362
Commands & Signals	364
visicon-update	364
visual-clear	364
installing-vision-device	364
print-visicon	365
printed-visicon	366

remove-visual-finsts	366
set-visloc-default	368
add-word-characters	370
set-visual-center-point	372
attend-visual-coordinates	372
schedule-encoding-complete	373
chunk-to-visual-position	374
Audio module	
Auditory world	
The Where System	
The What System	
History Stream	
audicon-history	
Parameters	
:aural-encoding-hook	
:aural-loc-hook	
:digit-detect-delay	
:digit-duration	
:digit-recode-delay	
:overstuff-aural-location.	
:sound-decay-time	
:tone-detect-delay	
:tone-recode-delay	
:unstuff-aural-location	
Aural-location buffer	
Queries	
Requests	
Aural buffer	
Queries	
Requests	
Chunks & Chunk-types	
Commands & Signals	
new-sound	
new-digit-sound/new-tone-sound/new-other-sound/new-word-sound	
print-audiconprint-audicon	
printed-audicon.	
set-audloc-default	
schedule-audio-encoding-complete	
Motor module	
Physical world	
Operation	
Fitts's Law	
Interface & Devices	
Keyboard	
Cursor	
Parameters	
:cursor-noise	
:incremental-mouse-moves	
:min-fitts-time	402

:motor-burst-time	402
:motor-feature-prep-time	402
:motor-initiation-time	402
:peck-fitts-coeff	402
Manual Buffer	402
Requests	404
Chunks & Chunk-types	417
Commands	418
start-hand-at-mouse	418
start-hand-at-joystick1	418
start-hand-at-joystick2start-hand-at-joystick2	
start-hand-at-keypad	
start-hand-at-key	
set-hand-location	
set-cursor-position	
extend-manual-requests	
remove-manual-request	
Speech module	
The vocal world	
Operation	
Interface & Devices	
Microphone	
Parameters	
:char-per-syllable	
:subvocalize-detect-delay	
:syllable-rate	
Vocal buffer	
Queries	
Requests	
Chunks & Chunk-types	
Commands	
get-articulation-time/register-articulation-time	
Femporal Module	
Parameters	
:record-ticks	
:time-master-start-increment	
:time-mult	
:time-noise	
Temporal buffer	
Requests	
Modification requests	
Chunks & Chunk-types	
Commands	
Advanced Topics	
Extending Possible Chunk Slots	
Commands	
extend-possible-slots	
Extend-possible-siots	
Commands	
Communication	445

define-chunk-spec	
chunk-spec-to-id	448
release-chunk-spec-id	448
chunk-name-to-chunk-spec	449
pprint-chunk-spec	450
printed-chunk-spec	451
match-chunk-spec-p	452
find-matching-chunks	
chunk-spec-slots	456
slot-in-chunk-spec-p	
chunk-spec-slot-spec	
slot-spec-modifier/slot-spec-slot/slot-spec-value	
chunk-spec-variable-p	
chunk-spec-to-chunk-def	
verify-single-explicit-value	
test-for-clear-request	
chunk-difference-to-chunk-spec	
Using Buffers	
Commands	
buffer-read	
query-buffer	
clear-buffer	
set-buffer-chunk	
overwrite-buffer-chunk	
mod-buffer-chunk.	
set-buffer-failure	
module-request	
module-mod-request	
buffer-spread	
buffers-module-name	
Extending Chunks	
Commands	
extend-chunks	
Defining New Modules	
Documentation	
Buffers	
spreading activation weight	
request parameters	
queries	
query printing	
multi-buffer	
Parameters	
name	
owner	
documentation	
default-value	
valid-test	
warning	
Interaction commands	

creation	
reset	
deletedelete	508
parameters	508
queries	509
requests	509
buffer modification requests	510
notify upon clearing	511
notify at the start of a new call to run the system	
notify upon a completion of a call to run the system	
warning of an upcoming request	512
search and offset	513
Common Class of Modules – Goal Style	513
Writing Module Code	
Module examples	515
Commands	515
get-module	515
define-buffer	
define-parameter	
define-module	
undefine-module	525
goal-style-query	526
goal-style-request	
create-new-buffer-chunk	
goal-style-mod-request	529
Multi-buffers	
Commands	532
store-m-buffer-chunk.	
get-m-buffer-chunks	
remove-m-buffer-chunk	
remove-all-m-buffer-chunks	537
erase-buffer	537
Searchable buffers	
Multiple Models	
Commands	
current-model	
mp-models	
delete-model	
with-model	
Other multiple model examples	
Configuring Real Time Operation	
Dynamic events	
Commands	
mp-real-time-management	
Module Activity and Brain Predictions	
What counts as buffer activity?	
Recording module activity	
Getting module activity	
module-demand-times	

module-demand-functions	559
module-demand-proportion	562
BOLD module	564
Parameters	566
:bold-param-mode	566
:bold-exp & :neg-bold-exp	567
:bold-scale & :neg-bold-scale	
:bold-positive & :bold-negative	567
:bold-settle	
:bold-inc	568
:point-predict	568
History Processors	569
bold-prediction	569
bold-prediction-with-time	570
bold-prediction-with-time-scaled	571
Commands	571
predict-bold-response	571
Checking and testing version information	
Feature tests	
System parameters	575
:act-r-version	575
:act-r-architecture-version	575
:act-r-major-version	576
:act-r-minor-version	576
Version test command	576
written-for-act-r-version	576
Loading Extra Components	579
Commands	579
require-extra	579
Creating Visual Features	581
Object-creator device	581
Examples	582
Commands	582
add-visicon-features	582
modify-visicon-features	584
delete-visicon-features	586
delete-all-visicon-features	586
set-default-vis-loc-slots	587
Adding new production compilation types	589
References	

Preface

This document is a work in progress. It started as the reference manual for ACT-R 7 and has been updated to reflect the software for versions 7.x (where x > 5). All of the information has been updated and should accurately reflect the operation of the new software, but there are some features of the new system (as well as the older ones) which are not yet documented. The hope is that although it is not yet complete, this working version will be of some use to ACT-R modelers.

Introduction

ACT-R is a cognitive architecture: a theory about how human cognition works. Its constructs reflect assumptions about human cognition which are based on numerous facts derived from psychology experiments. It is a hybrid cognitive architecture — it has both symbolic and subsymbolic components. Its symbolic structure is a production system and its subsymbolic structure is represented by a set of massively parallel processes that can be summarized by a number of mathematical equations. The subsymbolic equations control many of the symbolic processes, and are also responsible for most learning processes in ACT-R.

Using ACT-R, researchers can create models that incorporate ACT-R's view of cognition and their own assumptions about a particular task. These assumptions can be tested by comparing the results of the model performing the task with the results of people doing the same task. By "results" we mean the traditional measures of cognitive psychology: time to perform the task, accuracy in the task, and, (more recently) neurological data such as those obtained from fMRI.

One important feature of ACT-R that distinguishes it from other theories in the field is that it allows researchers to collect quantitative measures that can be directly compared with the quantitative measures obtained from human participants.

ACT-R has been used successfully to create models in domains such as learning and memory, problem solving and decision making, language and communication, perception and attention, cognitive development, and individual differences.

Beside its applications in cognitive psychology, ACT-R has also been used in other fields including:

- human-computer interaction to produce user models that can assess different computer interfaces
- education (cognitive tutoring systems) to "guess" the difficulties that students may have and provide focused help
- computer-generated forces to provide cognitive agents that inhabit training environments
- neuropsychology, to interpret fMRI data.

For more detailed information, please refer to the description of the ACT-R theory in the paper "An Integrated Theory of the Mind" (2004) which is available from the ACT-R web site at: <a href="http://act-paper/linear.com/http://act-paper/linear.com/http://act-paper/linear.com/http://act-paper/linear.com/http://act-paper/linear.com/http://act-paper/linear.com/http://act-paper/linear.com/http://act-paper/linear.com/http://act-paper/linear.com/http://act-paper/linear.com/http://act-paper/linear.com/http://act-paper/linear.com/http://act-paper/linear.com/http://act-paper/linear.com/http://act-paper/linear.com/http://act-paper/linear.com/http://act-paper/linear.com/http://act-paper/linear.com/http://act-paper/linear.com/http://act-paper/linear.com/http://act-paper/linear.com/http://act-paper/linear.com/http://act-paper/linear.com/http://act-paper/linear.com/http://act-paper/linear.com/http://act-paper/linear.com/http://act-paper/linear.com/http://act-paper/linear.com/http://act-paper/linear.com/http://act-paper/linear.com/http://act-paper/linear.com/http://act-paper/linear.com/http://act-paper/linear.com/http://act-paper/linear.com/http://act-paper/linear.com/http://act-paper/linear.com/http://act-paper/linear.com/http://act-paper/linear.com/http://act-paper/linear.com/http://act-paper/linear.com/http://act-paper/linear.com/http://act-paper/linear.com/http://act-paper/linear.com/http://act-paper/linear.com/http://act-paper/linear.com/http://act-paper/linear.com/http://act-paper/linear.com/http://act-paper/linear.com/http://act-paper/linear.com/http://act-paper/linear.com/http://act-paper/linear.com/http://act-paper/linear.com/http://act-paper/linear.com/http://act-paper/linear.com/http://act-paper/linear.com/http://act-paper/linear.com/http://act-paper/linear.com/http://act-paper/linear.com/http://act-paper/linear.com/http://act-paper/linear.com/http://act-paper/linear.com/http://act-paper/linear.com/http://act-paper/linear.com/http://act-paper/linear.com/http://act-paper/linear.com/http://act-paper/linear.com/http

<u>r.psy.cmu.edu/papers/403/IntegratedTheory.pdf</u>, or to the book "How Can the Human Mind Occur in the Physical Universe?".

Document Overview

This manual is a guide and reference for the ACT-R 7.6 (and newer) software implementation. It is not meant to be a tutorial or a textbook on the ACT-R theory or a "how to" on writing models using ACT-R. The ACT-R Tutorial, which accompanies the software, is designed to introduce the theory and techniques for modeling with ACT-R. This document is intended to be a compliment to the tutorial, and it describes the components of the implementation, how they are connected, the commands available to the user, and some recommended practices for use.

This manual is a reference for the ACT-R 7.6 (and newer) implementations only. It does not describe mechanisms from older implementations nor does it thoroughly discuss how commands may differ from similar commands in previous versions.

General Software Description

ACT-R 7.6 (hereafter referred to only as ACT-R) is written in ANSI Common Lisp. To use the remote capabilities of the software will also require Quicklisp to load the following additional libraries: :bordeaux-threads, :usocket, :cl-json, and :jsown, but it can be loaded in a Lisp only mode which does not require Quicklisp. It was implemented and tested using Allegro Common Lisp by Franz Inc. http://www.franz.com/ and Clozure CL http://www.clozure.com/clozurecl.html. The remote capable version has also been tested with LispWorks by LispWorks http://www.lispworks.com and SBCL http://sbcl.sourceforge.net/. Although the necessary Quicklisp libraries are also available for ABCL http://common-lisp.net/project/armedbear/, there appears to be some problem with the socket implementation which prevents it from working. However, ABCL will work in the Lisp only mode as will Embeddable Common-Lisp https://common-<u>lisp.net/project/ecl/</u>. If you have problems loading or running ACT-R in any Lisp please contact Dan Bothell (db30@andrew.cmu.edu) with the details. We also make the ACT-R system available as a standalone application for those that do not have Lisp software. The standalone versions include a command line only version of Clozure CL and thus are as complete a system as one has when using the ACT-R source code, but it may not be as easy to use as a Lisp which has a nice IDE or which is used through an interface like SLIME, SLIMV, or with the Inferior Lisp mode of Emacs.

It is not necessary for one to be a Lisp programmer to be able to use ACT-R. However, because ACT-R is running in Lisp and the ACT-R model files are written using Lisp syntax, some familiarity with basic Lisp constructs can be helpful. An introduction to Lisp is beyond the scope of this document, but there are many introductory Lisp books available as well as many online resources. Two online resources where you can find additional information about Lisp are <u>The Association of Lisp Users</u> and <u>CLiki, the Common Lisp wiki</u>.

Prior to this version of ACT-R the only means of interacting with ACT-R was through the Lisp readeval-print loop (a command line interface) and a set of GUI tools called the ACT-R Environment (which is described in its own manual). While those are still available, this version of the software also contains an RPC (remote procedure call) system which allows one to interact with the software from external systems as well. Not all of the commands are currently available through that remote interface (which is described in detail in a separate document), but those that are will be noted in this manual. Also, included with the ACT-R tutorial materials is a Python module which provides access to all of the ACT-R commands necessary for running the tutorial's experiments and interacting with ACT-R from an interactive Python session. Information on using that interface are included in the tutorial.

Licensing

The ACT-R software is provided under the LGPL license version 2.1, which can be found in the docs directory of the distribution.

Case sensitivity

Generally the names of items in ACT-R are not case-sensitive. However, the one exception to that is that the names of commands accessed through the RPC interface are case sensitive, but the names of ACT-R elements passed to those commands through the RPC interface are still case insensitive. In addition to that, names provided through the RPC may not necessarily be returned in the same case as provided. The ACT-R software typically upcases names, but that is not guaranteed and no assumptions should be made about the case of names for ACT-R elements.

When using the ACT-R source code one should only use an ANSI compliant case insensitive Lisp system. A Lisp like the "modern mode" version available with ACL may result in problems when trying to use ACT-R and a warning will be displayed if the software is loaded into such a system to indicate that problems could occur.

Functions vs. Macros

When working from Lisp many of the ACT-R user commands are implemented as macros which do not evaluate their arguments so that one does not have to quote the arguments. This makes it generally easier to work with the ACT-R software without having to worry as much about Lisp syntax, but does mean that if one wants to use ACT-R commands programmatically more effort is required to either explicitly evaluate the macro command with its arguments or to use a corresponding ACT-R function. Most of the macro based ACT-R commands also have a corresponding function which will have the same name, but with a –fct appended to it e.g. add-dm and add-dm-fct. The functions occasionally require a slightly different specification of the parameters relative to the macro, for example requiring that a list of items be provided instead of just specifying an arbitrary number of items. A command's description and examples will indicate any such differences.

Compatibility issues

There are a few minor issues with particular Lisp versions that require some patches in the ACT-R code. Those changes are described here because it may affect other Lisp code which one writes in those Lisps while using ACT-R.

Three such issues occur with SBCL. The first is that SBCL takes a very strict interpretation of how defconstant should operate which prevents some code which contains defconstant calls from being compiled and then loaded within the same instance of SBCL. To avoid that problem the ACT-R code shadows the defconstant macro in SBCL with a macro which calls cl::defconstant and wraps it with an ignore-errors when the variable specified is already bound. The second is that the internal SBCL code already defines a function called reset. To fix that the ACT-R code just shadows the reset function. The final patch for SBCL occurs for the Windows version of the directory function because it does not handle wildcard characters in the same way as other Lisps (or even other OS versions of SBCL). Again, to address this the default function is shadowed with one in the ACT-R code which handles things as needed.

There is one such issue with CLisp because it has a function named execute defined internally. The fix for that is to shadow the internal function with the one defined in ACT-R.

Notations in the Documentation

In the description of some commands it will describe a parameter or return value as a "generalized boolean". What that means is that the value is used to represent a truth value – either true/successful or false/failure. If the value is the symbol **nil** then it represents false and all other values represent true. When a generalized boolean is returned by one of the commands, one should not make any assumptions about the returned value for the true case. Sometimes the true value may look like it provides additional information, but if that is not specified in the command's description then it is not guaranteed to hold for all cases or across updates to the command.

Command Syntax

When describing a command's syntax the following conventions will be used:

- items appearing in **bold** are to be entered verbatim
- items appearing in *italics* take user-supplied values
- items enclosed in {curly braces} are optional
- * indicates that any number of items may be supplied
- + indicates that one or more items may be supplied
- | indicates a choice between options which are enclosed in [square brackets]
- (parentheses) denote that the enclosed items are to be in a list
- -> indicates that calling the command on the left of the "arrow" will return the item to the right of the "arrow"
- ::= indicates that the item on the left of that symbol is of the form given by the expression on the right

These two additional indicators will be used when describing the syntax of commands available through the remote interface when they differ from that of the Lisp command.

- <angle brackets> denote an options list for providing optional named parameters to a command and the available parameter names and values are indicated between the angle brackets and separated by commas
- 'single quotes' around one or more parameters indicates that those parameters use the additional string encoding <u>noted below</u>

Examples

When examples are provided for the commands they are shown as if they have been evaluated at a Lisp prompt. The prompt that is shown prior to the command indicates additional information about the example. There are three types of prompts that are used in the examples:

- A prompt with just the character '>' indicates that it is an individual example independent of those preceding or following it.
- A prompt with a number followed by '>', for example "2>" means that the example is part of a sequence of calls which were evaluated and the result depends on the preceding examples. For any given sequence of calls in an example the numbering will start at 1 and increase by 1 with each new example in the sequence.
- A prompt with the letter E preceding the '>', "E>", indicates that this is an example which is either incorrect or was evaluated in a context where the call results in an error or warning. This is done to show examples of the warnings and errors that can occur.

Remote commands

When a command is available for use through the RPC interface the name of the command to access it and any differences in the parameters for using it through the RPC interface will be described. One general issue to note is that many of the items provided through the RPC interface will be in strings since Lisp symbols are not a valid data format for the communication protocol (nor in most other languages from which the RPC will likely be accessed). That is true for values that are being passed into ACT-R commands as well as any values that they return. When the strings refer to the names of ACT-R constructs (chunks, productions, modules, etc) they are not case sensitive and no assumptions should be made about the case of any result e.g. just because the Lisp being used is upcasing symbol names does not guarantee that all strings of names returned through the RPC interface will be upper case.

Embedded Strings

For some commands in Lisp either a symbol or a string could be provided and that distinction would be important (for example in a slot value of a chunk). In those cases a special syntax is required for the strings sent through the RPC interface to distinguish a string containing a name from a value which should be treated as just a string. The special syntax for that is to mark the item which should be a string instead of a name with an additional bracketing of single quotes inside the string e.g. "chunk1" would represent the symbol chunk1 but "'chunk1" would represent the string "chunk1". If

a command requires this addition syntax for differentiating names (symbols) from strings it will be noted, otherwise the assumption is that all strings will be converted to symbols coming into ACT-R commands and symbols will be converted to strings when returned from ACT-R commands that are sent through the remote interface.

Transmission Protocol

The underlying format for the data sent through the remote interface is JSON. When dealing with the Lisp symbols **t** or **nil** as return values from ACT-R commands, they will be converted to the JSON values of **true** and **null** respectively. When truth values are passed into an ACT-R command through the RPC it will convert the JSON value of **true** to the Lisp symbol **t** and both the JSON values **false** and **null** will be converted to the Lisp symbol **nil**.

ACT-R Software Distribution

There are two primary means of acquiring the ACT-R software. The first is from the ACT-R web site http://act-r.psy.cmu.edu. The software page of the web site has the most recently released version of ACT-R available as either a .zip of the source files or built into a standalone application for Linux, Mac OS, or Windows. The released versions have been tested against the reference models and the output of the models should be consistent with respect to what is printed in the tutorial. New releases are made when there are significant updates or patches and typically happen two or three times a year. The other method for acquiring the software is via version control software called Subversion. More information on Subversion can be found at http://subversion.apache.org/. The ACT-R archive is located at <svn://act-r.psy.cmu.edu/actr7.x>. The Subversion archive contains the most up to date version of ACT-R, and often contains minor changes or bug fixes not yet available in a released version. Note however that the minor changes made to the sources available through Subversion are not all tested thoroughly against the tutorial models and there may be discrepancies with respect to the tutorial documentation until the next released version.

Distribution Contents

The ACT-R distribution consists of: the Lisp source code files which implement ACT-R, the ACT-R Environment application along with its corresponding Tcl/Tk source code files, the ACT-R Tutorial unit texts and models, documentation for the software and tools, examples showing some advanced capabilities not covered in the tutorial, and some extensions of the system which are not included by default. All of the files are distributed in a single directory, called actr7.x, which contains three files and several subdirectories. The files are load-act-r.lisp which is the file that should be loaded to load the main ACT-R software (see Loading and Running the ACT-R System), load-single-threaded-act-r.lisp which loads a special "Lisp only" version of the software (see Single-threaded mode), and a file called readme.txt which contains some information about the distributed files. Here is a listing of the subdirectories along with a general description of their purpose and some of their specific contents.

Subdirectories

commands

This directory contains the Lisp code for user commands for some of the central modules. One feature of this directory is that any file with a .lisp extension placed into this folder will be compiled and loaded with the rest of the system.

core-modules

This directory contains the Lisp code that defines the modules which instantiate the main ACT-R system described in the theory. They are assumed to always be available, but are not absolutely required. The core modules are Procedural, Declarative, Goal, Vision, Auditory, Motor, Speech, and Imaginal and are all described in this manual.

dev-tools

This directory contains subdirectories with the scripts that are used to build the distribution bundles as well as the standalone applications. It is not intended for users and is only included in the subversion repository – not in the distributed software releases.

devices

This directory previously contained subdirectories where one could provide the implementation of devices for ACT-R which can interact with particular Lisps' GUI components. The overall notion of a device for ACT-R has changed as of ACT-R 7.6 to better support remote interactions, and thus the current version only contains a generic virtual system for models to use. [However, the Lisp specific

implementations from prior versions of ACT-R may be updated and included in the future.] The details on creating and using <u>devices</u> is described later in this manual and there is also an additional manual with documentation on using the virtual GUI components implemented with the provided device called the AGI (ACT-R GUI Interface).

docs

This directory contains the documentation files for ACT-R. They include details on using the system, as well as documents describing particular features. Most are either Microsoft Word documents (.doc files) or PDFs depending on how the files were acquired (the Subversion repository holds the .docs but they are converted to .pdf for the releases found on the website). Here are descriptions of some of the files found there:

- AGI
 - o The manual for the AGI tools. (not currently updated for 7.6)
- compilation.xls
 - O An Excel Spreadsheet that is used to define the operation of the production compilation mechanism for different buffer styles.
- device-interaction-issues
 - O A document indicating some issues to be aware of when building and working with devices in ACT-R which connect to real GUI items or external systems. (not currently updated for 7.6)
- EnvironmentManual
 - o A manual for the GUI tools provided by the ACT-R Environment application. (not currently updated for 7.6)
- LGPL.txt
 - O The Lesser Gnu Public License text. That is the license under which the ACT-R software is distributed.
- QuickStart.txt
 - O A text file with instructions on how to load ACT-R and start the ACT-R Environment.
- reference-manual
 - o This document.
- remote
 - O A document which describes the underlying details of the remote interface.

In the subversion repository (but not the released versions) there is also a subdirectory called notes which contains some files with historical documentation on utility learning and production compilation as well as some files that contain information which is useful for development purposes (not generally applicable to users).

environment

The environment directory contains all of the files necessary for using the ACT-R Environment. There are several items in this directory: Lisp files that provide the internal support for the tools, the Environment applications for Linux, Mac OS X, and Windows, and a GUI directory that contains the Tcl/Tk files used by the Environment application.

examples

Several Lisp files and directories which contain examples of using more advanced components of the software like multiple models, visual tracking, creating new visual features, making remote connections in various languages (currently C, Lisp, Java, MATLAB, Node.js, Python, R, and Tcl/tk examples available), and adding new modules (both locally in Lisp and remotely from Python).

extras

The extras directory contains additional modules and other files that have been contributed to the distribution, but which are not part of the default ACT-R system and are not loaded by default. Each addition is included in its own subdirectory and directions for using the extension should be found within the files themselves or the documentation which accompanies them. For most of the extras there is a command which can be added to a model file to load the file(s) necessary to use that extra automatcally described in the <u>loading extra components</u> section. Currently none of the extras have been tested with ACT-R 7.6, and their use is not recommended at this time.

framework

The framework directory contains the Lisp files that define the software framework upon which the ACT-R system is based. The software framework is a basic discrete event simulation system that was designed to implement ACT-R, but is not based on the theory of the ACT-R.

modules

The modules directory contains Lisp files which implement additional modules which are loaded into the default ACT-R system. As with the commands directory, any files with a .lisp name placed into this directory will be loaded automatically when ACT-R is loaded.

other-files

This directory contains Lisp files that add additional tools for ACT-R. Like the commands and modules directories, any file with a .lisp extension placed into this directory will be automatically loaded with the system.

support

The support directory contains Lisp files that may be needed for certain Lisp implementations, by certain modules of the system, or for particular extensions or tools. These files are loaded when required by other files. Files with a .lisp name placed here can be compiled and loaded when needed using the <u>require-compiled</u> command.

test-models

This directory contains tasks and models from the ACT-R tutorial (in both Lisp and Python), other model and task files, and files of the expected output for the tests. These are used for regression testing the software and is only available via subversion.

tools

The tools directory contains Lisp files that define additional functions and tools for ACT-R. Like the commands and modules directories, all files with a .lisp name placed into this folder will be automatically loaded.

tutorial

The tutorial directory contains several subdirectories. There are directories for each of the units in the tutorial, and also directories for implementations of the experiments used in the tutorial for different languages (currently Lisp and Python). Each unit consists of a text on a particular aspect of ACT-R, one or more demonstration models, a partial model which provides a starting point for an assignment, a text describing the code that implements the tasks for the models in that unit, and in some units an additional text with details on how to debug models along with a broken model to work through the debugging process.

user-loads

The user-loads directory contains no files in the distribution. It is provided as a place for users to add files which will be loaded automatically after ACT-R has finished loading and initializing. All of the files in the user-loads directory with a .lisp name will be compiled and loaded in order based on the file names sorted using the Lisp string< function. Because this occurs after the system has been initialized it is safe to put a model file into this directory.

Loading and Running the ACT-R System

To start ACT-R from source code all one needs to do is load the load-act-r.lisp file into a Lisp which

also has Quicklisp installed. That will load all of the necessary files for ACT-R. The file should only

be loaded into a given Lisp session once.

The files are compiled before loading and that will usually generate some warnings from the

compiler. Those warnings can be safely ignored. The files are only compiled the first time you load

ACT-R. The compiled files are saved with the source files and on subsequent loadings there is no

need to recompile everything. Thus, on all loadings after the first one, it should load faster and

produce fewer warnings, but there may be times when you need to have files compiled again and that

is described in the section below.

Single-threaded mode

If one does not need to use the remote connection ability and is not accessing ACT-R commands

from other threads in Lisp then the load-single-threaded-act-r.lisp file may be used instead. When

that file is loaded Quicklisp is not necessary and the system generally runs much faster (about twice

as fast in most test models).

ACT-R version details

Once the loading of the ACT-R code is complete, you will see a print out describing the current

version of ACT-R that has been loaded. That is indicated by the line that starts with Software

followed by a version description. That will take one of two general forms:

ACT-R 7 Version Information:

Software : 7.6.1-<internal>

or

ACT-R 7 Version Information:

Software : 7.6.1-<2496:2018-01-11>

All of the versions will start with 7 because that indicates the current cognitive architecture (it is

effectively the name much like the X (ten) in the name of the current Apple Macintosh operating

system). That will be followed by one or two digits (separated by periods) indicating the specific

software version, and then a hyphen and a tag in angle brackets which describes where that code

33

came from. If the tag says "internal" that means that it was not a relased version of the software and it was likely checked out from the subversion repository. For an official release of the software the tag will indicate which specific repository revision it contains followed by a colon and then the date on which the release occurred (the above example indicating that it is repository revision 2496 and was released on January 11th, 2018). If it is a standalone version there will be an additional letter after the revision number indicating the OS for which it was built.

The digits representing the software version will be updated when a significant change (not routine maintenance or bug fixes) to the software occurs. A significant change which does not affect the operation of existing models (which would usually be an addition of a new capability or extension of an existing one) will result in an increment of the second version number or setting the second version number to 1 if it doesn't currently have one. A change which may affect the operation of existing models will cause the first version number to be incremented.

That means models written for version 7.A.B should run the same in any version 7.A.C where C is greater than or equal to B (where B is considered to be 0 if it does not exist) i.e. within a given major version (the A) models can be expected to run the same in any version after the one in which they were initially created but not necessarily those before because those prior versions may be lacking in some new feature or capability. Whereas a model written for major version A is not guaranteed to run the same in any different major version – it might still work the same but that is not guaranteed.

In a <u>later section</u> there are additional details on how one can test the current version information if needed, and it also describes a command which can be placed into a model file to warn users if the version of ACT-R being used may not be compatible with the version for which the model was written.

Component and Module versions

After the ACT-R version has been printed there will be a listing of all the compoents and modules that are currently defined in the software along with their versions and brief descriptions. That will look like this:

Components

AGI : 5.0 Manager for the AGI windows

...

Modules

AUDICON-HISTORY : 3.0 Module to record audicon changes.

. . .

The version information for a module is not as structured as the overall ACT-R version, but generally a change in the major version number for a module indicates a significant change that likely affects the compatibility with existing models/code (and would trigger a corresponding change in the ACT-R version). Whereas a minor version number change can occur for many reasons, but typically does not affect the existing functionality of the module.

The module details will be followed by a line that looks like this:

```
####### Loading of ACT-R 7 is complete #######
```

At that point, all of the ACT-R code has been loaded and if there are no user provided files to be loaded the software is ready to use.

User Load files

If there are any files in the user-loads directory then there will be at least two additional lines displayed. The first will be:

```
####### Loading user files #######
```

That will be followed by any information displayed while the files in that directory are compiled and loaded. After all of those files have been loaded this will then be displayed:

```
####### User files loaded #######
```

The software is then ready to use.

Compiler Optimizations

Normally, when ACT-R compiles its files it uses the current optimization settings of the Lisp. However, if **:actr-fast** is on the features list when load-act-r.lisp is loaded it will apply these settings before compiling the ACT-R sources:

```
(proclaim '(optimize (speed 3) (safety 1) (space 0) (debug 0))))
```

and those settings will remain after the loading is finished. With those settings ACT-R should run faster, but how much faster will vary from Lisp to Lisp. If the ACT-R source files were compiled without the switch then setting the switch and recompiling them will be required to see the improved performance.

Logical Host

As part of loading ACT-R a logical host of "ACT-R" is defined which maps to the directory where the load-act-r.lisp file is located. That logical host is available for use by the user, and it can be useful when working with the tutorial to load the tutorial models. Here is an example which will load the count model from unit1 (assuming that one has not moved the tutorial files):

```
> (load "ACT-R:tutorial;unit1;count.lisp")
; Loading C:\Users\db30\Desktop\actr7\tutorial\unit1\count.lisp
T
```

Note however that some Lisps will not allow a logical pathname to be passed to commands like load and one will have to translate that into a physical pathname using translate-logical-pathname:

```
> (load (translate-logical-pathname "ACT-R:tutorial;unit1;count.lisp"))
; Loading C:\Users\db30\Desktop\actr7\tutorial\unit1\count.lisp
```

To avoing having to explicitly translate the pathname, there is a function provided which performs those two steps, and two additional functions which will optionally compile a file as well which can also be used remotely.

actr-load

Syntax:

actr-load pathname -> [load-return-value | nil]

Arguments and Values:

```
pathname ::= a string or pathname indicating the location of a file to load load-return-value ::= a generalized boolean returned from calling the load command
```

Description:

The actr-load function takes one parameter which is the pathname to a file to be loaded. It will first use the Lisp function translate-logical-pathname to create a physical pathname to the file and if that file exists it will be loaded and return the result of the load function call.

If it does not exist then a warning is printed and **nil** returned.

Examples:

```
> (actr-load "ACT-R:tutorial;unit1;count.lisp")
```

```
E> (actr-load "ACT-R:tutorial;unit12;no-file.lisp")
#|Warning: File #P"C:\\actr7.x\\tutorial\\unit12\\no-file.lisp" does not exist.|#
NTI
```

load-act-r-model/load-act-r-code

Syntax:

```
load-act-r-model pathname {compile} -> [ t | nil ]
load-act-r-code pathname {compile} -> [ t | nil ]
```

Remote command names:

load-act-r-model load-act-r-code

Arguments and Values:

```
pathname ::= a string or pathname indicating the location of a file to load compile ::= a generalized boolean indicating whether to compile the file before loading
```

Description:

The load-act-r-model and load-act-r-code commands take one required parameter which is the pathname to a file to be loaded. They use the Lisp function translate-logical-pathname to create a physical pathname to the file. If such a file exists and the optional parameter is not provided or is **nil** then they will attempt to load that file. If the optional parameter is privided as a non-**nil** value the that file will be compiled and the resulting compiled file will attempt to be loaded. While loading and compiling the file these commands will capture all of the output which is generated and that output will be output to the ACT-R warning trace when complete under a line which says "Non-ACT-R messages during load of *pathname*:". These commands also trap any errors which occur during the compiling and loading and will terminate if an error occurs and output the details of the error to the warning trace.

If the file is successfully compiled and loaded then a value of **t** is returned otherwise they return **nil**.

Only one instance of each of these commands can be operating at a time as a safety measure since they are available through the remote interface. If a second call is made to one of them before a current call completes (regardless of the origin of that ongoing call) it will report an error and return **nil**.

The tutorial unit files like demo2.lisp include a call to load-act-r-model since a single model file can be loaded and run with a task regardless of how it is implemented (currently only Lisp and Python are included with the tutorial).

```
> (load-act-r-code "ACT-R:tutorial;lisp;demo2.lisp")
#|Warning: Non-ACT-R messages during load of "ACT-R:tutorial;unit2;demo2-model.lisp":
; Loading C:\Users\db30\Desktop\actr7.x\tutorial\unit2\demo2-model.lisp
#|Warning: Non-ACT-R messages during load of "ACT-R:tutorial;lisp;demo2.lisp":
; Loading C:\Users\db30\Desktop\actr7.x\tutorial\lisp\demo2.lisp
 |#
> (load-act-r-code "ACT-R:tutorial;lisp;demo2.lisp" t)
#|Warning: Non-ACT-R messages during load of "ACT-R:tutorial;unit2;demo2-model.lisp":
; Loading C:\Users\db30\Desktop\actr7.x\tutorial\unit2\demo2-model.lisp
#|Warning: Non-ACT-R messages during load of "ACT-R:tutorial;lisp;demo2.lisp":
;;; Compiling file C:\Users\db30\Desktop\actr7.x\tutorial\lisp\demo2.lisp
;;; Writing fasl file C:\Users\db30\Desktop\actr7.x\tutorial\lisp\demo2.fasl
;;; Fasl write complete
; Fast loading C:\Users\db30\Desktop\actr7.x\tutorial\lisp\demo2.fasl
|#
T
E> (load-act-r-model "ACT-R:tutorial;unit12;no-file.lisp")
#|Warning: Error "Error #<SIMPLE-ERROR File \"ACT-R:tutorial;unit12;no-file.lisp\" which
translates to #P\"C:\\\\db30\\\Desktop\\\actr7.x\\\\tutorial\\\\unit12\\\\no-
file.lisp\" does not exist.> occurred while trying to evaluate command \"load-act-r-
model\" with parameters (\"ACT-R:tutorial;unit12;no-file.lisp\" NIL)" while attempting to
evaluate the form ("load-act-r-model" "ACT-R:tutorial;unit12;no-file.lisp" NIL) |#
E> (load-act-r-model "ACT-R:tutorial;lisp;demo2.lisp")
#|Warning: Error "Load-act-r-model currently loading a model" while attempting to evaluate
the form ("load-act-r-model" "ACT-R:tutorial;unit2;demo2-model.lisp" NIL) |#
#|Warning: Non-ACT-R messages during load of "ACT-R:tutorial;lisp;demo2.lisp":
; Loading C:\Users\db30\Desktop\actr7.x\tutorial\lisp\demo2.lisp
T #
```

Load order

For those considering adding extensions or just having files loaded automatically, the files and directories are loaded in the following order:

- framework directory files in a predefined order
- core-modules directory files in a predefined order
- all .lisp files from the commands directory in no particular order

- the virtual device files
- any Lisp specific device files
- all .lisp files from the modules directory in no particular order
- all .lisp files from the tools directory in no particular order
 - o the ACT-R Environment files are loaded as part of this step
- all .lisp files from the other-files directory in no particular order
- all .lisp files from the user-loads directory in order with the file names sorted using the Lisp string< function.

Recompiling

If one of the source files in the distribution changes (the date on the .lisp file is newer than the date on the compiled version of that file) then it will automatically be recompiled the next time it is loaded. However, there may be times when you need to force all of the ACT-R files to be recompiled. For instance, if you upgrade or change your Lisp system you will likely need to recompile everything. Also, if you get an update to your current set of ACT-R files it is often best to force a recompile the next time you load it because there may be some interdependencies that will require more than just the updated file to be recompiled.

To force ACT-R to recompile all of its files you should add the :actr-recompile switch to the features list which can be done with this call before loading the load-act-r.lisp file:

```
(push :actr-recompile *features*)
```

If you switch between loading the full version and the single-threaded version then it will automatically recompile all of the files.

Packaging

By default, the ACT-R files are loaded into which ever package is current at the time they are loaded i.e. there are no package specifications. However, there are two features which can be set that will change the package into which ACT-R is loaded. If the ACT-R files have been compiled previously, then it will be necessary to also force the recompiling of the sources when changing the package into which they are loaded. Note that these options may not work properly in all systems – please contact Dan if you have any problems or questions with using the packaged ACT-R code.

Clean

The first option is to add the :clean-actr switch to the features list before loading. That will force the files to be loaded into the :cl-user package in most Lisps (the only exception is that in ACL with the IDE it will load them into the :cg-user package).

Packaged

The other option is to add the :packaged-actr switch to the features list. That will create a new package called :act-r when the load-act-r.lisp file is loaded and the ACT-R code will be loaded into that package. Nothing is exported from that package by the ACT-R code.

Requiring files

Files placed into the support directory of the distribution can be compiled and loaded when needed by using an ACT-R extension of the Lisp require function.

require-compiled

Syntax:

require-compiled lisp-module-name pathname -> [load-return-value | nil]

Arguments and Values:

lisp-module-name ::= a string containing the name of a Lisp module pathname ::= a string or pathname indicating the location of a .lisp file which provides the module load-return-value ::= a generalized boolean returned from calling the load command

Description:

The require-compiled function takes two parameters. The first is the Lisp module name string as would be passed to the require function (note this is not the same as an ACT-R module name) and the second is the pathname to the file to be loaded. Since the pathname can be anywhere this is not technically specific to the support directory of ACT-R, but of the ACT-R source code files only those in the support directory use the provide function to specify a module name for use in requiring.

The reason for using require-compiled compared to just loading the file directly is that require-compiled will only compile and load the file if it has not been loaded previously. That way one can specify that a particular support file is necessary in multiple files and only the first one will actually compile and load it. The differences between this and the Lisp require function is that this will

guarantee that the file is compiled instead of just being loaded and this requires the pathname instead of allowing a search in some implementation dependent location.

If the file is compiled and loaded the return value will be the one returned by that load. If it does not need to be compiled and loaded it will return **nil**.

To go along with the intended use of this command there is another logical host created when ACT-R is loaded called "ACT-R-support" which refers to the support directory of the current ACT-R source code tree.

Examples:

> (require-compiled "CENTRAL-PARAMETERS" "ACT-R-support:central-parameters")

Overall Software Design

The ACT-R software is composed of three major subsystems. From the perspective of the user, they operate together to implement "ACT-R", but it is worth noting that not everything in the software is a representation of elements of the ACT-R cognitive architecture.

The first subsystem is a discrete event simulation system which controls the timing and coordination of operations within ACT-R. It was designed to provide all of the support necessary to implement the current ACT-R theory, but is not itself a part of the theory. It defines the abstractions and tools which underlie the operations of the system, namely a <u>meta-process</u>, a <u>model</u>, a <u>module</u>, a <u>componenet</u>, a <u>buffer</u>, a <u>chunk</u> and a <u>parameter</u>. Some of those items are elements of the theory of ACT-R, for example buffers and chunks, but their specific implementation in the software is not prescribed by the theory.

The next subsytem is the RPC server which provides the remote interface for the system to interact with other software. This is not a component of the ACT-R cognitive architecture and is purely a construct for the software implementation. The RPC system will be referred to as the dispatcher. As part of providing the external interface the dispatcher is also used to coordinate the <u>output of the system</u> in a way that makes it available remotely. Many of the commands described in this manual are available remotely through the dispatcher. When that is the case, the remote name and any additional details needed will be described with the command. However, this document does not describe the operation of the underlying RPC system itself. That information is found in the document called remote in the docs directory.

The last subsystem is the set of modules that instantiate the theory of ACT-R. These modules contain the components that are used to model human cognition as described in the paper "Integrated Theory of the Mind" and the book "How Can the Human Mind Occur in the Physical Universe?". The actions and timing profiles generated by these modules when a model is run are the actual predictions of the theory. Anything else, for instance the actual time it takes the software to run the simulation, is not based on the theory. Those distinctions can be important so that the modeler appropriately differentiates what is a psychological claim of a model and what is just a consequence of the current software implementation.

Model files

Generally, when working with ACT-R one will generate text files that contain the description of a model which will be loaded into the ACT-R system. This is not the only way to develop models in ACT-R, but is by far the most typical usage.

An ACT-R model file is a text file of Lisp source code. It can be generated in any text editor. Because it will be loaded into Lisp it must be syntactically correct Lisp code. Thus, it can be useful to use an editor that helps with that. The editors built into the GUI based Lisp systems (like CCL on a Mac, LispWorks, or ACL with its IDE) are good choices if using such a Lisp, but if not, an editor like Emacs which has automatic Lisp indenting and parentheses matching can also help.

A typical model file will have the following structure:

```
(clear-all)
{supporting Lisp code}

(define-model model-name
   (sgp {parameter value}*)
   {chunk-type definitions}
   {initial chunks are defined}
   {productions are specified}
   {any additional model set-up commands}
   {additional model parameter settings}
)
```

The ACT-R commands shown above and the model components referenced (<u>chunk-types</u>, <u>chunks</u>, and <u>productions</u>) will be described in detail in later sections of this document, but for now here is a basic description of what the components of the model file do.

(clear-all)

The clear-all command completely resets ACT-R's state to a clean slate. This does not have to be the first thing in the file, but it should occur before defining any models.

{supporting Lisp code}

Since the model file will be loaded into ACT-R (which is running in Lisp) it can be convenient to also create the experiment/task for the model in Lisp along with the actual model, and sometimes one may also want to extend or modify the operation of the ACT-R system by providing support functions for things like generating similarity values dynamically.

- (define-model model-name

The define-model command is used to specify exactly what constitutes the components of the model and to give it a name for reference. Everything between the name specified for the model and the closing parenthesis of this command are considered the model's initial configuration. The commands are processed sequentially from left to right (which would be top down if spread over multiple lines as shown above).

- (sgp {parameter value}*)

The sgp command is used to set parameters that control the general operation of the system. This is typically the first command in the model's definition so that all of the conditions are properly set before anything else occurs.

- {chunk-type definitions}

Descriptions are given for declaring the configuration of slots that will be used in the chunks in the model.

{initial chunks are defined}

The initial chunks for the model are created and typically placed into the model's declarative memory.

{productions are specified}

The productions that control how the model will act are written here.

{any additional model set-up commands}

Any other commands necessary to configure components of the model or modules are specified.

- {additional model parameter settings}

Parameters for chunks and productions specified above are set.

-)

The define-model call is ended with a closing parenthesis.

Commands & Signals

This document will use the term commands to generally refer to the oprators that are available for using ACT-R. The commands described in this document will typically be functions, macros, or methods written in Lisp, but the term will also apply to operators which are made available from outside of Lisp through the dispatcher. Many of the ACT-R commands implemented in Lisp are also available from outside of Lisp through the dispatcher, but the external version of those commands may differ from the version available directly in Lisp. If a command makes a remote version available that will be noted in the description along with any differences in its use.

A subset of the commands available through the dispatcher do not perform any actions and only exist for monitoring purposes. Those commands are referred to as signals. There are many signals generated by the software, and they are used to indicate a variety of things both for the underlying software and for the operation of the running cognitive models. The signals will be described along with the other commands in the appropriate sections.

ACT-R Output

The output of ACT-R is coordinated through signals. All of the ACT-R output commands result in the generation of a signal with the corresponding output in a string. There are four output signals which can be monitored through the dispatcher for displaying the various types of ACT-R output. By default, all of the output signal strings are sent to *standard-output* for display in Lisp. That output can be disabled and reenabled using commands described below. The commands for generating output are described in a <u>later section</u>.

Commands & Signals

general-trace

Signal:

general-trace output-string

Arguments and Values:

output-string ::= a string containing output from an ACT-R command

Description:

The general-trace signal is used to provide ACT-R output which is not dependent upon there being a current model.

model-trace

Signal:

model-trace output-string

Arguments and Values:

output-string ::= a string containing output from an ACT-R command

Description:

The model-trace signal is used to provide ACT-R output from a model. That output is controlled by the <u>:v parameter</u> in the printing module for that model.

command-trace

Signal:

command-trace output-string

Arguments and Values:

output-string ::= a string containing output from an ACT-R command

Description:

The command-trace signal is used to provide ACT-R output from a model. That output is controlled by the <u>:cmdt parameter</u> in the printing module for that model.

warning-trace

Signal:

warning-trace output-string

Arguments and Values:

output-string ::= a string containing output from an ACT-R command

Description:

The warning-trace signal is used to provide ACT-R output which indicates a warning or error has occurred. Some warnings can be suppressed through the the <u>:model-warnings parameter</u> in the printing module for a model.

echo-act-r-output

Syntax:

echo-act-r-output -> name

Arguments and Values:

name ::= a string containing the name of the command which is used to monitor the output signals

Description:

The echo-act-r-output command is used to route all of the output generated by ACT-R to *standard-output* in Lisp. When it is called, first it removes any existing output signal monitors which were previously created by echo-act-r-output. Then it generates a new name for a command to use to print output to the current *standard-output*. That new command is then set to monitor all four of the

output signals: model-trace, command-trace, warning-trace, and general-trace. It returns the name of the command which it created.

Examples:

```
> (echo-act-r-output)
"G2354"
```

turn-off-act-r-output

Syntax:

turn-off-act-r-output -> [t, nil]

Arguments and Values:

none

Description:

The turn-off-act-r-output command is used to stop printing the output from ACT-R to *standard-output* in Lisp as enabled by echo-act-r-output. When it is called, it removes any output signal monitors which were previously created by echo-act-r-output. If there were output signal monitors then it returns **t** otherwise it returns **nil**.

Examples:

```
1> (turn-off-act-r-output)
T
2> (turn-off-act-r-output)
NIL
```

suppress-act-r-output

Syntax:

suppress-act-r-output form* -> result

Arguments and Values:

```
form ::= a Lisp form to be evaluated result ::= the return value from the last form evaluated
```

Description:

The suppress-act-r-output command can be used to temporarily disable the outputting of information through echo-act-r-output. It is a macro which can be wrapped around any number of Lisp forms to evaluate. While those forms are being evaluated any output which is created is not sent to *standard-output*, but the existing monitoring commands (if there are any) are not removed to do so. It returns the return value from the last form evaluated.

This is generally more efficient than turning off the output and then echoing it again for short blocks of code since the removal and then reinstating of the monitors is costly. However, for large blocks of code it may be more efficient to turn it off and then echo again since the monitoring function is still active during suppressed output and will be called even though it is not printing to *standard-output*.

Software Operation

The next several sections are going to discuss the operation and data structures of the underlying software. Although some of these are used to represent components of the ACT-R cognitive architecture e.g. chunks, the specific implemenation and operations of these items are not a part of the cognitive architecture itself. Thus, while the architecture says that delcarative knowledge is represted in chunks which contain slots and values, it does not say how those chunks are represented nor what sort of operators should be available for a modeler to work with them.

Meta-process

The operation of the discrete event simulation system is controlled primarily by a mechanism called the meta-process. The meta-process maintains the schedule of events, the simulation clock, the available models, and executes the events at the appropriate times when it is run. Currently, with this version of ACT-R, there is only one meta-process which is defined automatically when the software starts and it is not possible to create any others. [Note: some prior versions of ACT-R allowed for the creation of more than one meta-process and you may still see references to the "current meta-process" in this documentation. The single meta-process in this version of ACT-R will always be the current meta-process.]

The operation of the scheduling and running will be discussed in following sections. Here we will describe the high-level commands applicable to the meta-process.

Commands & Signals

clear-all

Syntax:

clear-all -> nil

Arguments and Values:

none

Description:

Clear-all restores ACT-R to its initial state:

- It generates the clear-all-start signal.
- It removes all currently defined models and their associated modules.
- It removes all events from the event queue and the waiting queue.
- It removes all event hooks which have been created.
- It sets the current simulation time to 0.
- It restores the default real time clock.
- It initializes all components which have been added.

In addition, the current binding of the Lisp variable *load-truename* is recorded for use by the reload command.

The typically usage of clear-all is to place it at the top of a model file to ensure that when the model is defined it starts with a clean system and that the <u>reload</u> command can be used.

Clear-all cannot be used while the meta-process is actively running, and doing so will result in the generation of a Lisp error which provides details on how to resolve that issue under the typical

situations where it can occur. **Examples:** > (clear-all) clear-all-start Signal: clear-all-start **Arguments and Values:** none **Description:** The clear-all-start signal is generated whenever the clear-all command starts to initialize the system, and there are no parameters associated with the signal. reset **Syntax:** reset -> [t | nil] **Remote command name:** reset **Arguments and Values:**

none

Description:

The reset command is used to clear the event queue and restore the current set of models and modules to their initial states (unlike <u>clear-all</u> which removes all of the models and modules).

- It generates a reset-start signal.
- It removes all events from the event queue and the waiting queue.
- It sets the current simulation time to 0.
- It resets all components, modules, and models.

The details of what happens when a model, module, and component are reset are described in the corresponding sections.

Reset cannot be used while the model is running and trying to do so will result in a warning being output to indicate that. If the reset completes successfully then it will return **t** (Lisp) or **true** (remote) otherwise it will return **nil** (Lisp) or **null** (remote).

Examples:

```
> (reset)
T
E> (reset)
#|Warning: Top-level-lock unavailable. Reset cannot be used. |#
NTI
```

reset-start

Signal:

reset-start

Arguments and Values:

none

Description:

The reset-start signal is generated whenever the reset command starts to reset the system, and there are no parameters associated with the signal.

reload

Syntax:

```
reload {compile?} -> [load-return-value | :none]
```

Remote command name:

reload

Arguments and Values:

compile? ::= a generalized boolean indicating whether or not to compile the file load-return-value ::= a generalized boolean returned from calling the load command

Description:

The reload command calls the Lisp load command to load the file recorded during the last call to the <u>clear-all</u> command. It is provided as a shortcut for loading a model file that has been edited. If the compile? parameter is specified with a true value and that file has a type of "lisp" it will be compiled before loading. If the compile? parameter is specified as true but the recorded file is not of type "lisp" then it is not compiled, a warning is printed, and the file is just loaded.

If there is no file recorded by clear-all then no file is loaded and the keyword **:none** is returned. Reload cannot be used while the system is running. If there are any errors generated during the reloading of the model they will be automatically handled and the error messages printed as warnings. There may be additional information printed in warnings even for a successful load because all output to Lisp *standard-output* and *standard-error* during the load will be captured and printed in warnings.

If the reload completes successfully it will return a true value, otherwise it will return **nil**.

```
> (reload)
T
> (reload)
#|Warning: Non-ACT-R messages during load of #P"C:demo-model.lisp":
; Loading C:demo-model.lisp

|#
T
> (reload t)
#|Warning: To use the compile option the pathname must have type lisp. |#
; Loading C:\model.txt
T

E> (reload)
#|Warning: No model file recorded to reload. |#
:NONE
```

mp-time

Syntax:

mp-time -> current-time

Remote command name:

mp-time

Arguments and Values:

current-time ::= a number representing the current simulation time in seconds

Description:

Mp-time returns the current time of the meta-process in seconds.

This is generally used for two purposes, either debugging a model or collecting response time data from a model.

Examples:

```
> (mp-time)
0.3
```

mp-time-ms

Syntax:

mp-time-ms -> current-time

Remote command name:

mp-time-ms

Arguments and Values:

current-time ::= a number representing the current simulation time in milliseconds

Description:

Mp-time-ms returns the current time of the meta-process like mp-time. The difference is that mp-time-ms returns the time as an integer count of milliseconds.

```
> (mp-time-ms)
```

mp-print-versions

Syntax:

mp-print-versions -> nil

Remote command name:

mp-print-versions

Arguments and Values:

none

Description:

Mp-print-versions outputs using the <u>general-trace</u> the <u>specific version number of the ACT-R software</u> with a tag indicating whether the code is an <u>official release or an internal version checked out of the source repository</u> followed by the name, version number, and documentation string of each of the <u>components</u> and <u>modules</u> which is currently defined in the system. It always returns **nil**.

```
> (mp-print-versions)
ACT-R 7 Version Information:
Software
                    : 7.6.2-<internal>
_____
Components
             : 5.0
                           Manager for the AGI windows
                           Maintains a table of chunk-specs for remote use
CHUNK-SPEC
              : 3.0
HISTORY-RECORDER: 1.0
                           Maintain the tables of defined history recorders and state ...
KEYBOARD-TABLE : 2.0
                           Record the keyboards used for each model.
MOUSE-TABLE
              : 2.0
                           Record the mouse devices that are used.
NAMING
               : 2.0
                           Provides new symbol generation for the system.
                           Component for recording trace information
TRACE-HISTORY
               : 1.0
_____
Modules
AUDICON-HISTORY
                   : 3.0
                                Module to record audicon changes.
                    : 5.1
                                A module which gives the model an auditory attentional ...
AUDIO
BOLD
                    : 4.0
                                A module to produce BOLD response predictions from ...
                                Module to record buffer change history.
BUFFER-HISTORY
                    : 2.0
BUFFER-PARAMS
                    : 1.0
                                Module to hold and control the buffer parameters
BUFFER-TRACE
                    : 3.0
                                A module that provides a buffer based history mechanism.
CENTRAL-PARAMETERS
                    : 1.2
                                a module that maintains parameters used by other modules
                                The declarative memory module stores chunks from the ...
DECLARATIVE
                    : 5.1
                    : 4.0
                                The device interface for a model
DEVICE
                    : 2.1
GOAL
                                The goal module creates new goals for the goal buffer
                                Module to support the saving and accessing of ...
HISTORY-RECORDER
                    : 2.0a1
IMAGINAL
                    : 4.0
                                The imaginal module provides a goal style buffer with ...
MOTOR
                    : 4.0
                                Module to provide a model with virtual hands
```

NAMING-MODULE :	2.0	Provides safe and repeatable new name generation for
PRINTING-MODULE :	1.3	Coordinates output of the model.
PROCEDURAL :	5.0	The procedural module handles production definition
PRODUCTION-COMPILATION:	2.0	A module that assists the primary procedural module
PRODUCTION-HISTORY :	2.0	Module to record production history for display in
RANDOM-MODULE :	1.0	Provide a good and consistent source of pseudorandom
RETRIEVAL-HISTORY :	2.0	Module to record retrieval history data.
SPEECH :	5.1	A module to provide a model with the ability to speak
STEPPER :	1.0	Store the model specific information for the
TEMPORAL :	2.1	The temporal module is used to estimate short time
UTILITY :	4.0	A module that computes production utilities
VISICON-HISTORY :	3.0	Module to record visicon changes.
VISION :	6.0	A module to provide a model with a visual attention system
NIL		·

Events

As indicated in the description of the meta-process, the simulation system for ACT-R is implemented using discrete events. The system runs by executing a sequence of events each occurring at a specific simulated time. Effectively, every action of the model is performed by an event in the system, and the model's trace when it runs is a printing of those events as they occur.

Each event consists of the time at which it should occur, an indication of which, if any, module created the event, and an action to perform. There are some additional details and capabilities of events (like the ability to have them wait for some other action to occur instead of having a prespecified time) and those will be described in the section on <u>creating events</u>. This section will only describe the commands for inspecting the events which exist in the current meta-process.

Commands

mp-show-queue

Syntax:

mp-show-queue {indicate-traced} -> event-count

Remote command name:

mp-show-queue

Arguments and Values:

indicate-traced ::= a generalized boolean indicating whether to mark events that will occur in the trace event-count ::= a number indicating how many items are in the event queue

Description:

Mp-show-queue outputs a line of text that says "Events in the queue:" followed by all of the events that are on the event queue in the order that they will be executed using the general-trace output signal. If the indicate-traced value is provided and is non-nil then the character "*" will be displayed before the events which will be displayed in the trace with the current parameter settings for the associated model. It returns the number of events in the queue.

This command can be useful for debugging a model as well as when working on creating modules and experiments which generate events.

Examples:

```
> (mp-show-queue)
Events in the queue:
     0.000
             NONE
                                     CHECK-FOR-ESC-NIL
     0.000
             GOAL
                                     SET-BUFFER-CHUNK GOAL FREE NIL
     0.000
             PROCEDURAL
                                     CONFLICT-RESOLUTION
     0.000
                                     CLEAR-DELAYED-GOAL
             GOAL
4
> (mp-show-queue t)
Events in the queue:
      0.000
              NONE
                                      CHECK-FOR-ESC-NIL
                                      SET-BUFFER-CHUNK GOAL FREE NIL
      0.000
              GOAL
              PROCEDURAL
      0.000
                                      CONFLICT-RESOLUTION
      0.000
              GOAL
                                      CLEAR-DELAYED-GOAL
```

mp-queue-text

Syntax:

mp-queue-text {indicate-traced} -> events-string

Remote command name:

mp-queue-text

Arguments and Values:

indicate-traced ::= a generalized boolean indicating whether to mark events that will occur in the trace events-string ::= a string containing the printed event details

Description:

Mp-queue-text generates a string containing the printed form of all of the events that are on the event queue in the order that they will be executed. If the indicate-traced value is provided and is non-**nil** then the character "*" will be included before the events which will be displayed in the trace with the current parameter settings for the associated model. That generated string is returned.

```
> (mp-queue-text)
      0.000
              NONE
                                       CHECK-FOR-ESC-NIL
     0.000
             GOAL
                                      SET-BUFFER-CHUNK GOAL FREE NIL
             PROCEDURAL PROCEDURAL
     0.000
                                      CONFLICT-RESOLUTION
     0.000
             GOAL
                                      CLEAR-DELAYED-GOAL
  (mp-queue-text t)
       0.000
               NONE
                                        CHECK-FOR-ESC-NIL
      0.000
               GOAL.
                                       SET-BUFFER-CHUNK GOAL FREE NIL
      0.000
               PROCEDURAL
                                       CONFLICT-RESOLUTION
      0.000
               GOAL
                                       CLEAR-DELAYED-GOAL
```

mp-queue-count

Syntax:

mp-queue-count -> event-count

Remote command name:

mp-queue-count

Arguments and Values:

event-count ::= a number indicating how many items are in the event queue

Description:

Mp-queue-count returns the number of events which are currently in the queue of the meta-process.

Examples:

```
> (mp-queue-count)
4
```

mp-show-waiting

Syntax:

mp-show-waiting -> event-count

Remote command name:

mp-show-waiting

Arguments and Values:

event-count ::= a number indicating how many items are in the waiting queue

Description:

Mp-show-waiting outputs all of the events that are on the waiting queue of the meta-process to the general-trace along with the description of the condition for which it is waiting to occur to be added to the main event queue. The first element in the waiting description indicates whether it is waiting for any event or a particular module. If it is waiting on a module then the second element indicates which module. The last element of the description indicates whether a maintenance event will satisfy the condition. It returns the number of events that are in the waiting queue.

This command can be useful for debugging, but is generally more important when working on creating modules and experiments than when debugging a model.

Examples:

mp-modules-events

Syntax:

mp-modules-events module-name -> event-list

Arguments and Values:

```
module-name ::= a symbol which should be the name of a module event-list ::= a list of events scheduled for the named module
```

Description:

Mp-modules-events returns a list of all of the events from both the regular and waiting queues of the meta-process which have a module specified that matches the module-name provided. The elements of the list are the actual event structures which should only be accessed with the commands described in the event accessors section.

This command does not currently have a remote version.

```
> (mp-modules-events 'procedural)
(#S(ACT-R-EVENT ...))
> (mp-modules-events 'not-a-module)
NIL
```

Component

A component is a software construct used to build the system that implements the ACT-R theory, but which has no basis in the theory. A component is a data structure which is instantiated once in the software and can provide commands which will be called automatically when <u>clear-all</u>, <u>reset</u>, <u>model definition</u>, and <u>model deletion</u> occur. Currently, the interface for creating and working with components is not a supported mechanism.

Module

Module is an overloaded term in ACT-R (ignoring the many uses of the term outside of ACT-R). Within ACT-R it has different connotations when talking about the software and the theory. At the software level a module is a part of the system which gets instantiated for each model that is defined. It can serve any number of purposes, for instance there is a printing module, a pseudorandom number generator module, as well as a vision module, a declarative memory module and many others. Each module is essentially an independent structure, and it is the modules which provide the functionality for a model. There are basically no restrictions on what a software module can do and adding new modules is the primary way of extending or modifying the overall system.

From the theory perspective however a module is a reference to some cognitive faculty which can typically be ascribed to a particular region of the brain. Thus, something like the printing module in the software obviously would not be considered a module of the theory. To further complicate the issue, the implementation of the cognitive modules as software modules is not always one-to-one. For example, the vision system of ACT-R, which is implemented in the software as one module, is probably more appropriately considered as two cognitive modules – one for location information and one for object information. In the other direction, the theory's procedural module is actually implemented as three modules in the software (one that controls production definition and matching, one to handle the utility computations, and one to implement the production compilation mechanism).

Often the context in which one encounters "module" with respect to ACT-R makes it clear what is being discussed (the software or the theory) so it is not always as confusing as it might seem. For clarity, from this point on in the manual, when it says module, the reference will always be to the software modules unless explicitly stated otherwise.

Each of the specific modules of the ACT-R software will be described in its own section of this manual. There will also be sections describing the mechanisms which can be used in a module, like <u>buffers</u> and <u>parameters</u>, as well as <u>how to implement a new module</u>. This section will only include the command for getting the names of all the currently defined modules.

Commands

all-module-names

Syntax:

all-module-names -> (module-name*)

Arguments and Values:

module-name ::= a symbol which names a module in the system

Description:

All-module-names returns a list of the names of the currently defined modules in the system in alphabetical order. There is no remote version of this command.

```
> (all-module-names)
(:AUDICON-HISTORY :AUDIO BOLD BUFFER-HISTORY BUFFER-PARAMS BUFFER-TRACE ...)
```

Buffers

Buffers in ACT-R are the interfaces between modules. Each buffer is connected to a specific module and has a unique name by which it is referenced e.g. the goal buffer or the retrieval buffer which are associated with the goal and declarative modules respectively. A buffer is used to relay requests for actions to its module, to query its module about the module's state, it can hold one chunk which is visible to all other modules, and it will respond directly to queries about the contents of the buffer itself.

A module will respond to a query through its buffer with a generalized-boolean indicating the result. In response to a request, the module will usually generate one or more events to perform some action(s) and may place a chunk into the buffer to indicate the result of that action. Any module may access or modify the chunk in any buffer at any time, but typically a module will only manipulate its own buffer(s).

The buffer itself responds to five queries all specified with the name buffer and the possible values: empty, full, failure, requested, and unrequested. Each query will return **t** if the condition is true and **nil** if it is false. The first three query values, empty, full, and failure, are determined based on whether there is a chunk in the buffer and whether or not the failure flag for the buffer has been set. Only one of those queries will be true at a time. If the buffer contains a chunk then full will be true. If the failure flag has been set then failure will be true (it is not possible to set the failure flag if there is a chunk in the buffer). If neither of those is true then empty will be true. The other two queries indicate whether the chunk which is in the buffer or the failure flag, if it is set, was the result of a request or not. The determination of whether a chunk or failure flag in the buffer was the result of a request is determined by the call to the function which sets that item (see the <u>Using Buffers</u> section for details). If there is no chunk in the buffer and the failure flag is not set then both of those queries will be false.

An important thing to note is that when a chunk is placed into a buffer the buffer makes a copy of that chunk which it then makes available. Any changes made to the chunk in the buffer only affect the copy that it holds – they do not affect the original chunk from which it was copied.

One of the current research areas with ACT-R is in using the buffers to track the activity of their associated modules and then comparing that activity to data from neruoimaging studies (fMRI, MEG, or EEG) to find correlations between regions of the brain and particular buffer/module activity in

ACT-R models. Thus providing a mechanism for mapping cognitive modeling work onto actual brain regions and even being able to make predictions about where activation should show up in future neruoimaging research. Details on how that is done can be found in the <u>Module Activity and Brain Predictions section</u>.

The commands described here provide general information about buffers which is most often needed for modeling in ACT-R. The <u>Using Buffers</u> section describes the commands one can use for more low-level interaction with the buffers which would be necessary for creating a new module.

Commands

buffers

Syntax:

buffers {sorted} -> (buffer-name*)

Remote command name:

buffers

Arguments and Values:

sorted ::= a generalized boolean indicating whether to sort the list of names buffer-name ::= a symbol which is the name of a currently existing buffer

Description:

The buffers command will return a list with the names of all the currently defined buffers. If the sorted parameter is provided with a non-nil value then the list will be in alphabetical order otherwise it will be in no particular order.

Examples:

```
> (buffers)
(RETRIEVAL IMAGINAL MANUAL GOAL IMAGINAL-ACTION VOCAL AURAL PRODUCTION VISUAL-LOCATION
AURAL-LOCATION TEMPORAL VISUAL)
> (buffers t)
(AURAL AURAL-LOCATION GOAL IMAGINAL IMAGINAL-ACTION MANUAL PRODUCTION RETRIEVAL TEMPORAL
```

buffer-chunk

VISUAL VISUAL-LOCATION VOCAL)

Syntax:

```
buffer-chunk buffer-name* -> [((buffer-name {chunk-name})*) | ([chunk-name | :error]*) | nil]
buffer-chunk-fct (buffer-name*) -> [((buffer-name {chunk-name})*) | ([chunk-name | :error]*) | nil]
```

Remote command name:

buffer-chunk

Arguments and Values:

```
buffer-name ::= a symbol that names a buffer chunk-name ::= a symbol that names a chunk
```

Description:

Generally, the buffer-chunk command prints out the names of buffers along with the chunks those buffers hold in the current model using the <u>command-trace</u>.

If no buffer names are specified, then it prints all the buffers and the chunk name of the chunk in that buffer (or **nil** if the buffer is empty) one per line to the <u>command-trace</u> and returns a list of lists where the first element of each sublist is the name of a buffer and if the buffer holds a chunk there will be a second element in the list containing the name of that chunk.

If specific buffers are provided, then for each of those buffers, in the order provided, it prints the buffer name followed by the name of the chunk in that buffer (or **nil** if the buffer is empty) and if there is a chunk in the buffer that chunk is also printed. In this case it returns a list of the names of the chunks in the buffers provided in the same order as they were specified in the call. If an invalid buffer name is provided the corresponding value in the return list will be the keyword **:error** and nothing will have been printed.

If there is no current model then a warning is printed and **nil** is returned.

The remote version of the command takes parameters in the same way as the macro buffer-chunk – any number of buffer names.

Examples:

These examples (except for the final error example) were generated after running the count model in unit 1 of the tutorial like this:

```
1> (actr-load "ACT-R:tutorial;unit1;count.lisp")
T
```

```
2> (run 1)
                                      SET-BUFFER-CHUNK GOAL FIRST-GOAL NIL
     0.000
             GOAL
     0.300
            -----
                                      Stopped because no events left to process
0.3
50
NIL
> (buffer-chunk)
RETRIEVAL: E-0 [E]
IMAGINAL: NIL
MANUAL: NIL
GOAL: NIL
IMAGINAL-ACTION: NIL
VOCAL: NIL
AURAL: NIL
PRODUCTION: NIL
VISUAL-LOCATION: NIL
AURAL-LOCATION: NIL
TEMPORAL: NIL
VISUAL: NIL
((RETRIEVAL E-0) (IMAGINAL) (MANUAL) (GOAL) (IMAGINAL-ACTION) (VOCAL) (AURAL) (PRODUCTION) (VISUAL-LOCATION) (AURAL-LOCATION) ...)
> (buffer-chunk-fct '(retrieval goal))
RETRIEVAL: E-0 [E]
E-0
   FIRST 4
   SECOND 5
GOAL: NIL
(E-0 NIL)
E> (buffer-chunk-fct '(bad-buffer-name))
(:ERROR)
E> (buffer-chunk retrieval bad-name goal)
RETRIEVAL: E-0 [E]
E-0
   FIRST 4
   SECOND 5
GOAL: NIL
(E-0 :ERROR NIL)
E> (buffer-chunk)
#|Warning: buffer-chunk called with no current model. |#
NIL
printed-buffer-chunk
```

Syntax:

printed-buffer-chunk buffer-name* -> [output-string | nil]

Remote command name:

printed-buffer-chunk

Arguments and Values:

```
buffer-name ::= a symbol that names a buffer output-string ::= a string containing the output of the corresponding buffer-chunk
```

Description:

The printed-buffer-chunk command works like the buffer-chunk command except that it does not print the information to the <u>command-trace</u> and instead of returning the list of chunks or buffers and chunks it returns a string containing the output that buffer-chunk would have sent to the <u>command-trace</u>.

Examples:

These examples (except for the final error example) were generated after running the count model in unit 1 of the tutorial like this:

```
1> (actr-load "ACT-R:tutorial;unit1;count.lisp")
2> (run 1)
                                    SET-BUFFER-CHUNK GOAL FIRST-GOAL NIL
    0.000
             GOAL
    0.300
                                    Stopped because no events left to process
             -----
0.3
50
NIL
> (printed-buffer-chunk)
"RETRIEVAL: E-0 [E]
IMAGINAL: NIL
MANUAL: NIL
GOAL: NIL
IMAGINAL-ACTION: NIL
VOCAL: NIL
AURAL: NIL
PRODUCTION: NIL
VISUAL-LOCATION: NIL
AURAL-LOCATION: NIL
TEMPORAL: NIL
VISUAL: NIL
> (printed-buffer-chunk 'retrieval 'goal)
"RETRIEVAL: E-0 [E]
E-0
  FIRST 4
  SECOND 5
GOAL: NIL
E> (printed-buffer-chunk 'bad-buffer-name)
E> (printed-buffer-chunk)
#|Warning: printed-buffer-chunk called with no current model. |#
NİL
```

buffer-status

Syntax:

```
buffer-status buffer-name* -> [ ([buffer-name | :error]*) | nil]
buffer-status-fct (buffer-name*) -> [ ([buffer-name | :error]*) | nil]
```

Remote command name:

buffer-status

Arguments and Values:

buffer-name ::= a symbol that names a buffer

Description:

The buffer-status command prints the current values for the possible queries to which the buffers and their modules respond from the current model using the <u>command-trace</u>. For each buffer specified (or all buffers if none are specified) the buffer name is printed followed by the current result of the buffer's queries and the required module queries, one per line, indicating **t** for a true query and **nil** for a false result. That is followed by any module specific status the module prints (the module specific status is not constrained by the system and could be any type of output). It returns a list of the buffer names of the buffers for which the status was printed.

If specific buffers are provided, and an invalid buffer name is specified, the corresponding value in the return list will be the keyword **:error** and nothing will have been printed.

If there is no current model then a warning is printed and **nil** is returned.

The remote version of the command uses the same syntax as the buffer-status macro.

```
> (buffer-status)
RETRIEVAL:
  buffer empty
                        : T
  buffer full
                        : NIL
  buffer failure
                        : NIL
  buffer requested
                        : NIL
  buffer unrequested
                        : NIL
  state free
  state busy
                        : NIL
  state error
  recently-retrieved nil: NIL
  recently-retrieved t
IMAGINAL:
  buffer empty
                        : T
  buffer full
                        : NIL
  buffer failure
                        : NIL
                        : NIL
  buffer requested
  buffer unrequested
                        : NIL
```

```
state free : T
state busy : NIL
state error : NTI
  state error
                                  : NIL
MANUAL:
  buffer empty : T
buffer full : NIL
buffer failure : NIL
buffer requested : NIL
buffer unrequested : NIL
state free : T
 state bus,
state error
preparation free : I
preparation busy : NIL
processor free : T
busy : NIL
: T
                                  : NIL
                                  : T
  execution busy
                                : NIL
: NONE
  last-command
 (RETRIEVAL IMAGINAL MANUAL VISUAL AURAL PRODUCTION VOCAL ...)
> (buffer-status goal)
GOAL:
  buffer empty
  buffer full
                                  : NIL
  buffer full : NIL
buffer failure : NIL
buffer requested : NIL
buffer unrequested : NIL
state free : T
  state busy
                                 : NIL
  state error
                            : NIL
(GOAL)
> (buffer-status-fct '(retrieval))
RETRIEVAL:
 butter empty : T
buffer full : NIL
buffer failure : NIL
buffer requested : NIL
buffer unrequested : NIL
state free : T
state busy : NT
                        : NIL
: NIL
  state error
  recently-retrieved nil: NIL
  recently-retrieved t : NIL
(RETRIEVAL)
E> (buffer-status goal non-buffer)
GOAL:
  buffer empty
                                    : T
  buffer full : NIL
buffer failure : NIL
buffer requested : NIL
buffer unrequested : NIL
                                  : T
  state free
  state busy
                                  : NIL
  state error
                                  : NIL
 (GOAL : ERROR)
E> (buffer-status)
#|Warning: buffer-status called with no current model. |#
```

printed-buffer-status

Syntax:

printed-buffer-status buffer-name* -> [output-string | nil]

Remote command name:

printed-buffer-status

Arguments and Values:

```
buffer-name ::= a symbol that names a buffer output-string ::= a string containing the output of the corresponding buffer-chunk
```

Description:

The printed-buffer-status command works like the buffer-status command except that it does not print the information to the <u>command-trace</u> and instead of returning the list of buffers it returns a string containing the output that buffer-status would have sent to the <u>command-trace</u>.

```
> (printed-buffer-status)
"RETRIEVAL:
  buffer empty
                                  : T
  buffer full : NIL
buffer failure : NIL
buffer requested : NIL
buffer unrequested : NIL
state free : T
  state busy
                                : NIL
  state error
  recently-retrieved nil: NIL
  recently-retrieved t : NIL
IMAGINAL:
 unter full : NIL
buffer failure : NIL
buffer requested
buffer unrequest
state
  buffer unrequested : NIL state free
  state free
  state busy
                                 : NIL
  state error
                                 : NIL
 buffer full : NIL buffer failure : NIL buffer requested : NTI buffer unrequest
MANUAL:
  state free
                                : T
  state busy
state error
preparation free
preparation busy
                                : NIL
                                : NIL
                                : T
                               : NIL
  processor free
                                 : T
  processor busy
                                 : NIL
```

```
execution free : T
execution busy : NIL
last-command : NONE

""

> (printed-buffer-status goal)
"GOAL:
buffer empty : T
buffer full : NIL
buffer failure : NIL
buffer requested : NIL
buffer unrequested : NIL
state free : T
state busy : NIL
state error : NIL"

E> (printed-buffer-status)
#|Warning: printed-buffer-status called with no current model. |#
NIL
```

Models

An ACT-R model is one simulated cognitive agent. Theoretically the software can have any number of models defined simultaneously (practically there is a limit that will depend on the hardware and Lisp software). All of the defined models will be run at the same time by the meta-process. However, the most common usage of ACT-R is to work with only one model at a time. Most of this manual assumes that one is working with only one model at a time. Information about dealing with more than one model simultaneously is covered in the <u>multiple models</u> section.

A model is referenced by the name specified when it is defined, and that name must be unique. A model consists of the code specified in its definition, an instance of each module in the system (which is independent of any other model's copy of that module unless a specific module indicates otherwise), and its set of chunks (which are always independent of the chunks of any other model).

A model is created using the define-model command which specifies the model's name and its initial conditions and results in the creation of a new instance of each module for that model to use.

Specifically, when a model is created the following sequence of actions occur:

- A new instance of each module is created for that model
- The default <u>chunk-types</u> and <u>chunks</u> are created
- All of the buffers for that model are set to empty
- The model's modules have their primary reset functions called (in no specific order)
- The parameters of all the model's modules are set to their default values (in no specific order)
- The model's modules have their secondary reset functions called (in no specific order)
- The model's definition code is evaluated in the order given (left to right)
- The model's modules have their tertiary reset functions called (in no specific order)

When a model is reset a similar sequence of actions occurs. The difference is that new module instances are not created and instead any chunks and chunk-types in the model are deleted first.

Regardless of how many models are defined, only one is accessible at any given time. This is referred to as the current model. Only the current model may be manipulated or inspected by the ACT-R commands. If there is only one model defined, then it will be the current model. If there is

more than one model defined, then it is up to the modeler to specify which is current before executing any commands (see the multiple models section for more details).

Commands

define-model

Syntax:

```
define-model model-name {model-code*} -> [model-name | nil]
define-model-fct model-name ({model-code*}) -> [model-name | nil]
```

Arguments and Values:

```
model-name ::= a symbol that will be the name of the model model-code ::= a Lisp expression that will be evaluated when the model is created and when it is reset
```

Description:

The define-model command creates a new model with the given model-name. Its initial conditions are specified by the model-code provided.

If there is not already a model by that name and there are no errors in evaluation of the model-code forms then the new model is created and model-name is returned.

If the model-name is already the name of a defined model or an error occurs during the evaluation of the model-code then a warning is printed and **nil** is returned.

Examples:

Only basic usage of define-model is shown here – see the tutorial for definition of actual cognitive models that perform meaningful tasks.

```
> (define-model-fct 'model-10 (list '(chunk-type start slot)))
MODEL-10

1> (define-model model-1 (chunk-type goal state))
MODEL-1

2E> (define-model-fct 'model-1 nil)
#|Warning: MODEL-1 is already the name of a model in the current meta-process. Cannot be redefined. |#
NIL

E> (define-model model-3 (pprint "start") (pprnt "end"))
"start"
#|Warning: Error encountered in model form:
```

```
(PPRNT "end")
Invoking the debugger. |#
#|Warning: You must exit the error state to continue. |#
Debug: attempt to call `PPRNT' which is an undefined function.
[condition type: UNDEFINED-FUNCTION]
#|Warning: Model MODEL-3 not defined. |#
NTI
```

delete-model

Syntax:

```
delete-model {model-name} -> [t | nil]
delete-model-fct model-name -> [t | nil]
```

Arguments and Values:

model-name ::= a symbol that should be the name of a model

Description:

The delete-model command removes the model with the specified model-name. If model-name is not provided the current model is deleted. Deleting a model removes all events generated by that model from the event queues, deletes each of the model's instances of the modules, and removes the model from the set of models currently defined. If a model is successfully deleted then **t** is returned.

If model-name is not the name of a currently defined model or no model-name is given and there is no current model, then a warning is printed and **nil** is returned.

The delete-model command is typically only useful when working with multiple models.

```
> (delete-model)
T
> (delete-model-fct 'model)
T
E> (delete-model)
#|Warning: No current model to delete. |#
NIL
E> (delete-model-fct 'model)
#|Warning: No model named MODEL in current meta-process. |#
NIL
```

Chunks & Chunk-types

Chunks are the elements of declarative knowledge in the ACT-R theory and are used to communicate information among modules through the buffers. A chunk consists of a set of named slots each holding a single value. A chunk also has a name which is used to reference it, however, the name is not considered to be a part of the chunk itself from a theoretical standpoint. Previous versions of ACT-R also required each chunk to have a specific chunk-type associated with it that defined the set of slots which it had. As of ACT-R 6.1 chunks are no longer cast into specific types. A chunk may have any combination of slots desired without having to first specify an appropriate type, and a chunk may also now have slots removed as well as added. Chunk-types still exist as a potentially useful tool for users, but they are no longer a required component of chunks.

In the ACT-R software, chunks exist at the "model level" and may be created and used by any module or additional code – they do not have to be associated with a model's declarative memory module unlike older versions of ACT-R (those prior to 6.0). In addition to the slots and values of a chunk, in the software each chunk also maintains a set of parameters which contain additional information needed by the modules or the modeler. A modeler may add chunk parameters for recording additional information as needed. See the section on extending chunks for more information on adding and manipulating chunk parameters. Along with the parameters, there is an additional feature associated with a chunk in the ACT-R software which indicates whether the slots and values of the chunk can be modified or not. When a chunk is created it is initially able to have its content modified, but the modeler (or a module) may mark a chunk as "immutable" at any point after it has been created. Once a chunk is marked as immutable it cannot be changed back to modifiable. The final thing to note about chunks is that they should always be referenced by their name and only manipulated through the provided mechanisms – the underlying representation of a chunk in the code is not considered to be part of the ACT-R software's API.

Chunk-types in ACT-R are used as a pre-processing mechanism in the definition of a model. A chunk-type associates a name with a set of slots and optional default values for those slots. That chunk-type name may then be used when creating chunks and specifying productions to indicate the slots which are intended and to include the default slot values from that chunk-type for any slots not specified in the chunk or production. The chunk-type name itself does not get recorded in the model with the chunk or production it is used in – it only serves as a declaration which will be used to provide warnings if the chunk or production does not conform to the chunk-type indicated and to fill in any default slot values from that chunk-type. If a chunk-type does not include default values for its

slots then whether it is specified or not in the creation of a chunk or production will not affect the resulting item – it will be the same with or without the chunk-type specification.

When creating chunk-types they may be organized into a hierarchy, with new chunk-types inheriting slots from one or more parent chunk-types. If a chunk-type is created with one or more parent chunk-types then that new type will include all the slots and default values from all of the parent chunk-types along with those specified in the new chunk-type. A default value specified for a slot directly in a chunk-type overrides any default value which would be inherited from a parent type. If multiple parent chunk-types specify a default value for the same slot then unless those default values are all the same such a chunk-type cannot be created. When specifying a chunk-type in creating a chunk or production a parent type may be specified and use any of the slots specified for the children of that chunk-type, but only the default values for the specific chunk-type named will be applied.

Default Chunk-types

There are a few chunk-types created with every model automatically. Those are, chunk, constant-chunks, query-slots, and clear. These are used to create some of the default chunks for the model and may be used freely in creating additional chunks or productions. Many of the provided modules also specify new chunk-types which may be used and those will be indicated with the module description.

chunk

The chunk-type named chunk has no slots specified for it. Its purpose is to serve as the root of the chunk-type hierarchy i.e. all chunk-types which are created implicitly inherit from the chunk-type named chunk.

constant-chunks

The constant-chunks chunk-type specifies one slot named name.

query-slots

The query-slots chunk-type specifies three slots named state, buffer, and error. Those are the names of the queries which all buffers will respond to and by creating a chunk-type with those slot names one can create chunk-specs which use those slots to perform queries from code.

clear

The clear chunk-type has one slot named clear which has a default value of t. It is provided as a convenient and consistent mechanism for use when creating a module which needs to provide a request which performs some sort of "clearing" of the module.

Default Chunks

There are several chunks created for each model automatically which may be used as needed. All of these default chunks are marked as immutable. There will also be many chunks created by the provided modules and the details of those can be found in the specific module sections.

Chunks named free, busy, error, empty, full, failure, requested, and unrequested are created each with a slot named name that is set to the chunk's name i.e. the chunk named free has one slot called name with the value free.

A chunk named clear is created having one slot named clear with a value of t.

Commands

The commands described here are general chunk and chunk-type actions which can be used for any chunk. Some modules provide additional commands for manipulating or inspecting the chunks that are being used by that module and the details of those commands can be found in the specific module sections.

Chunk-type Commands

chunk-type

Syntax:

```
chunk-type { [new-name | (new-name (:include parent-name)*) ] {doc-string} [slot-name | (slot-name default-value)]*} -> [ type-name | (type-name*) | nil ]
```

```
chunk-type-fct [ nil | ( [new-name | (new-name (:include parent-name)<sup>+</sup>) ] {doc-string} [slot-name | (slot-name default-value)]<sup>*</sup>) ] -> [ type-name | (type-name*) | nil ]
```

Arguments and Values:

```
new-name ::= a symbol that is to be the name of the new chunk-type
type-name ::= a symbol that is the name of a chunk-type
parent-name ::= a symbol that names a chunk-type to be a parent type of this new chunk-type
doc-string ::= a string that is used as documentation for this chunk-type
slot-name ::= a symbol that names a slot which will be part of this chunk-type
```

default-value ::= any Lisp value which specifies the value that will be used as the default value for the corresponding slot-name

Description:

The chunk-type command creates a new chunk-type for the current model or displays all of the currently defined chunk-types for the current model.

If no parameters are passed to the chunk-type command (or **nil** to the function) then all of the existing chunk-types in the current model are printed to the <u>command-trace</u> as described by <u>pprint-chunk-type</u> and a list of their names is returned (in no particular order).

If a valid chunk-type specification is provided then a new chunk-type is created for the current model and the name of that chunk-type is returned. If the chunk-type provides the same specification as an existing chunk-type in the model then a warning will be displayed.

If there is no current model, the given new-name already names an existing chunk-type in the current model, or there is an error in the specification of the chunk-type then a warning is printed and **nil** is returned.

```
> (chunk-type)
SOUND
  KIND
  CONTENT
  EVENT
AUDIO-COMMAND
MOVE-CURSOR <- MOTOR-COMMAND
  OBJECT
  LOC
   DEVICE
(SOUND AUDIO-COMMAND MOVE-CURSOR ...)
1> (chunk-type goal slot1 state)
GOAL
2> (chunk-type-fct '(other-type slot1 slot2))
OTHER-TYPE
3> (chunk-type (subgoal1 (:include goal)) new-slot)
SUBGOAL1
4> (chunk-type-fct '((subgoal2 (:include goal) (:include other-type))))
```

```
SUBGOAL2
5> (chunk-type new-type (slot default-value) (other-slot 4))
NEW-TYPE
6> (chunk-type detailed-type "The chunk-type detailed-type" slot)
DETAILED-TYPE
7> (chunk-type-fct nil)
GOAL
   SL0T1
  STATE
OTHER-TYPE
  SL0T1
   SL0T2
SUBGOAL1 <- GOAL
  NEW-SLOT
  SL0T1
  STATE
SUBGOAL2 <- GOAL, OTHER-TYPE
  SL0T2
  SL0T1
  STATE
NEW-TYPE
  SLOT (DEFAULT-VALUE)
  OTHER-SLOT (4)
DETAILED-TYPE "The chunk-type detailed-type"
  SL0T
(CHUNK CONSTANT-CHUNKS CLEAR AUDIO-EVENT SET-AUDLOC-DEFAULT SOUND GENERIC-ACTION ...)
8E> (chunk-type repeat slot1 state)
#|Warning: Chunk-type REPEAT has the same specification as the chunk-type GOAL. |#
RÉPEAT
E> (chunk-type (new-type (:include bad-type)))
#|Warning: Non-existent chunk-type BAD-TYPE specified as an :include in NEW-TYPE chunk-
type definition. |#
NIL
E> (chunk-type (bad :include goal))
#|Warning: Invalid modifier list specified with the chunk-type name: (:INCLUDE GOAL) |#
NIL
E> (chunk-type no-model)
#|Warning: chunk-type called with no current model. |#
```

pprint-chunk-type

NIL

Syntax:

```
pprint-chunk-type type-name -> [ type-name | nil ]
pprint-chunk-type-fct type-name -> [ type-name | nil ]
```

Arguments and Values:

type-name ::= a symbol that is the name of a chunk-type

Description:

The pprint-chunk-type command is used to print a description of a chunk-type. The output is sent to the command-trace.

If the parameter provided is the name of a chunk-type in the current model then that chunk-type is printed like this: the chunk-type name is printed and if the chunk-type has any parent types specified then the name is followed by "<-" and the names of the parent chunk-types are printed separated by commas, the documentation string for the chunk-type, if it has one, is printed, and then the slot names of the chunk-type are printed one per line with the slot's default value in parentheses after the slot name if one was provided.

If there is no current model or the given type-name does not name an existing chunk-type in the current model then a warning is printed and **nil** is returned.

```
1> (chunk-type test slot1 (slot2 2))
TEST

2> (chunk-type (subtest (:include test)) "a subtype of test" slot3)
SUBTEST

3> (pprint-chunk-type test)
TEST
    SLOT1
    SLOT2 (2)

TEST

4> (pprint-chunk-type-fct 'subtest)
SUBTEST <- TEST "a subtype of test"
    SLOT1
    SLOT2 (2)
SLOT3

SUBTEST

E> (pprint-chunk-type not-a-chunk-type)
```

```
#|Warning: NOT-A-CHUNK-TYPE does not name a chunk-type in the current model. |#
NIL
E> (pprint-chunk-type chunk)
#|Warning: pprint-chunk-type called with no current model. |#
NII
```

chunk-type-p

Syntax:

```
chunk-type-p chunk-type-name? -> [ t | nil ]
chunk-type-p-fct chunk-type-name? -> [ t | nil ]
```

Arguments and Values:

chunk-type-name? ::= a symbol to be tested to determine if it names a chunk-type

Description:

The chunk-type-p command returns **t** if chunk-type-name? is a symbol that names a chunk-type in the current model and returns **nil** if it does not. If there is no current model then a warning is printed and **nil** is returned.

Examples:

```
> (chunk-type-p clear)
T
> (chunk-type-p-fct 'chunk)
T
> (chunk-type-p bad-name)
NIL
> (chunk-type-p-fct 'non-chunk-type)
NIL
E> (chunk-type-p chunk)
#|Warning: get-chunk-type called with no current model. |#
NTI
```

all-chunk-type-names

Syntax:

```
all-chunk-type-names -> (type-name*)
```

Arguments and Values:

type-name ::= a symbol that names a chunk-type

Description:

All-chunk-type-names takes no parameters and returns a list of all the chunk-type names in the current model. The type names are ordered based on the order in which they were defined (first name in the list is the first one defined).

If there is no current model a warning is printed and **nil** will be returned.

Examples:

```
> (all-chunk-type-names)
(CHUNK CONSTANT-CHUNKS CLEAR QUERY-SLOTS AUDIO-EVENT SET-AUDLOC-DEFAULT SOUND ...)
E> (all-chunk-type-names)
#|Warning: all-chunk-type-names called with no current model. |#
NTI
```

chunk-type-possible-slot-names-fct

Syntax:

chunk-type-possible-slot-names-fct chunk-type-name -> [(slot-name*) | nil]

Arguments and Values:

slot-name ::= a symbol which names a slot usable in the specified chunk-type

Description:

Chunk-type-possible-slot-names-fct takes one parameter which should be the name of a chunk-type. It returns a list of all the names of slots which are valid for use with that chunk-type in the current model along with all of the request parameters which have been defined for the buffers. A slot is valid for the chunk-type if it is specified in that chunk-type's definition, is specified in a chunk-type which has the specified chunk-type as a parent, or is a slot which has been added to chunks through extension with <a href="extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extension-extensi

If there is no current model or the specified name does not name a chunk-type in the current model then a warning is printed and **nil** is returned.

```
> (chunk-type-possible-slot-names-fct 'clear)
(CLEAR :MP-VALUE :RECENTLY-RETRIEVED :CENTER :NEAREST :FINISHED :ATTENDED)
> (chunk-type-possible-slot-names-fct 'chunk)
```

```
(SCALE RIGHT LEFT TYPE SET-VISLOC-DEFAULT SIZE DISTANCE SCREEN-Y SCREEN-X COLORS ...)
E> (chunk-type-possible-slot-names-fct 'bad-name)
#|Warning: Invalid chunk-type name BAD-NAME passed to chunk-type-possible-slot-names-fct.
|#
NIL

E> (chunk-type-possible-slot-names-fct 'chunk)
#|Warning: get-chunk-type called with no current model. |#
#|Warning: Invalid chunk-type name CHUNK passed to chunk-type-possible-slot-names-fct. |#
NIL
```

Chunk Commands

define-chunks

Syntax:

```
define-chunks [chunk-description* | chunk-name*] -> (chunk*)
define-chunks-fct (chunk-description* | chunk-name*) -> (chunk*)
```

Remote command name:

```
define-chunks [ 'chunk-description '* | chunk-name*]
```

Arguments and Values:

```
chunk-description ::= ({chunk-name}{[doc-string isa chunk-type | isa chunk-type]} {slot value}*)
chunk-name ::= the name of the chunk
doc-string ::= a string that will be the documentation for the chunk
chunk-type ::= a name of a chunk-type in the model
slot ::= the name of a slot for the chunk
value ::= any value which will be the contents of the correspondingly named slot for this chunk
```

chunk ::= a symbol which names a chunk that was created

Description:

The define-chunks command creates a new chunk in the current model for each valid chunk description list provided or all the chunk names provided and then returns a list of the names of the chunks that were created.

Within a chunk description list the chunk name is optional. If a chunk-name is provided, it must not name an existing chunk in the current model and must be a non-keyword, non-nil symbol that begins with an alphanumeric character. If a chunk-name is not provided, a new name will be generated for the chunk, and that name is guaranteed to be unique.

The name may be followed by an optional chunk-type specification and if it does it may also include a documentation string for the chunk. If a chunk-type is specified it must name a valid chunk-type in the current model.

That may then be followed by any number of slot and value pairs for the chunk. If a given slot is named more than once in the definition then the last value it is given (rightmost) will be the one set for the chunk. If the value for a slot is non-nil then that slot is added to the chunk being created with the value specified.

If a chunk-type is specified then each of the slots specified will be tested to see if it is a valid slot for the type indicated. If it is not then a warning will be printed, but the chunk will still be created. If it is not a valid slot for any chunk-type then it will automatically extend the valid slots for chunks with that slot name.

If a chunk-type is specified and there are slots with default values in that chunk-type's definition which are not included in the chunk definition the chunk will get all of those unspecified slots with their corresponding default values.

If a value for a slot is a non-nil symbol other than the Lisp true symbol t then it is assumed to be the name of a chunk. If there is not already a chunk by that name, then one is created automatically which has no slots and a warning is printed to indicate that.

However, within a call to define-chunks one can use the names of the chunks that are being defined in the other chunks without having them created as default chunks. Here is an example to clarify that:

Because both a and b are being defined in the same call to define-chunks neither will need to be created automatically. However, unless d already names a chunk in the model a chunk with that name will be created automatically in the process of creating chunk c.

If the syntax is incorrect or any of the components are invalid in a description list then a warning is displayed and no chunk is created for that chunk description, but any other valid chunks defined will still be created.

If there is no current model no chunks are created and **nil** is returned.

```
1> (chunk-type test1 slot1)
TEST1
2> (chunk-type test2 slot1 (slot2 2))
TEST2
3> (define-chunks (a isa test1) (b isa test2))
(A B)
4> (define-chunks-fct '((c slot1 a) (d slot2 c)))
(C D)
```

```
5> (define-chunks ("this is chunk e" isa test1 slot1 100))
(TEST10)
6E> (define-chunks-fct '((isa test1 slot2 "value")))
#|Warning: Invalid slot SLOT2 specified when creating chunk with type TEST1, but creating
chunk TEST11 anyway. |#
(TEST11)
7> (define-chunks ())
(CHUNKO)
8> (define-chunks c1 c2 c3)
(C1 C2 C3)
9E> (define-chunks (slot1 new-name))
#|Warning: Creating chunk NEW-NAME with no slots |#
(CHUNK1)
10E> (define-chunks ("not allowed" slot2 t))
#|Warning: Invalid chunk definition: ("not allowed" SLOT2 T) chunk name is not a valid
symbol. |#
NIL
11E> (define-chunks (slot1 t new-slot 10))
#|Warning: Extending chunks with slot named NEW-SLOT because of chunk definition (SLOT1 T
NEW-SLOT 10) |#
(CHUNK2)
E> (define-chunks (z isa chunk))
#|Warning: define-chunks called with no current model. |#
NIL
```

pprint-chunks & pprint-chunks-plus

Syntax:

```
pprint-chunks chunk-name* -> [chunk-name-list | nil ]
pprint-chunks-fct (chunk-name*) -> [chunk-name-list | nil ]
pprint-chunks-plus chunk-name* -> [chunk-name-list | nil ]
pprint-chunks-plus-fct (chunk-name*) -> [chunk-name-list | nil ]
```

Remote command name:

pprint-chunks
pprint-chunks-plus

Arguments and Values:

```
chunk-name ::= a symbol that should be the name of a chunk chunk-name-list ::= ([chunk-name | :error ]*)
```

Description:

The pprint-chunks family of commands are used to print a description of each of the chunks specified, or all of the chunks in the model if no names are provided. The output is sent to the command-trace.

For each chunk specified, on one line it will print the chunk's name followed by its "true name" in parentheses if the chunk's true name differs from the chunk's current name (see merge-chunks and true-chunk-name below for more details on a chunk's true name). If a documentation string was provided for the chunk that is printed on the next line. Then one per line, each of the chunk's slots is printed followed by that slot's value.

The pprint-chunks-plus command prints all of the chunk's parameters after the description of the chunk is printed. The parameters are printed one per line with the name of the parameter and its current value. Note, that these chunk parameters are the ones that have been added to the chunks (typically by a module as described in the extending chunks section) and may not have any direct significance to the model or modeler. For example, the declarative memory parameters of chunks used by the declarative module to compute and record the activation of chunks should be viewed using the declarative module's sdp command because the values shown with pprint-chunks-plus are values used internally by the declarative module and may not adequately reflect the current value of activations as would be shown by calling the module's command for inspecting the declarative memory chunk's parameters (sdp).

These commands return a list with the names of all the chunks that were printed in the same order as they were specified. If an invalid chunk-name is given nothing is printed for that item and the value **:error** is returned in its place in the list.

If there is no current model then a warning is printed and **nil** is returned.

Examples:

These examples assume that the chunks created in the examples for define-chunks exist.

```
> (pprint-chunks)
TEST10
"this is chunk e"
    SLOT1 100

BUSY
    NAME BUSY

SPEAK
    NAME SPEAK

CURRENT
```

```
NAME CURRENT
SUBVOCALIZE
  NAME SUBVOCALIZE
AUDIO-EVENT
   NAME AUDIO-EVENT
   SLOT2 C
CHUNK0
(TEST10 BUSY SPEAK CURRENT SUBVOCALIZE AUDIO-EVENT D CHUNKO B MAGENTA ...)
> (pprint-chunks a b test10)
Α
   SLOT2 2
TEST10
"this is chunk e"
  SL0T1 100
(A B TEST10)
> (pprint-chunks-fct '(c d))
   SLOT1 A
D
   SLOT2 C
(C D)
> (pprint-chunks-plus chunk0)
CHUNKO
  --chunk parameters--
  VISUAL-APPROACH-WIDTH-FN NIL
   REAL-VISUAL-VALUE NIL
   SPECIAL-VISUAL-OBJECT NIL
   VISUAL-OBJECT NIL
   VISUAL-TSTAMP NIL
   VISUAL-FEATURE-NAME NIL
   VISICON-ENTRY NIL
   VISUAL-NEW-P NIL
   SYNTH-FEAT NIL
   FAST-MERGE-KEY NIL
   RETRIEVAL-TIME NIL
   RETRIEVAL-ACTIVATION NIL
   SJIS NIL
   PERMANENT-NOISE 0.0
   SIMILARITIES NIL
   REFERENCE-COUNT 0
   REFERENCE-LIST NIL
   SOURCE-SPREAD 0
   LAST-BASE-LEVEL 0
   BASE-LEVEL NIL
   CREATION-TIME 0
   FAN-IN NIL
   C-FAN-OUT 0
   FAN-OUT 0
   IN-DM NIL
```

```
ACTIVATION 0
BUFFER-SET-INVALID NIL

(CHUNKO)

E> (pprint-chunks a bad-name b)
A

B
SLOT2 2

(A :ERROR B)

E> (pprint-chunks)
#|Warning: pprint-chunks called with no current model. |#
```

chunk-p

Syntax:

```
chunk-p chunk-name? -> [t | nil ]
chunk-p-fct chunk-name? -> [t | nil ]
```

Remote command name:

chunk-p

Arguments and Values:

chunk-name? ::= a name tested to determine if it names a chunk

Description:

The chunk-p command returns **t** if chunk-name? is a symbol that names a chunk in the current model and returns **nil** if it does not. If there is no current model then a warning is printed and **nil** is returned.

Examples:

These examples assume that chunks named a and b have been created.

```
> (chunk-p a)
T
> (chunk-p not-chunk)
NIL
> (chunk-p-fct 'b)
T
E> (chunk-p-fct 'a)
#|Warning: get-chunk called with no current model. |#
NIL
```

chunk-documentation

Syntax:

```
chunk-documentation chunk-name -> [ doc-string | nil]
chunk-documentation-fct chunk-name -> [ doc-string | nil]
```

Arguments and Values:

```
chunk-name ::= the name of a chunk doc-string ::= a string of the documentation provided when chunk-name was created
```

Description:

Chunk-documentation returns the documentation string of the chunk chunk-name from the current model if it names a valid chunk and has a documentation string. If it does not have a documentation string it returns **nil**. If chunk-name is not the name of a chunk in the current model or there is no current model then a warning is printed and **nil** is returned.

Examples:

These examples assume that the chunks created in the examples for define-chunks exist.

```
> (chunk-documentation test10)
"this is chunk e"
> (chunk-documentation a)
NIL
> (chunk-documentation-fct 'test10)
"this is chunk e"

E> (chunk-documentation-fct 'not-a-chunk)
#|Warning: NOT-A-CHUNK does not name a chunk in the current model. |#
NIL

E> (chunk-documentation c)
#|Warning: get-chunk called with no current model. |#
NIL
```

chunk-slot-value

Syntax:

```
chunk-slot-value chunk-name slot-name -> [ slot-value | nil ] chunk-slot-value-fct chunk-name slot-name -> [ slot-value | nil ]
```

Remote command name:

chunk-slot-value chunk-name slot-name -> ['slot-value' | nil]

Arguments and Values:

```
chunk-name ::= the name of a chunk
slot-name ::= the name of a slot in the chunk chunk-name
slot-value ::= the value from slot-name in chunk chunk-name
```

Description:

Chunk-slot-value is used to get the value of a slot in a chunk. If chunk-name is the name of a chunk in the current model and slot-name is the name of a slot in chunk-name then the value in the slot-name slot of the chunk chunk-name is returned. If chunk-name is the name of a chunk but it does not have a slot named slot-name then **nil** will be returned.

If chunk-name does not name a chunk in the model or there is no current model then a warning is printed and **nil** is returned.

Examples:

These examples assume that the chunks created in the examples for define-chunks exist.

```
> (chunk-slot-value c slot1)
A
> (chunk-slot-value c slot2)
NIL
>(chunk-slot-value-fct 'd 'slot2)
C
> (chunk-slot-value a other-slot)
NIL

E> (chunk-slot-value bad-chunk-name slot1)
#|Warning: BAD-CHUNK-NAME does not name a chunk in the current model. |#
NIL

E> (chunk-slot-value c slot1)
#|Warning: get-chunk called with no current model. |#
NTI
```

set-chunk-slot-value

Syntax:

```
set-chunk-slot-value chunk-name slot-name slot-value -> [ slot-value | nil ] set-chunk-slot-value-fct chunk-name slot-name slot-value -> [ slot-value | nil ]
```

Remote command name:

set-chunk-slot-value chunk-name slot-name 'slot-value' -> ['slot-value' | nil]

Arguments and Values:

```
chunk-name ::= the name of a chunk
slot-name ::= the name of a slot
slot-value ::= a value for slot-name in chunk chunk-name
```

Description:

Set-chunk-slot-value is used to set the value of the slot slot-name in the chunk chunk-name in the current model to the value slot-value. If successful, slot-value is returned.

If slot-value is a name and not the name of a current chunk in the current model then it is created as a new chunk with no slots and a warning is displayed.

If a slot-value of **nil** is specified for a slot that will remove that slot from the chunk.

If the chunk chunk-name has been marked as immutable then a warning is printed, no changes are made to the chunk and **nil** is returned.

If either chunk-name or slot-name is invalid or there is no current model then a warning is printed and **nil** is returned.

Examples:

These examples assume that the chunks created in the examples for define-chunks exist.

```
> (set-chunk-slot-value a slot1 10)
10
> (set-chunk-slot-value-fct 'b 'slot2 "value")
"value"
> (set-chunk-slot-value a slot2 new-chunk)
#|Warning: Creating chunk NEW-CHUNK with no slots |#
NEW-CHUNK

1> (make-chunk-immutable 'b)
T

2E> (set-chunk-slot-value b slot1 10)
#|Warning: Cannot change contents of chunk B. |#
NIL

E> (set-chunk-slot-value-fct 'not-a-chunk 'slot1 t)
#|Warning: NOT-A-CHUNK does not name a chunk in the current model. |#
NIL

E> (set-chunk-slot-value c not-a-slot b)
```

```
#|Warning: NOT-A-SLOT is not a valid slot name. You can use extend-possible-slots to add
it first if needed. |#
NIL

E> (set-chunk-slot-value a slot1 b)
#|Warning: get-chunk called with no current model. |#
NIL
```

mod-chunk

Syntax:

```
mod-chunk chunk-name {slot-value}* -> [ chunk-name | nil ]
mod-chunk-fct chunk-name ({slot-name slot-value}*) -> [ chunk-name | nil ]
```

Remote command name:

mod-chunk chunk-name '{slot-name slot-value}'*

Arguments and Values:

```
chunk-name ::= the name of a chunk
slot-name ::= the name of a slot in the chunk chunk-name
slot-value ::= a value for the corresponding slot-name in chunk chunk-name
```

Description:

Mod-chunk is used to set the value of multiple slots in the chunk named chunk-name in the current model. It is essentially a short hand for multiple calls to set-chunk-slot-value.

If chunk-name is the name of a chunk in the current model and there are an even number of items specified thereafter, then those items are considered pair-wise to be the name of a slot and a value for that slot in that chunk. All of those slots in the chunk are set to the values specified and chunk-name is returned.

If any slot-value is a name and not the name of a chunk in the current model then it is created as a new chunk with no slots and a warning is displayed.

A slot name may only be specified once in the set of slot-names. If a slot name is specified more than once a warning is printed, no changes are made to the chunk, and **nil** is returned.

If any slot name provided is not a valid slot for chunks no changes are made to the chunk, and **nil** is returned.

If the chunk chunk-name has been marked as immutable then a warning is printed, no changes are made to the chunk and **nil** is returned.

If chunk-name does not name a chunk in the current model or there are an odd number of items provided after the chunk-name then a warning is displayed, no changes are made, and **nil** is returned.

Examples:

These examples assume that the chunks created in the examples for define-chunks exist.

```
> (mod-chunk a slot1 b slot2 c)
> (mod-chunk-fct 'b '(slot1 10 new-slot t))
> (mod-chunk a slot1 new-chunk-name)
#|Warning: Creating chunk NEW-CHUNK-NAME with no slots |#
1> (make-chunk-immutable 'b)
2E> (mod-chunk b slot1 10)
#|Warning: Cannot modify chunk B because it is immutable. |#
E> (mod-chunk a slot1 1 slot1 2)
#|Warning: Slot name used more than once in modifications list. |#
NIL
E> (mod-chunk-fct 'a '(slot1 b slot2))
#|Warning: Odd length modifications list in call to mod-chunk. |#
NIL
E> (mod-chunk a slot1 b)
#|Warning: get-chunk called with no current model. |#
NIL
```

copy-chunk

Syntax:

```
copy-chunk chunk-name -> [new-name | nil ]
copy-chunk-fct chunk-name -> [new-name | nil ]
```

Remote command name:

copy-chunk

Arguments and Values:

```
chunk-name ::= the name of a chunk
new-name ::= a unique name for a new chunk
```

Description:

Copy-chunk creates a copy of the chunk chunk-name in the current model and returns the name of the newly created chunk. The newly created copy has the same slots and values as the chunk chunk-name. The values of the parameters defined for the new chunk will have the default value unless the parameter was specified with a copy-function, in which case, the value will be the one returned by that function.

If chunk-name does not name a chunk in the current model or there is no current model then a warning is displayed and **nil** is returned.

Examples:

These examples assume that there are chunks named a and b in the current model.

```
> (copy-chunk a)
A-0
> (copy-chunk-fct 'b)
B-0

E> (copy-chunk not-a-chunk)
#|Warning: NOT-A-CHUNK does not name a chunk in the current model. |#
NIL

E> (copy-chunk a)
#|Warning: get-chunk called with no current model. |#
NIL
```

chunk-copied-from

Syntax:

```
chunk-copied-from chunk-name -> [original-name | nil] {other}
chunk-copied-from-fct chunk-name -> [original-name | nil] {other}
```

Remote command name:

chunk-copied-from

Arguments and Values:

```
chunk-name the name of a chunk
original-name ::= the name of a chunk
other ::= a generalized boolean indicating whether this chunk was a copy and is still unmodified
```

Description:

The chunk-copied-from command returns one or two values. If chunk-name is the name of a chunk in the current model then two values will be returned. If chunk-name was created with copy-chunk, it has not been modified since its creation, and the original chunk has not been modified such that it now differs from the copy (the original could have been modified but if it is still a match using equal-chunks it is still considered the same) then the name of the chunk from which chunk-name was copied is returned as both the first and second value. If it was not created using copy-chunk, it has since been modified, or the original chunk has been modified in such a way that the two now differ (including being deleted) then **nil** is returned for the first value. If the chunk was created using copy-chunk and has not been modified then the second value will be the name of the chunk from which it was copied (which may no longer be an interned symbol in Lisp if that chunk was purged) otherwise the second value will be **nil**.

If chunk-name does not name a chunk in the current model or there is no current model then a warning is displayed and a single value of **nil** is returned.

This command is rarely used by modelers because needing to copy chunks and keep track of how they came about are not typical actions. However, it can be important to those creating new modules where it can be used to determine if a chunk passed in as part of a request is a copy of a chunk which the module had placed into a buffer i.e. the request is using a copy of a chunk for which the module has created the original.

```
1> (chunk-type test slot1 slot2)
TEST

2> (define-chunks (a slot1 10 slot2 "answer") (b slot1 a))
(A B)

3> (copy-chunk a)
A-0

4> (copy-chunk b)
B-0

5> (chunk-copied-from a-0)
A
A

6> (chunk-copied-from a)
NIL
NIL

7> (mod-chunk a slot1 5)
A

8> (chunk-copied-from-fct 'a-0)
NIL
```

```
A
9> (chunk-copied-from-fct 'b-0)
B
B
10> (mod-chunk b-0 slot2 10)
B-0
11> (chunk-copied-from b-0)
NIL
NIL
E> (chunk-copied-from-fct 'not-a-chunk)
#|Warning: NOT-A-CHUNK does not name a chunk in the current model. |#
NIL
E> (chunk-copied-from b-0)
#|Warning: get-chunk called with no current model. |#
NTI
```

chunks

Syntax:

chunks -> [(chunk-name*) | nil]

Remote command name:

chunks

Arguments and Values:

chunk-name ::= the name of a chunk in the current model

Description:

The chunks command returns a list of the names of all the chunks defined in the current model in no particular order.

If there is no current model then a warning is printed and **nil** is returned.

```
> (chunks)
(GREEN CYAN SPEECH C DARK-CYAN RED-COLOR B-0 OVAL ...)
E> (chunks)
#|Warning: chunks called with no current model. |#
NIL
```

chunk-slot-equal

chunk-slot-equal val-1 val-2 -> equal-result

Arguments and Values:

```
val-1 ::= any value
val-2 ::= any value
equal-result ::= a generalized boolean indicating whether the values are equal slot contents
```

Description:

The chunk-slot-equal function is used to determine if two values are considered equivalent for the contents of slots in chunks. It relies upon three Lisp equality functions, and the values will be equivalent if one of the following is true:

- the values are eq
- both values are symbols which name chunks in the current model and those chunks return true from eq-chunks
- both values are strings and those strings return true from string-equal
- if the values are not both chunk names or not both strings and they return true from equalp

If the two values are equivalent, then a true value is returned. Otherwise, **nil** will be returned.

```
> (chunk-slot-equal 1 1)
T
> (chunk-slot-equal 1 1.5)
NIL
> (chunk-slot-equal "String1" "strING1")
T
> (chunk-slot-equal 'not-a-chunk 'not-a-chunk)
T
> (chunk-slot-equal 'not-a-chunk :not-a-chunk)
NIL
1> (define-chunks (c1)(c2))
(C1 C2)
2> (chunk-slot-equal 'c1 'c2)
NIL
3> (merge-chunks c1 c2)
C1
4> (chunk-slot-equal 'c1 'c2)
```

equal-chunks

```
equal-chunks chunk-name-1 chunk-name-2 -> equal-result
equal-chunks-fct chunk-name-1 chunk-name-2 -> equal-result
```

Arguments and Values:

```
chunk-name-1 ::= the name of a chunk
chunk-name-2 ::= the name of a chunk
equal-result ::= a generalized boolean indicating whether the chunks are equal
```

Description:

The equal-chunks command can be used to determine if the chunks named by chunk-name-1 and chunk-name-2 in the current model are equivalent chunks. They will be equivalent if they are eqchunks or if they have the same set of slots and for each slot the values of those slots in the two chunks are the same as determined by the chunk-slot-equal test. If the two chunks are equivalent, then a true value is returned. Otherwise, **nil** will be returned.

If either name does not name a chunk or there is no current model, then a warning is printed and **nil** is returned.

```
8> (mod-chunk c5 slot3 t)
C5

9> (equal-chunks c5 c6)
NIL

E> (equal-chunks not-a-chunk free)
#|Warning: NOT-A-CHUNK does not name a chunk in the current model. |#
NIL

E> (equal-chunks c1 c2)
#|Warning: get-chunk called with no current model. |#
#|Warning: get-chunk called with no current model. |#
NIL
```

eq-chunks

Syntax:

```
eq-chunks chunk-name-1 chunk-name-2 -> equal-result eq-chunks-fct chunk-name-1 chunk-name-2 -> equal-result
```

Arguments and Values:

```
chunk-name-1 ::= the name of a chunk
chunk-name-2 ::= the name of a chunk
equal-result ::= a generalized boolean indicating whether the chunks are the same
```

Description:

Eq-chunks is used to determine if the chunks named by chunk-name-1 and chunk-name-2 are the exact same chunk in the current model. They will be the same chunk if chunk-name-1 and chunk-name-2 are the same name or if the two named chunks have been merged. If they are the same chunk, then a true value is returned. Otherwise **nil** will be returned.

If either name does not name a chunk or there is no current model, then a warning is printed and **nil** is returned.

```
T

5> (eq-chunks-fct 'c1 'c2)
NIL

6> (merge-chunks c1 c2)
C1

7> (eq-chunks c1 c2)
T

8> (eq-chunks c3 c4)
NIL

E> (eq-chunks c1 not-a-chunk)
#|Warning: NOT-A-CHUNK does not name a chunk in the current model. |#
NIL

E> (eq-chunks c1 c2)
#|Warning: get-chunk called with no current model. |#
NII

NII
```

delete-chunk

Syntax:

delete-chunk chunk-name -> [chunk-name | nil]
delete-chunk-fct chunk-name -> [chunk-name | nil]

Remote command name:

delete-chunk

Arguments and Values:

chunk-name ::= the name of a chunk

Description:

Delete-chunk removes the chunk named chunk-name from the set of chunks in the current model. If chunk-name is the name of a chunk in the current model then after that chunk is deleted chunk-name is returned.

If chunk-name has been marked as immutable then it cannot be deleted, a warning will be printed and **nil** will be returned.

If chunk-name does not name a chunk in the current model or there is no current model then a warning is printed and **nil** is returned.

Note: there is no additional clean-up done in conjunction with deleting the chunk. Thus, if it is used as a slot value in other chunks or currently residing in a buffer the consequences of deleting it are undefined and warnings or errors could result from later actions involving such chunks or buffers. Delete-chunk should be used rarely and only when it is certain that the chunk being deleted is not referenced elsewhere.

Examples:

These examples assume that chunks named a, b, and c exist.

```
> (delete-chunk a)
A

1> (delete-chunk-fct 'b)
B

2E> (delete-chunk b)
#|Warning: B does not name a chunk in the current model. |#
NIL

1> (make-chunk-immutable 'c)
T

2E> (delete-chunk c)
#|Warning: Cannot delete chunk C because it is marked as immutable. |#
NIL

E> (delete-chunk c)
#|Warning: get-chunk called with no current model. |#
NIL
```

purge-chunk

Syntax:

```
purge-chunk chunk-name -> [t | nil ]
purge-chunk-fct chunk-name -> [t | nil ]
```

Remote command name:

purge-chunk

Arguments and Values:

```
chunk-name ::= the name of a chunk
```

Description:

Purge-chunk removes the chunk named chunk-name from the set of chunks in the current model using <u>delete-chunk</u> and releases the name of that chunk using the <u>release-name</u> command as

described under the <u>naming module</u>. If chunk-name is the name of a chunk in the current model and its name was released then **t** is returned.

If chunk-name does not name a chunk in the current model or there is no current model then a warning is printed and **nil** is returned.

If the chunk is deleted, but the name is not released **nil** is returned without a warning being printed.

As with delete-chunk, there is no additional clean-up done in conjunction with purging the chunk. Thus, if it is used as a slot value in another chunk or currently residing in a buffer undefined consequences could arise.

Because purge-chunk also attempts to unintern the name of the chunk it should only be used for chunks for which the name was automatically generated by ACT-R or explicitly generated with the new-name command. This is not going to be a command used by most modelers. However, in situations where (computer) memory usage is important in long running models or models which generate a lot of temporary chunks, explicitly freeing some of that space may be necessary.

Examples:

These examples assume that there are chunks named a and b.

```
1> (copy-chunk b)
B-0

2> (purge-chunk-fct 'b-0)
T

3E> (purge-chunk b-0)
#|Warning: B-0 does not name a chunk in the current model. |#
NIL

> (purge-chunk a)
NIL

E> (purge-chunk a)
#|Warning: get-chunk called with no current model. |#
NIL
```

merge-chunks

Syntax:

```
merge-chunks chunk-name-1 chunk-name-2 -> [ chunk-name-1 | nil ] merge-chunks-fct chunk-name-1 chunk-name-2 -> [ chunk-name-1 | nil ]
```

Arguments and Values:

```
chunk-name-1 ::= a symbol that should be the name of a chunk chunk-name-2 ::= a symbol that should be the name of a chunk
```

Description:

If the chunks named by chunk-name-1 and chunk-name-2 are equivalent chunks as determined by <u>equal-chunks</u> then both chunks are replaced by a single chunk. Effectively, the two chunks are merged into one chunk. The "true name" of the merged chunk will be chunk-name-1, but references which use either name will still be valid and now refer to the single chunk resulting from the merge.

If the chunks are merged, then any additional chunk parameters that have been added to the chunks will remain those that existed for chunk-name-1 unless there is a merge-function defined for the parameter.

If either chunk is later deleted, both of the chunks will become unavailable i.e. deleting any one of a set of merged chunks deletes all of those merged chunks since there is only one underlying chunk.

If the chunks are equivalent as tested by <u>eq-chunks</u> then no actions are taken and chunk-name-1 is returned.

If the chunks are successfully merged, then chunk-name-1 is returned.

If the chunks are not equal-chunks **nil** is returned.

If either name does not name a chunk in the current model or there is no current model then a warning is displayed and **nil** is returned.

The merge-chunks command is primarily for use by the declarative memory module, and it is not expected to be used elsewhere but is available if one finds a need. As with delete-chunk, it should be used carefully to avoid circumstances were chunks to which other modules already have references are merged which could result in unexpected consequences.

```
A  
4> (eq-chunks a b)
NIL

5> (merge-chunks-fct 'a 'b)
A  
6> (eq-chunks a b)
T  
7> (merge-chunks a c)
NIL

E> (merge-chunks a not-a-chunk)
#|Warning: NOT-A-CHUNK does not name a chunk in the current model. |#
NIL

E> (merge-chunks a b)
#|Warning: get-chunk called with no current model. |#
NII  
E> (merge-chunks a b)
#|Warning: get-chunk called with no current model. |#
```

create-chunk-alias

Syntax:

```
create-chunk-alias chunk-name alias -> [ alias | nil ]
create-chunk-alias-fct chunk-name alias -> [alias | nil ]
```

Arguments and Values:

chunk-name ::= a symbol that should be the name of a chunk alias ::= a symbol that should not be the name of a chunk

Description:

If the chunk specified by chunk-name exists in the current model and the symbol provided as alias is not the name of a chunk in the current model then alias will be added as a reference to the chunk chunk-name. This works essentially the same as if a chunk named alias had been merged with the chunk named chunk-name.

If the alias is successfully created, then alias is returned.

If chunk-name does not name a chunk in the current model, alias is not a symbol, alias is already the name of a chunk in the model, or there is no current model then a warning is displayed and **nil** is returned.

This command is not likely to be used often, but it may be helpful if a chunk which has a long name is generated automatically by the model and one needs to perform lots of actions or tests using that chunk.

Examples:

```
1> (define-chunks (a) (b))
(A B)
2> (chunk-p alias)
NIL
3> (create-chunk-alias a alias)
ALIAS
4> (eq-chunks a alias)
5E> (create-chunk-alias-fct 'a 'b)
#|Warning: B is already the name of a chunk in the current model and cannot be used as an
alias. |#
NIL
E> (create-chunk-alias c new-chunk-name)
#|Warning: C is not the name of a chunk in the current model. |#
NIL
E> (create-chunk-alias a alias)
#|Warning: create-chunk-alias called with no current model. |#
```

true-chunk-name

Syntax:

```
true-chunk-name chunk-name -> [ true-name | chunk-name ]
true-chunk-name-fct chunk-name -> [ true-name | chunk-name ]
```

Arguments and Values:

```
chunk-name ::= any value true-name ::= a symbol that is the name of a chunk in the current model
```

Description:

True-chunk-name is used to find the "true name" of a chunk in the current model. The true name of a chunk which has not been merged with another chunk is its own name. The true name of a chunk that has been merged with another chunk is the true name of the chunk that was returned from a merging of that chunk with another. The true name of a chunk alias is the true name of the chunk to which it was aliased.

If chunk-name is the name of a chunk in the current model then its true name is returned. If chunk-name is any other value, then chunk-name is returned.

If there is no current model then a warning is printed and chunk-name is returned.

Examples:

```
1> (define-chunks (a) (b) (c))
(A B C)

2> (merge-chunks a b)
A

3> (create-chunk-alias b alias)
ALIAS

4> (true-chunk-name a)
A

5> (true-chunk-name-fct 'c)
C

6> (true-chunk-name b)
A

7> (true-chunk-name alias)
A

8> (true-chunk-name d)
D

> (true-chunk-name 100)
100

E> (true-chunk-name t)
#|Warning: get-chunk called with no current model. |#
```

normalize-chunk-names

normalize-chunk-names { unintern } -> nil

Arguments and Values:

unintern ::= a generalized boolean indicating whether to delete the merged chunks and release the names

Description:

The normalize-chunk-names command will iterate through all chunks in the current model and replace all chunk references in slots with the true name of that chunk. That may be useful for

debugging purposes and the <u>naming module</u> has a parameter (:ncnar) which can trigger this call automatically.

In addition, if the unintern parameter is true then all chunks which have been merged with other chunks (those for which their name is not the chunk's true name) will be deleted from the model and the chunk name will be released using <u>release-name</u>.

The command will always return **nil**. If there is no current model then a warning will be printed indicating that.

Notes: This command may take a long time to run if the model has a large number of chunks. Also, the unintern option is generally not recommended because it may cause problems for modules which have stored internal references to those temporary names. However, in some extreme circumstances (a very long continuous run or a model which does a lot of buffer manipulations over a long run) a model can generate so many chunk name symbols than it can become unable to continue running (the Lisp heap or the physical memory of the machine is exhausted) thus calling normalize-chunk-names periodically with the unintern option would be necessary to continue running. If you are encountering such situations, please let me know about it because there may be other options or changes that could be made.

Examples:

To show the command in use, there must be a chunk which has been merged with another and also used in a slot value.

```
SLOT1 C1

(C3)

7> (pprint-chunks c2)
C2 (C1)
SLOT1 1
SLOT2 T

(C2)
8> (normalize-chunk-names t)
NIL

9> (pprint-chunks c2)
(:ERROR)

E> (normalize-chunk-names)
#|Warning: No current model in which to normalize chunk names. |#
NIL
```

chunk-filled-slots-list

Syntax:

```
chunk-filled-slots-list chunk-name {sorted} -> [( slot-name* ) | nil ]
chunk-filled-slots-list-fct chunk-name {sorted} -> [( slot-name* ) | nil ]
```

Remote command name:

chunk-filled-slots-list

Arguments and Values:

```
chunk-name ::= the name of a chunk
slot-name ::= the name of a slot
sorted ::= a generalized boolean indicating whether the returned list should be in a cannonical order
```

Description:

Chunk-filled-slots-list is used to get a list of the slots which contain values in the chunk specified by chunk-name in the current model. If the optional sorted parameter is provided with a non-nil value then the list returned will be sorted so that if two chunks have the same set of slots with values then this command will return the same list for both. If the sorted parameter is not provided or specified as **nil** then there is no guarantee that the same list will be returned for different chunks with the same set of slots.

If chunk-name is invalid or there is no current model then a warning is printed and **nil** is returned.

```
1> (define-chunks
     (a color blue value "a")
     (b value "b" color green)
     (c)
     (d size 100))
(A B C D)
2> (chunk-filled-slots-list a)
(COLOR VALUE)
3> (chunk-filled-slots-list-fct 'b)
(VALUE COLOR)
4> (chunk-filled-slots-list c)
NIL
5> (chunk-filled-slots-list-fct 'd)
(SIZE)
6> (chunk-filled-slots-list a t)
(VALUE COLOR)
7> (chunk-filled-slots-list b t)
(VALUE COLOR)
E> (chunk-filled-slots-list "not-a-chunk")
#|Warning: "not-a-chunk" does not name a chunk in the current model. |#
NIL
E> (chunk-filled-slots-list a)
#|Warning: get-chunk called with no current model. |#
NIL
```

General Parameters

General parameters are the primary means of configuring the operation of ACT-R both from a usability standpoint and at the level of controlling the performance of a model. They can be used to control how much output is shown when a model runs or to adjust how long it takes a model to retrieve a chunk from its declarative memory as well as many other things. Each module in the system can make available any number of general parameters that are relevant to its operation. The specific parameters of each module will be described in that module's section. In this section, the common aspects of those parameters will be described along with the commands that can be used to set, get, and show them.

The general parameters are each referenced by a name which is a Lisp keyword e.g. :v or :trace-detail, and can be set to some value which is meaningful to the module that owns the parameter. Each one has a default value specified by the owning module and often there are limits as to what values can be given to a particular parameter. Attempting to set an invalid value will result in a warning and no change in the parameter. In most cases the parameters are independent between models i.e. two concurrent models could have different values for the same general parameter. However, there can be exceptions to that. For example, a module that allows models to connect to some external simulation might provide parameters to specify where to connect to that simulation, but may require that all models connect to the same simulation. None of the provided modules operate that way, but it is worth noting that modules could be added which have parameters that are linked between models.

One final thing to note about general parameters is that it is possible for modules other than the parameter's owning module to monitor the parameter setting and possibly modify the parameter. The details of doing that are covered in the <u>module creation</u> section. Because of that one should be aware that it is possible for parameters to start with values other than their specified default after a model is reset or to be set to a value different than one the user requests if a monitoring module changes it. An example of the first situation (a starting value other than the default) exists in the main ACT-R system with the :do-not-harvest parameter. The procedural module owns that parameter and specifies a default value of **nil**, but the goal module will change that parameter at reset time to include the goal buffer. It is also the case that if one starts the ACT-R Environment then several of the tracing and hook parameters will be set automatically to values which allow the Environment to operate. There are no modules in the provided set which modify the values a user specifies, but an example where such a situation could be used might be a module which provides support for modeling alertness or

sleepiness. It could automatically adjust the parameters that a user specifies for controlling other modules to take into account the current alertness setting. Of course it does not have to work that way, but it is a possibility which modelers and module writers should know about.

Commands

sgp

Syntax:

Arguments and Values:

```
param-name ::= a keyword which names a parameter param-value-pair ::= param-name new-param-value new-param-value ::= a Lisp value to which the preceding param-name is to be set
```

param-value ::= the current value of a param-name

Description:

Sgp is used to set or get the value of the parameters from the modules of the current model.

If no parameters are provided, all of the current model's parameters are printed to the <u>command-trace</u>. They are organized alphabetically by module name and then by parameter name within a module, and **nil** is returned. For each parameter, its name and current value is printed followed by the default value and any documentation provided by the module that owns the parameter.

If all of the parameters passed to sgp are keywords, then it is a request for the current values of those general parameters' values in the current model. Those parameters are printed and a list of their values in the order requested is returned. If any of the names are not of valid parameters then a warning is displayed and the keyword :bad-parameter-name is returned for that position in the list. Note: because the test to determine that a call to sgp is a request for parameter values is that all the values passed to sgp are keywords, a module should never have a parameter accept a keyword as a possible value because it will not be possible to set such a parameter value on its own.

If there are any non-keyword parameters in the call to sgp and the total number of elements is even, then they are assumed to be pairs of a parameter name and a parameter value. Each of those parameter values will be passed to the corresponding parameter's owning module and all monitoring

modules. The return value will be the current settings of those parameters in the order given (the values may or may not be the same as the values passed in to set them depending on the module) unless a parameter value was not of the appropriate type as required by the module. In that case, a warning is printed and the value returned in that position will be the keyword :invalid-value.

If there are non-keywords passed to sgp and the number of items is odd or if there is no current model at the time of the call, then a warning is displayed and **nil** is returned.

Examples:

```
> (sgp)
:AUDIO module
-----
:DIGIT-DETECT-DELAY 0.3 default: 0.3 : Lag between onset and detectability for digits
:DIGIT-DURATION 0.6 default: 0.6 : Default duration for digit sounds.
                        default: 0.5 : Recoding delay for digit sound content.
:DIGIT-RECODE-DELAY 0.5
:HEAR-NEWEST-ONLY NIL
                        default: NIL
                                       : Whether to stuff only the newest unattended
audio-event from the audicon into the aural-location buffer.
:SOUND-DECAY-TIME 3.0 default: 3.0 : The amount of time after a sound has finished
it takes for the sound to be deleted from the audicon
:TONE-DETECT-DELAY 0.05 default: 0.05 : Lag between sound onset and detectability for
tones
:TONE-RECODE-DELAY 0.285 default: 0.285 : Recoding delay for tone sound content.
BOLD module
> (sgp :v :lf)
:V T (default T) : Verbose controls model output
:LF 1.0 (default 1.0) : Latency Factor
(T 1.0)
> (sgp-fct '(:v nil :lf 4.5))
(NIL 4.5)
E> (sgp-fct '(:v t :lf nil))
#|Warning: Parameter :LF cannot take value NIL because it must be a positive number. |#
(T :INVALID-VALUE)
E> (sgp :not-a-parameter 10)
#|Warning: Parameter :NOT-A-PARAMETER is not the name of an available parameter |#
(:BAD-PARAMETER-NAME)
E> (sgp :esc t :v)
#|Warning: Odd number of parameters and values passed to sgp. |#
E> (sgp)
#|Warning: sgp called with no current model. |#
NIL
```

get-parameter-default-value

Syntax:

```
get-parameter-default-value param-name -> [ param-default | :bad-parameter-name ]
```

Arguments and Values:

```
param-name ::= a keyword which should name a parameter param-default ::= the default value specified for param-name when it was defined
```

Description:

The get-parameter-default-value command is used to get the default value that a parameter was given when it was defined. If param-name is the name of a general parameter then the default value specified for that parameter is returned. If param-name does not name a general parameter then a warning is printed and **:bad-parameter-name** is returned.

Examples:

```
> (get-parameter-default-value :v)
T
E> (get-parameter-default-value :not-a-param)
#|Warning: Invalid parameter name :NOT-A-PARAM in call to get-parameter-default-value. |#
:BAD-PARAMETER-NAME
```

with-parameters

Syntax:

```
with-parameters parameter-list form* -> [ result | nil ] with-parameters-fct parameter-list form* -> [ result | nil ]
```

Arguments and Values:

```
parameter-list ::= ({param-name value}*)
param-name ::= a keyword which should name a parameter
value ::= a value to which the preceding parameter should temporarily be set
form ::= a valid Lisp expression to evaluate
result ::= the value returned from the last form evaluated
```

Description:

The with-parameters command is used to temporarily set some parameters in the current model and then execute some commands. If all of the param-name values provided name valid parameters then each will be set to the corresponding value given before executing the forms. After those forms have been evaluated each of those parameters will be set back to the value it had previously and the result

of the last form evaluated will be returned. The forms are evaluated in an unwind-protect so that the restoring of the parameters occurs even if the forms result in an error.

If any of the param-name values do not name a valid parameter or there is no current model then a warning will be printed, the forms will not be evaluated, and **nil** is returned.

The difference between with-parameters and with-parameters-fct is not quite the same as it is for other commands. In this case both are macros, but with-parameters-fct evaluates the items on the parameter-list and with-parameters does not. Thus the parameter-list for with-parameters will look similar to what one would provide to sgp whereas the parameter-list for with-parameters-fct may contain expressions and variables which need to be evaluated.

Examples:

This example sequence assumes that the count model from unit 1 of the tutorial is loaded.

```
1> (reset)
DEFAULT
2> (run .05)
             GOAL
                                     SET-BUFFER-CHUNK GOAL FIRST-GOAL REQUESTED NIL
     0.000
     0.000
             PROCEDURAL
                                     CONFLICT-RESOLUTION
     0.000
             PROCEDURAL
                                     PRODUCTION-SELECTED START
             PROCEDURAL
     0.000
                                     BUFFER-READ-ACTION GOAL
     0.050
             PROCEDURAL
                                     PRODUCTION-FIRED START
             PROCEDURAL
                                     MOD-BUFFER-CHUNK GOAL
     0.050
     0.050
             PROCEDURAL
                                     MODULE-REQUEST RETRIEVAL
     0.050
             PROCEDURAL
                                     CLEAR-BUFFER RETRIEVAL
     0.050
             DECLARATIVE
                                     START-RETRIEVAL
     0.050
             PROCEDURAL
                                     CONFLICT-RESOLUTION
     0.050
                                     Stopped because time limit reached
             _ _ _ _ _ _
0.05
13
NIL
3> (with-parameters (:v nil)
     (run .05))
0.05
NIL
4> (with-parameters-fct (:trace-detail 'low)
     (run .05))
                                     PRODUCTION-FIRED INCREMENT
     0.150
             PROCEDURAL
2
                                     Stopped because time limit reached
     0.150
             -----
0.05
6
NIL
5> (run .05)
     0.200
             DECLARATIVE
                                     RETRIEVED-CHUNK D
     0.200
             DECLARATIVE
                                     SET-BUFFER-CHUNK RETRIEVAL D
     0.200
             PR0CEDURAL
                                     CONFLICT-RESOLUTION
     0.200
             PROCEDURAL
                                     PRODUCTION-SELECTED INCREMENT
     0.200
             PROCEDURAL
                                     BUFFER-READ-ACTION GOAL
```

```
0.200
                                     BUFFER-READ-ACTION RETRIEVAL
            PR0CEDURAL PR0CEDURAL
                                     Stopped because time limit reached
     0.200
             _ _ _ _ _ _
0.05
NIL
E> (with-parameters (:not-valid 10)
     (run .05))
#|Warning: :NOT-VALID is not the name of a parameter. with-parameters body ignored. |#
E> (with-parameters-fct (:v)
     (run .05))
#|Warning: Odd length parameters list in call to with-parameters. The body is ignored. |#
NIL
E> (with-parameters (:v t)
     (run 1))
#|Warning: with-parameters called with no current model. |#
```

get-parameter-value

Syntax:

```
get-parameter-value param-name -> [ param-value | :bad-parameter-name | :no-model ]
```

Remote command name:

```
get-parameter-value param-name -> [ 'param-value' | :bad-parameter-name | :no-model ]
```

Arguments and Values:

```
param-name ::= the name of a parameter param-value ::= the current value for the parameter param-name
```

Description:

The get-parameter-value command is used to get the current value that a parameter has in the current model. If param-name is the name of a parameter then the current value for that parameter is returned. If param-name does not name a general parameter then a warning is printed and **:bad-parameter-name** is returned. If there is no current model then a warning is printed and **:no-model** is returned.

```
> (get-parameter-value :lf)
0.05
E> (get-parameter-value 'bad)
#|Warning: Invalid parameter name BAD in call to get-parameter-value. |#
:BAD-PARAMETER-NAME
```

```
E> (get-parameter-value :v)
#|Warning: get-parameter-value called with no current model. |#
:NO-MODEL
```

set-parameter-value

Syntax:

```
set-parameter-value param-name new-value -> [ param-value | :bad-parameter-name | :invalid-value | :no-model ]
```

Remote command name:

```
set-parameter-value param-name 'new-value' -> [ 'param-value' | :bad-parameter-name | :invalid-value | :no-model ]
```

Arguments and Values:

```
param-name ::= the name of a parameter
new-value ::= any value which will be set as the new value for param-name
param-value ::= the current value for the parameter param-name
```

Description:

The set-parameter-value command is used to set the current value for a parameter in the current model. If param-name is the name of a parameter and param-value is a valid value for that parameter then the current value for that parameter is set to the new-value provided and the current value reported by the module is returned (that might not be the same as new-value depending on the module). If param-name does not name a general parameter then a warning is printed and :bad-parameter-name is returned. If param-value is not a valid value for param-name then a warning is printed and :invalid-value is returned. If there is no current model then a warning is printed and :no-model is returned.

```
> (set-parameter-value :v t)
T
> (set-parameter-value :do-not-harvest 'visual)
(VISUAL TEMPORAL GOAL)

E> (set-parameter-value :bad-name t)
#|Warning: Parameter :BAD-NAME is not the name of an available parameter |#
:BAD-PARAMETER-NAME

E> (set-parameter-value :lf t)
#|Warning: Parameter :LF cannot take value T because it must be a non-negative number. |#
:INVALID-VALUE
```

E> (set-parameter-value :v t)
#|Warning: set-parameter-value called with no current model. |#
:NO-MODEL

System Parameters

System parameters are similar to general parameters, but they are only used for configuring the operation of the ACT-R software itself. They do not have to be connected to any particular module or model and changing one will affect all models. They also retain their settings across a reset or clear-all therefore they will generally only need to be set once if one needs to use them and probably will not be included in a model definition.

Commands

ssp

Syntax:

Arguments and Values:

```
param-name ::= a keyword which names a parameter param-value-pair ::= param-name new-param-value new-param-value ::= a Lisp value to which the preceding param-name is to be set param-value ::= the current value of a param-name
```

Description:

The ssp command is used to set or get the value of the system parameters.

If no parameters are provided, all of the current system parameters are printed to the <u>general-trace</u> and **nil** is returned. For each parameter, its name and current value is printed followed by the default value and any documentation it has.

If all of the parameters passed to ssp are keywords, then it is a request for the current values of those parameters. Those parameters are printed and a list of their values in the order requested is returned. If any of the names are not of valid parameters then a warning is displayed and the keyword :bad-parameter-name is returned for that position in the list.

If there are any non-keyword parameters in the call to ssp and the total number of elements is even, then they are assumed to be pairs of a parameter name and a parameter value. Each of those parameters will be set to the provided value. The return value will be the current settings of those

parameters in the order given unless a parameter value was not an appropriate value. In that case, a warning is printed and the value returned in that position will be the keyword :invalid-value.

If there are non-keywords passed to ssp and the number of items is odd then a warning is displayed and **nil** is returned.

Examples:

```
> (ssp)
:ACT-R-VERSION
                             "7.10-<internal>"
                                                                        default: ...
:ACT-R-MAJOR-VERSION
                                                                        default: ...
                            10
:STARTING-PARAMETERS
                            NIL
                                                                        default: ...
:ACT-R-MINOR-VERSION
                            0
                                                                        default: ...
:MCTRT
                            NIL
                                                                        default: ...
                                                                        default: ...
:MCTS
                            NIL
:SAFE-PERCEPTUAL-BUFFERS
                             (TEMPORAL VISUAL-LOCATION AURAL-LOCATION) default: ...
                                                                        default: ...
:ACT-R-ARCHITECTURE-VERSION 7
:CHECK-ACT-R-VERSION
                                                                        default: ...
                            Τ
NIL
> (ssp :mcts)
(NIL)
> (ssp :mcts 10000)
(10000)
E> (ssp :mcts 'this)
#|Warning: System parameter :MCTS cannot take value (QUOTE THIS) because it must be
positive number or nil. |#
(:INVALID-VALUE)
E> (ssp :bad-name)
(:BAD-PARAMETER-NAME)
E> (ssp :mcts 100 :mctrt)
#|Warning: Odd number of parameters and values passed to ssp. |#
```

get-system-parameter-value

Syntax:

```
get-system-parameter-value param-name -> [ param-value | :bad-parameter-name ]
```

Remote command name:

```
get-system-parameter-value param-name -> [ 'param-value' | :bad-parameter-name ]
```

Arguments and Values:

```
param-name ::= the name of a system parameter param-value ::= the current value for the system parameter param-name
```

Description:

The get-system-parameter-value command is used to get the current value of a system parameter. If param-name is the name of a parameter then the current value for that parameter is returned. If param-name does not name a system parameter then a warning is printed and **:bad-parameter-name** is returned.

Examples:

```
> (get-system-parameter-value :act-r-version)
"7.10-<internal>"
E> (get-system-parameter-value :does-not-exist)
:BAD-PARAMETER-NAME
```

set-system-parameter-value

Syntax:

```
set-system-parameter-value param-name new-value -> [ param-value | :bad-parameter-name | :invalid-value ]
```

Remote command name:

```
set-system-parameter-value param-name 'new-value' -> [ 'param-value' | :bad-parameter-name | :invalid-value ]
```

Arguments and Values:

```
param-name ::= the name of a system parameter
new-value ::= any value which will be set as the new value for param-name
param-value ::= the current value for the parameter param-name
```

Description:

The set-system-parameter-value command is used to set the current value for a system parameter. If param-name is the name of a system parameter and param-value is a valid value for that parameter then the current value for that parameter is set to the new-value provided and the current value is returned (that might not be the same as new-value depending on the parameter). If param-name does not name a system parameter then a warning is printed and **:bad-parameter-name** is returned. If param-value is not a valid value for param-name then a warning is printed and **:invalid-value** is returned.

```
> (set-system-parameter-value :mcts 400)
```

```
E> (set-system-parameter-value :bad-name 1)
#|Warning: Parameter :BAD-NAME is not the name of an available system parameter |#
:BAD-PARAMETER-NAME
E> (set-system-parameter-value :mcts "a")
#|Warning: System parameter :MCTS cannot take value a because it must be positive number or nil. |#
:INVALID-VALUE
```

Parameters

:high-performance

The high-performance system parameter can be set to change the default values for several of the normal parameters as well as to disable the system output (more thouroughly than just setting the <u>:v</u> parameter to **nil**).

The possible values for :high-performance are:

- **nil** normal system operation (the default value)
- **t** disables ACT-R output commands and sets the default values of these parameters as shown: (:ncnar nil :style-warnings nil :model-warnings nil :cmdt nil :lhst nil :rhst nil :stable-loc-names nil :visual-movement-tolerance 0).

The default value is **nil**. This system parameter can only be changed when there are no models defined.

Generating Output

Many of the commands in ACT-R result in output being printed. There is a <u>printing module</u> which can be used to control where and when certain things are printed, and that is described in detail in a separate section. For now the general aspects of the output will be described as well as the commands that are used to generate the output. The generated output is sent through the appropriate signal of the dispatcher described in the <u>ACT-R Output</u> section.

Model Output

Model output is essentially all the things that are printed by a running model. The trace of the model is considered model output as are various internal module specific traces and notices. Model output is usually sent using the <u>model-trace</u> signal, but the <u>printing module</u> has a <u>parameter named :v</u> which allows one to redirect the output elsewhere or disable it.

Command Output

Command output is what gets printed when one calls one of the ACT-R commands, for example the parameter listing when one calls sgp. Command output depends upon there being a current model. By default this is sent using the command-trace, but like model output, it is configurable by a separate printing module <u>parameter named :cmdt</u>. Thus, one could have model output going one place and command output going elsewhere if desired. Often, one does not need or want the printed output from an ACT-R command because only the returned value is important. In those situations, there is a command called <u>no-output</u> that can be used to temporarily disable command output in Lisp.

Warnings

Warnings from ACT-R are always enclosed inside of a Lisp comment block (between the characters #| and |#) and start with "Warning:". The reason they are inside a comment block is so they do not create a problem if someone is using Lisp to read an output file generated by a model trace which might contain warnings. It also distinguishes them from any other warnings that may be generated by the system in Lisp or some other language when accessed remotely. There are two general classes of warnings and they are created with different commands. The first is referred to as model warnings. These are things like "undefined chunk FOO being created with no slots." They inform the modeler of something that was underspecified or unusual within a model. They are generally just hints or suggestions and can often be ignored. In fact, there is a parameter to automatically suppress such

warnings if desired (though if the model is not working as one would expect turning the model warnings back on and reading them carefully is probably a good first thing to look at). The other type is just referred to as a warning, and they are generated when an ACT-R command receives invalid parameters or a more serious issue has occurred e.g. the "... called with no current model" warning. These are usually more important issues and cannot be turned off with a simple switch. Warnings are sent using the warning-trace signal.

Other Output

If one needs to create other output which does not depend upon a model and/or is not a warning, then there is a command for that as well. That output will be sent using the <u>general-trace</u> signal.

Below are the commands that are used by the system for outputting information and which are available to generate output as described above.

Commands

model-output

Syntax:

model-output control-string {args*} -> nil

Remote command name:

model-output output-string

Arguments and Values:

control-string ::= a Lisp format control (a format string or function as returned by the formatter macro) args ::= arguments as required by the control-string provided output-string ::= a string to be output

Description:

Model-output is used to print model related output based on the settings of the current model. Typically, that output will go to the <u>model-trace</u>, but can be redirected by the <u>printing module</u>. The Lisp command will pass the provided control-string and args to format to generate the string to output, but the remote version requires specifying the string to display completely. The output

created will be followed by a new line. The Lisp version does not test the control-string or args for correctness, so any problems will likely trigger an error or warning from the format function.

If there is no current model a warning is printed and no other output is generated.

It always returns nil.

Examples:

```
> (model-output "This is ~A the ACT-R ~d model-output command" "output from" 7)
This is output from the ACT-R 7 model-output command
NIL

E> (model-output "This is ~A the ACT-R ~d model-output command" "output from" 7)
#|Warning: get-module called with no current model. |#
NII
```

meta-p-output

Syntax:

meta-p-output control-string {args*} -> nil

Arguments and Values:

control-string ::= a Lisp format control (a format string or function as returned by the formatter macro) args ::= arguments as required by the control-string provided

Description:

Meta-p-output is used to send the same output to all of the currently defined models. It sends that output using <u>model-output</u> for each model, but only sending out once to each different output destination i.e. if all models are configured to send output to the default location then only one output will occur. It does not test the control-string or args for correctness, so any problems will likely trigger an error or warning from the format function.

It always returns **nil**.

Meta-p-output is used internally for printing the trace because there can be multiple models running concurrently. It is not likely that users or module writers will have need for meta-p-output because it is above the level of a model or module, but it is described because its results are seen when using simultaneous multiple models.

One thing to note about meta-p-output is that it will evaluate the args separately for each stream to which the output is written. If there are no output streams (all models have <u>:v</u> set to **nil** for example) then the args are not evaluated. Thus, if there are any actions with side effects in the args the results could differ when the number of different locations to which output is written changes.

Examples:

```
> (meta-p-output "This is from ~s" "meta-p-output")
This is from "meta-p-output"
NIL

E> (meta-p-output "This is from ~s" "meta-p-output")
#|Warning: No current meta-process in call to meta-p-output |#
NIL
```

command-output

Syntax:

command-output control-string {args*} -> nil

Remote command name:

command-output output-string

Arguments and Values:

```
control-string ::= a Lisp format control (a format string or function as returned by the formatter macro) args ::= arguments as required by the control-string provided output-string ::= a string to be output
```

Description:

Command-output is used to print model related output from user commands based on the settings of the current model. Typically, that output will go to the <u>command-trace</u> but can be redirected by the <u>printing module</u>. The Lisp command will pass the provided control-string and args to format to generate the string to output, but the remote version requires specifying the string to display completely. The output created will be followed by a new line. The Lisp version does not test the control-string or args for correctness, so any problems will likely trigger an error or warning from the format function.

If there is no current model a warning is printed and no other output is generated.

It always returns **nil**.

Command-output is intended for use by things that print in response to being called outside of a model run, like the display of parameters from sgp or the chunk printing from pprint-chunks and can be turned off by the modeler using a parameter or the <u>no-output</u> command.

Examples:

```
> (command-output "A command-output ~s" 'example)
A command-output EXAMPLE
NIL
E> (command-output "A command-output ~s" 'example)
#|Warning: get-module called with no current model. |#
NIL
```

no-output

Syntax:

```
no-output {form*} -> [ result | nil ]
```

Arguments and Values:

```
form ::= a Lisp form to evaluate result ::= the return value from the last form evaluated
```

Description:

No-output is used to disable the command output of the current model while evaluating the forms provided. It returns the value returned by the last form evaluated.

If there is no current model a warning is printed and **nil** is returned.

No-output can be useful if one wants to get the results from an ACT-R command without having to see any of its output and without needing to explicitly disable and then possibly re-enable the <u>command output</u> parameter. The "wrapping" of forms like this macro provides is not something that is possible through the remote interface, but one can suppress the output remotely by not monitoring and then displaying the output signals. However, that is not exactly the same as what happens with no-output since it prevents the output from being generated at all.

```
> (no-output (pprint-chunks))
(EXTERNAL LIGHT-GRAY INTERNAL DIGIT CURRENT FULL FREE BLACK ...)
> (no-output (sqp-fct '(:v :lf)))
```

```
(T 1.0)
E> (no-output (sgp-fct '(:v :lf)))
#|Warning: get-module called with no current model. |#
NTI
```

print-warning

Syntax:

print-warning control-string {args*} -> nil

Remote command name:

print-warning output-string

Arguments and Values:

```
control-string ::= a Lisp format control (a format string or function as returned by the formatter macro) args ::= arguments as required by the control-string provided output-string ::= a string to be output
```

Description:

Print-warning is used to print a warning message using the <u>warning-trace</u>. It passes the provided control-string and args to format to generate an output string which is printed after "#| Warning:" and followed by "|#" and a new line. It does not test the control-string or args for correctness, so any problems will likely trigger an error or warning from the format function.

It always returns **nil**.

Print-warning is intended for use in printing important notices of problems or errors that occurred within a module or command.

Examples:

```
> (print-warning "This is a warning from ACT-R \sima" "!!") #|Warning: This is a warning from ACT-R !! |# NIL
```

model-warning

Syntax:

model-warning control-string {args*} -> nil

Remote command name:

model-warning output-string

Arguments and Values:

```
control-string ::= a Lisp format control (a format string or function as returned by the formatter macro) args ::= arguments as required by the control-string provided output-string ::= a string to be output
```

Description:

Model-warning is used to print a warning message using the <u>warning-trace</u>. It passes the provided control-string and args to format to generate an output string which is printed after "#| Warning:" and followed by "|#" and a new line. It does not test the control-string or args for correctness, so any problems will likely trigger an error or warning from the format function. If there is more than one model currently defined then the warning will also include the name of the model in which the warning was generated. If there is no current model then a warning about that situation is printed instead of the specified warning.

Model-warning differs from print-warning in that it requires a current model and the printing module of that model can suppress the model-warning output through the :model-warnings parameter.

It always returns **nil**.

Model-warning is intended for use when the model causes a problem within a module or a less serious situation has occurred which the modeler might want to be informed about but which may often be safely ignore.

```
> (model-warning "This may not be what you wanted: ~s" 'bad-value)
#|Warning: This may not be what you wanted: BAD-VALUE |#
NIL
> (with-model bar (model-warning "There is more than one model defined."))
#|Warning (in model BAR): There is more than one model defined. |#
NIL
E> (model-warning "This may not be what you wanted: ~s" 'bad-value)
#|Warning: get-module called with no current model. |#
NIL
```

one-time-model-warning

Syntax:

one-time-model-warning tag control-string {args*} -> nil

Remote command name:

model-warning tag output-string

Arguments and Values:

```
tag ::= any Lisp value control-string ::= a Lisp format control (a format string or function as returned by the formatter macro) args ::= arguments as required by the control-string provided output-string ::= a string to be output
```

Description:

One-time-model-warning operates like the <u>model-warning</u> command, except that it also requires specifying a tag which identifies the warning. One-time-model-warning will only output the given warning if this is the first time that tag has been used (as tested with equal) in a call to one-time-model-warning in the current model since the system has been reset.

It always returns **nil**.

Like model-warning, one-time-model-warning is intended for use when the model causes a problem within a module or a less serious situation has occurred which the modeler might need to be informed about but which may often be safely ignore. One-time-model-warning can be used if that situation may occur repeatedly to avoid a new warning being printed each time.

```
1> (one-time-model-warning :demo "This is a warning")
#|Warning: This is a warning |#
NIL

2> (one-time-model-warning :demo "This is a warning")
NIL

3> (one-time-model-warning "different tag" "Another warning")
#|Warning: Another warning |#
NIL

> (with-model bar (one-time-model-warning :other "the ~s warning" 'first))
#|Warning (in model BAR): the FIRST warning |#
NIL

E> (one-time-model-warning :demo "This is a warning")
#|Warning: get-module called with no current model. |#
```

Running the system

Running the system means executing the events that are in the queue of the meta-process. Those

events may lead to other events being scheduled and that will continue until the stopping condition

specified for the command used to run the system is met. There are several commands for running

the system which specify various stopping conditions as well as allowing users to specify arbitrary

stopping conditions. Because it is the meta-process which is run, all of the models that are defined

will be running together, and information about using more than one model at a time is included in

the multiple models section.

The system can run in either a simulated time frame where the events are processed as fast as

possible or in "real time mode" where the execution of the events is synchronized with the passing of

time from some other source. By default, running in real time mode is associated with the actual

passage of time (with a scale factor which can be specified by the modeler) and the model is

constrained to that, but it is possible to synchronize it with other time sources. For now, we will

focus mostly on the simulated time operation.

When running in simulated time the time stamps on the events control the advancement of the clock

in the meta-process. When the meta-process is initialized and whenever it is reset the current time is

set to 0.0. The event with the lowest time stamp is always the next one executed and if that time is

greater than the current time the clock is updated. This allows the system to run much faster than real

time for most models. The important thing to remember is that the timing of the events is produced

by the modules which instantiate the ACT-R theory and thus the predictions of a model do not

depend on how the model is run or the source of the clock.

While the meta-process is running it will print out the events which it executes as they occur. What

is displayed for an event is dependent upon the details of the event itself and the settings of the

printing module for the model which generated the event. That output is referred to as the trace of

the run. That output will be sent to the <u>model-trace</u> using <u>meta-p-output</u>.

Commands & signals

run-start

Signal:

run-start time

135

Arguments and Values:

time ::= the current model time in milliseconds

Description:

The run-start signal is generated every time that the system starts running and provides the current time.

run-stop

Signal:

run-stop time

Arguments and Values:

time ::= the current model time in milliseconds

Description:

The run-stop signal is generated every time that the system stops running and provides the current time.

run

Syntax:

run run-time {real-time?} -> [nil | time-passed event-count break?]

Remote command name:

run

Arguments and Values:

```
run-time ::= a number greater than 0 indicating the number of seconds to run
```

real-time? ::= a generalized boolean to indicate whether to run in real time and possibly the scale for the real time clock (default is **nil**)

time-passed ::= a number indicating the number of seconds in model time which passed during the run event-count ::= a number indicating how many events were executed during this run

break? ::= [**t** | **nil**] indicating whether the run terminated due to a break event

Description:

Run will run the meta-process until there are either no events remaining to execute, run-time seconds have passed, or a break event is executed. If the optional real-time? value is provided with a non-**nil** value then the model will be run in real time mode. If real-time? is a positive number that will be used as a scale for the real time clock (a number greater than one would cause the meta-process to run faster than real time and a number less than one would cause it to run slower than real time).

If run-time is not a number greater than 0 then the meta-process is not run, a warning is printed, and **nil** is returned.

If the meta-process is run, then when one of the end conditions has been met, run will output a line in the trace to indicate which condition terminated the run and it will return three values.

The first value is the number of seconds that passed during this run. The second is a count of the number of events that were executed (which could be greater than the number of lines shown in the trace because some events may have no output), and the last indicates whether or not the run was terminated by a break event. If it was, then the third value will be **t** otherwise it will be **nil**.

Examples:

For these examples the count model from unit 1 of the ACT-R tutorial is the only model defined.

```
> (run 10)
     0.000
             GOAL
                                     SET-BUFFER-CHUNK GOAL FIRST-GOAL NIL
     0.000
             PROCEDURAL
                                     CONFLICT-RESOLUTION
             PROCEDURAL
                                     PRODUCTION-SELECTED START
     0.000
             PROCEDURAL
                                     CONFLICT-RESOLUTION
     0.300
     0.300
                                     Stopped because no events left to process0.3
             _ _ _ _ _
50
NIL
> (run .1 t)
     0.000
             GOAL
                                     SET-BUFFER-CHUNK GOAL FIRST-GOAL NIL
             PROCEDURAL
     0.000
                                     CONFLICT-RESOLUTION
     0.000
             PROCEDURAL
                                     PRODUCTION-SELECTED START
     0.100
             PROCEDURAL
                                     BUFFER-READ-ACTION GOAL
     0.100
             PROCEDURAL
                                     BUFFER-READ-ACTION RETRIEVAL
     0.100
                                     Stopped because time limit reached
0.1
20
NIL
1> (schedule-break .075)
#S(ACT-R-BREAK-EVENT ...)
2> (run 10)
     0.000
             GOAL
                                     SET-BUFFER-CHUNK GOAL FIRST-GOAL NIL
     0.000
             PROCEDURAL
                                     CONFLICT-RESOLUTION
     0.000
             PROCEDURAL
                                     PRODUCTION-SELECTED START
```

```
0.050 PROCEDURAL CONFLICT-RESOLUTION 0.075 ----- BREAK-EVENT

0.075

14

T

E> (run 0) #|Warning: run-time must be a number greater than zero. |#
NIL

E> (run 'foo) #|Warning: run-time must be a number greater than zero. |#
```

run-full-time

Syntax:

run-full-time run-time {real-time?} -> [nil | time-passed event-count break?]

Remote command name:

run-full-time

Arguments and Values:

```
run-time ::= a number greater than 0 indicating the number of seconds to run real-time? ::= a generalized boolean to indicate whether to run in real time and possibly the scale for the real time clock (default is nil) time-passed ::= a number indicating the number of seconds in model time which passed during the run event-count ::= a number indicating how many events were executed during this run break? ::= [ t | nil ] indicating whether the run terminated due to a break event
```

Description:

Run-full-time will run the meta-process until either run-time seconds have passed or a break event is executed. This differs from the run command because unless there is a break event run-full-time will always run for the full run-time specified. If the optional real-time? value is provided with a non-**nil** value then the model will be run in real time mode. If real-time? is a positive number that will be used as a scale for the real time clock (a number greater than one would cause the meta-process to run faster than real time and a number less than one would cause it to run slower than real time).

If run-time is not a number greater than 0 then the meta-process is not run, a warning is printed, and **nil** is returned.

If the meta-process is run, then when one of the end conditions has been met, run-full-time will output a line in the trace to indicate which condition terminated the run and it will return three values.

The first value is the number of seconds that passed during this run. The second is a count of the number of events that were executed (which could be greater than the number of lines shown in the trace because some events may have no output), and the last indicates whether or not the run was terminated by a break event. If it was, then the third value will be **t** otherwise it will be **nil**.

Examples:

For these examples the count model from unit 1 of the ACT-R tutorial is the only model defined.

```
> (run-full-time 1.0)
             GOAL
                                     SET-BUFFER-CHUNK GOAL FIRST-GOAL NIL
     0.000
     0.000
             PROCEDURAL
                                     CONFLICT-RESOLUTION
     0.000
             PROCEDURAL
                                    PRODUCTION-SELECTED START
     0.300
             PROCEDURAL
                                     CLEAR-BUFFER GOAL
     0.300
             PROCEDURAL
                                     CONFLICT-RESOLUTION
                                    Stopped because time limit reached
     1.000
             -----
1.0
51
NIL
1> (schedule-break .55)
#S(ACT-R-BREAK-EVENT ...)
2> (run-full-time 2.0 t)
     0.000
             GOAL
                                     SET-BUFFER-CHUNK GOAL FIRST-GOAL NIL
     0.000
             PROCEDURAL
                                     CONFLICT-RESOLUTION
                                    PRODUCTION-SELECTED START
     0.000
             PROCEDURAL
     0.300
             PROCEDURAL
                                     CONFLICT-RESOLUTION
     0.550
             _ _ _ _ _ _
                                    BREAK-EVENT
0.55
51
Т
E> (run-full-time -1)
#|Warning: run-time must be a number greater than zero. |#
E> (run-full-time "2.0")
#|Warning: run-time must be a number greater than zero. |#
```

run-until-time

Syntax:

run-until-time end-time {real-time?} -> [nil | time-passed event-count break?]

Remote command name:

run-until-time

Arguments and Values:

end-time ::= a number greater than 0 indicating the explicit time at which the run should stop real-time? ::= a generalized boolean to indicate whether to run in real time and possibly the scale for the real time clock (default is **nil**)

time-passed ::= a number indicating the number of seconds in model time which passed during the run event-count ::= a number indicating how many events were executed during this run break? ::= $[t \mid nil]$ indicating whether the run terminated due to a break event

Description:

Run-until-time will run the meta-process until either the specified end-time is reached (which includes the current time already having passed the specified time) or a break event is executed. This differs from the run and run-full-time commands because an explicit time is provided instead of a duration. If the optional real-time? value is provided with a non-**nil** value then the model will be run in real time mode. If real-time? is a positive number that will be used as a scale for the real time clock (a number greater than one would cause the meta-process to run faster than real time and a number less than one would cause it to run slower than real time).

If end-time is not a number greater than 0 then the meta-process is not run, a warning is printed, and **nil** is returned.

If the meta-process is run, then when one of the end conditions has been met, run-until-time will output a line in the trace to indicate which condition terminated the run and it will return three values.

The first value is the number of seconds that passed during this run. The second is a count of the number of events that were executed (which could be greater than the number of lines shown in the trace because some events may have no output), and the last indicates whether or not the run was terminated by a break event. If it was, then the third value will be **t** otherwise it will be **nil**.

Examples:

For these examples the count model from unit 1 of the ACT-R tutorial is the only model defined.

```
1> (run-until-time .125)
     0.000
             GOAL
                                     SET-BUFFER-CHUNK GOAL FIRST-GOAL NIL
     0.000
             PROCEDURAL
                                     CONFLICT-RESOLUTION
                                     PRODUCTION-SELECTED START
     0.000
             PROCEDURAL
     0.100
             PROCEDURAL
                                     BUFFER-READ-ACTION RETRIEVAL
     0.125
                                     Stopped because time limit reached
0.125
21
NIL
2> (run-until-time .1)
     0.125
                                     Stopped because end time already passed
0
```

```
0
NIL
3> (run-until-time 10)
            PROCEDURAL PROCEDURAL
                                     PRODUCTION-FIRED INCREMENT
     0.150
     0.150
             PROCEDURAL
                                     MOD-BUFFER-CHUNK GOAL
     0.300
             PROCEDURAL
                                     CONFLICT-RESOLUTION
    10.000
                                     Stopped because time limit reached
9.875
31
NIL
1> (schedule-break .4)
#S(ACT-R-BREAK-EVENT ...)
2> (run-until-time .5)
     0.000
             GOAL
                                     SET-BUFFER-CHUNK GOAL FIRST-GOAL NIL
             PROCEDURAL
                                     CONFLICT-RESOLUTION
     0.000
     0.000
             PROCEDURAL
                                     PRODUCTION-SELECTED START
                                     CONFLICT-RESOLUTION
     0.300
             PROCEDURAL
     0.400
             -----
                                     BREAK-EVENT
0.4
51
Т
E> (run-until-time -10)
#|Warning: end-time must be a number greater than zero. |#
```

run-until-condition

Syntax:

run-until-condition condition {real-time?} -> [nil | time-passed event-count break?]

Remote command name:

run-until-condition

Arguments and Values:

condition ::= a Lisp function, the name of a Lisp function, or string naming an ACT-R command real-time? ::= a generalized boolean to indicate whether to run in real time and possibly the scale for the real time clock (default is **nil**)

time-passed ::= a number indicating the number of seconds in model time which passed during the run event-count ::= a number indicating how many events were executed during this run break? ::= $[t \mid nil]$ indicating whether the run terminated due to a break event

Description:

Run-until-condition will run the meta-process until either the specified condition returns a non-**nil** value when called, there are no events to process, a break event is executed, or an error occurs calling

the condition. The condition provided will be called before every event that is to be executed and it will be passed one parameter which is the time of the next event in milliseconds. If the optional real-time? value is provided with a non-**nil** value then the model will be run in real time mode. If real-time? is a positive number that will be used as a scale for the real time clock (a number greater than one would cause the meta-process to run faster than real time and a number less than one would cause it to run slower than real time).

If condition is not a valid function or command then the meta-process is not run, a warning is printed, and **nil** is returned.

If the meta-process is run, then when one of the end conditions has been met, run-until-condition will output a line in the trace to indicate which condition terminated the run and it will return three values.

The first value is the number of seconds that passed during this run. The second is a count of the number of events that were executed (which could be greater than the number of lines shown in the trace because some events may have no output), and the last indicates whether or not the run was terminated by a break event. If it was, then the third value will be **t** otherwise it will be **nil**.

Examples:

For these examples the count model from unit 1 of the ACT-R tutorial is the only model defined.

```
> (run-until-condition (lambda (x) nil))
     0.000
             GOAL
                                     SET-BUFFER-CHUNK GOAL FIRST-GOAL NIL
     0.000
             PROCEDURAL
                                     CONFLICT-RESOLUTION
             PROCEDURAL
                                     PRODUCTION-SELECTED START
     0.000
     0.300
             PROCEDURAL
                                     CONFLICT-RESOLUTION
     0.300
                                     Stopped because no events to process
0.3
50
NIL
1> (schedule-break .275)
#S(ACT-R-BREAK-EVENT ...)
2> (run-until-condition (lambda (x) nil))
     0.000
             GOAL
                                     SET-BUFFER-CHUNK GOAL FIRST-GOAL NIL
     0.000
             PROCEDURAL
                                     CONFLICT-RESOLUTION
     0.000
             PROCEDURAL
                                     PRODUCTION-SELECTED START
     0.250
             PROCEDURAL
                                     BUFFER-READ-ACTION GOAL
     0.275
                                     BREAK-EVENT
0.275
45
1> (defvar *count* 0)
*COUNT*
```

```
2 > (defun stop-at-10 (x)
     (> (incf *count*) 10))
STOP-AT-10
3> (run-until-condition 'stop-at-10)
     0.000
             GOAL
                                     SET-BUFFER-CHUNK GOAL FIRST-GOAL NIL
             PROCEDURAL
     0.000
                                     CONFLICT-RESOLUTION
             PROCEDURAL
                                    PRODUCTION-SELECTED START
     0.000
     0.000
             PR0CEDURAL PR0CEDURAL
                                    BUFFER-READ-ACTION GOAL
     0.050
             PROCEDURAL
                                    PRODUCTION-FIRED START
             PROCEDURAL
                                    MOD-BUFFER-CHUNK GOAL
     0.050
     0.050
            PROCEDURAL
                                    MODULE-REQUEST RETRIEVAL
     0.050
                                    Stopped because condition is true
0.05
10
NIL
1> (defun always-nil (x))
ALWAYS-NIL
2> (add-act-r-command "always-nil" 'always-nil "Test fn for run-until-condition example")
"always-nil"
3> (run-until-condition "always-nil")
     0.000
             GOAL
                                     SET-BUFFER-CHUNK GOAL FIRST-GOAL NIL
     0.000
             PROCEDURAL
                                     CONFLICT-RESOLUTION
     0.000
             PROCEDURAL
                                    PRODUCTION-SELECTED START
     0.300
             PROCEDURAL
                                    CONFLICT-RESOLUTION
     0.300
                                     Stopped because no events to process
             -----
0.3
50
NIL
E>: (run-until-condition "not-a-valid-command")
#|Warning: condition must be a function or valid dispatch command string. |#
NTI
```

run-until-action

Syntax:

run-until-action action {real-time?} -> [nil | time-passed event-count break?]

Remote command name:

run-until-action 'action' {real-time?}

Arguments and Values:

action ::= a string or symbol indicating an event action to stop after

real-time? ::= a generalized boolean to indicate whether to run in real time and possibly the scale for the real time clock (default is **nil**)

time-passed ::= a number indicating the number of seconds in model time which passed during the run event-count ::= a number indicating how many events were executed during this run

break? ::= [t | nil] indicating whether the run terminated due to a break event

Description:

Run-until-action will run the meta-process until either an event with an action that matches the one specified has been executed, there are no events to process, or a break event is executed. If the optional real-time? value is provided with a non-**nil** value then the model will be run in real time mode. If real-time? is a positive number that will be used as a scale for the real time clock (a number greater than one would cause the meta-process to run faster than real time and a number less than one would cause it to run slower than real time).

If action is not a symbol or string then the meta-process is not run, a warning is printed, and **nil** is returned.

If the meta-process is run, then when one of the end conditions has been met, run-until-action will output a line in the trace to indicate which condition terminated the run and it will return three values.

The first value is the number of seconds that passed during this run. The second is a count of the number of events that were executed (which could be greater than the number of lines shown in the trace because some events may have no output), and the last indicates whether or not the run was terminated by a break event. If it was, then the third value will be **t** otherwise it will be **nil**.

Because an action for an event can be specified in multiple ways, there are some subtilties in how the given action is compared to an event's action. When specifying an event the action can be provided as a symbol that names a Lisp function, an explicit Lisp function, or a string naming an ACT-R command. Only the actions with symbols and strings can be tested by run-until-action. The important distinction between those is that a symbol is case-insensitive whereas a command string is case-sensitive. If a symbol is provided as the action value then it will be tested in a case-insensitive manner against both symbol and string event actions to determine if it matches. If a string is provided as the action value then it will be tested in a case-sensitive manner if the event's action is a string and in a case-insensitive manner if the event's action is a symbol.

One final thing to note is that what is shown in the trace for an event may not actually be the action itself if the event was scheduled with details to display instead of the action. Therefore, it is possible for the run to continue past an event which has trace output that matches the action provided if that event's action was different from the details displayed.

For these examples the following model is the only model defined and it schedules an event that has a command string as the action:

```
(define-model test
  (goal-focus-fct (car (define-chunks (value 1))))
  (p repeat
      =goal>
       < value 5
        value =v
      !bind! =x (1+ =v)
      =qoal> value =x)
  (schedule-event-relative .175 "get-time" :output nil))
> (run-until-action 'production-fired)
                                     SÉT-BUFFER-CHUNK GOAL CHUNKO NIL
     0.000
             GOAL
     0.000
             PROCEDURAL
                                     CONFLICT-RESOLUTION
     0.050
             PROCEDURAL
                                     PRODUCTION-FIRED REPEAT
     0.050
                                     Stopped because PRODUCTION-FIRED action occurred
0.05
8
NIL
> (run-until-action "production-fired")
     0.000
             GOAL
                                     SET-BUFFER-CHUNK GOAL CHUNKO NIL
             PROCEDURAL
     0.000
                                     CONFLICT-RESOLUTION
     0.050
             PROCEDURAL
                                    PRODUCTION-FIRED REPEAT
     0.050
                                    Stopped because production-fired action occurred
             -----
0.05
NIL
> (run-until-action "Production-Fired")
     0.000
             GOAL
                                     SET-BUFFER-CHUNK GOAL CHUNKO NIL
     0.000
             PROCEDURAL
                                     CONFLICT-RESOLUTION
     0.050
             PROCEDURAL
                                    PRODUCTION-FIRED REPEAT
     0.050
                                     Stopped because Production-Fired action occurred
0.05
NIL
> (run-until-action 'get-time)
                                     SET-BUFFER-CHUNK GOAL CHUNKO NIL
     0.000
             GOAL
     0.000
             PROCEDURAL
                                     CONFLICT-RESOLUTION
     0.050
             PROCEDURAL
                                    PRODUCTION-FIRED REPEAT
             PROCEDURAL
                                     CONFLICT-RESOLUTION
     0.050
     0.100
             PROCEDURAL
                                    PRODUCTION-FIRED REPEAT
     0.100
             PROCEDURAL
                                    CONFLICT-RESOLUTION
     0.150
             PROCEDURAL
                                    PRODUCTION-FIRED REPEAT
     0.150
             PROCEDURAL
                                     CONFLICT-RESOLUTION
     0.175
                                     Stopped because GET-TIME action occurred
> (run-until-action "get-time")
     0.000
             GOAL
                                     SET-BUFFER-CHUNK GOAL CHUNKO NIL
     0.000
             PROCEDURAL
                                     CONFLICT-RESOLUTION
     0.050
             PROCEDURAL
                                    PRODUCTION-FIRED REPEAT
     0.050
             PROCEDURAL
                                     CONFLICT-RESOLUTION
     0.100
             PROCEDURAL
                                    PRODUCTION-FIRED REPEAT
     0.100
             PROCEDURAL
                                     CONFLICT-RESOLUTION
     0.150
             PROCEDURAL
                                    PRODUCTION-FIRED REPEAT
     0.150
             PROCEDURAL
                                     CONFLICT-RESOLUTION
     0.175
                                     Stopped because get-time action occurred
             -----
0.175
26
```

```
> (run-until-action "Get-Time")
     0.000
             GOAL
                                    SET-BUFFER-CHUNK GOAL CHUNKO NIL
     0.000
             PROCEDURAL
                                    CONFLICT-RESOLUTION
     0.050
             PROCEDURAL
                                    PRODUCTION-FIRED REPEAT
     0.050
             PROCEDURAL
                                    CONFLICT-RESOLUTION
    0.100
             PROCEDURAL
                                    PRODUCTION-FIRED REPEAT
             PROCEDURAL
    0.100
                                    CONFLICT-RESOLUTION
    0.150
             PROCEDURAL
                                    PRODUCTION-FIRED REPEAT
                                    CONFLICT-RESOLUTION
    0.150
             PROCEDURAL
                                    PRODUCTION-FIRED REPEAT
    0.200
             PROCEDURAL
    0.200
             PROCEDURAL
                                    CONFLICT-RESOLUTION
                                    Stopped because no events left to process
     0.200
0.2
29
NIL
E> (run-until-action 2)
#|Warning: run-until-action must be given a name(symbol) or a string, but given 2 which is
a FIXNUM. |#
```

run-n-events

Syntax:

run-n-events num-events {real-time?} -> [nil | time-passed event-count break?]

Remote command name:

run-n-events

Arguments and Values:

```
num-events ::= a number greater than 0 indicating the number of events to run
real-time? ::= a generalized boolean to indicate whether to run in real time and possibly the scale for
the real time clock (default is nil)
time-passed ::= a number indicating the number of seconds in model time which passed during the run
event-count ::= a number indicating how many events were executed during this run
```

break? ::= [t | nil] indicating whether the run terminated due to a break event

Description:

Run-n-events will run the meta-process until either num-events have been executed, there are no events to process, or a break event is executed. If the optional real-time? value is provided with a non-**nil** value then the model will be run in real time mode. If real-time? is a positive number that will be used as a scale for the real time clock (a number greater than one would cause the meta-process to run faster than real time and a number less than one would cause it to run slower than real time).

If num-events is not a number greater than 0 then the meta-process is not run, a warning is printed, and **nil** is returned.

If the meta-process is run, then when one of the end conditions has been met, run-n-events will output a line in the trace to indicate which condition terminated the run and it will return three values.

The first value is the number of seconds that passed during this run. The second is a count of the number of events that were executed (which could be greater than the number of lines shown in the trace because some events may have no output), and the last indicates whether or not the run was terminated by a break event. If it was, then the third value will be **t** otherwise it will be **nil**.

Examples:

For these examples the count model from unit 1 of the ACT-R tutorial is the only model defined.

```
> (run-n-events 10)
     0.000
             GOAL
                                     SET-BUFFER-CHUNK GOAL FIRST-GOAL NIL
     0.000
             PROCEDURAL
                                     CONFLICT-RESOLUTION
     0.000
             PROCEDURAL
                                     PRODUCTION-SELECTED START
                                     BUFFER-READ-ACTION GOAL
             PROCEDURAL
     0.000
     0.050
             PROCEDURAL
                                     PRODUCTION-FIRED START
     0.050
             PROCEDURAL
                                     MOD-BUFFER-CHUNK GOAL
     0.050
             PROCEDURAL
                                     MODULE-REQUEST RETRIEVAL
     0.050
                                     Stopped because event limit reached
0.05
10
NIL
> (run-n-events 100)
                                     SET-BUFFER-CHUNK GOAL FIRST-GOAL NIL
     0.000
             GOAL
     0.000
             PROCEDURAL
                                     CONFLICT-RESOLUTION
     0.000
             PR0CEDURAL
                                     PRODUCTION-SELECTED START
     0.300
             PROCEDURAL
                                     CONFLICT-RESOLUTION
     0.300
                                     Stopped because no events to process
             -----
0.3
50
NIL
1> (schedule-break .225)
#S(ACT-R-BREAK-EVENT ...)
2> (run-n-events 50)
     0.000
             GOAL
                                     SET-BUFFER-CHUNK GOAL FIRST-GOAL NIL
     0.000
             PROCEDURAL
                                     CONFLICT-RESOLUTION
     0.000
             PROCEDURAL
                                     PRODUCTION-SELECTED START
     0.200
             PROCEDURAL
                                     BUFFER-READ-ACTION RETRIEVAL
     0.225
                                     BREAK-EVENT
             _ _ _ _ _ _
0.225
35
E> (run-n-events "count")
#|Warning: event-count must be a number greater than zero. |#
```

NIL

run-step

Syntax:

run-step -> time-passed event-count break?

Arguments and Values:

time-passed ::= a number indicating the number of seconds in model time which passed during the run event-count ::= a number indicating how many events were executed during this run break? ::= $[t \mid nil]$ indicating whether the run terminated due to a break event

Description:

Run-step is only available from a Lisp prompt, and it will run the meta-process one event at a time. For each event a summary of the event is printed to *standard-output* and the user is prompted to respond as to whether that event should be executed, deleted, or the run terminated. This will stop for all events, even those which do not get displayed in the trace. The user can also show various debugging information before deciding what to do with the current event. The response is read from *standard-input* and should be one of the characters indicated in the prompt. It will continue to run the model until the user requests it to stop, there are no events remaining, or a break event is executed. Run-step cannot run the model in real time mode.

When one of the end conditions has been met, run-step will output a line in the trace to indicate which condition terminated the run and it will return three values.

The first value is the number of seconds that passed for the model. The second is a count of the number of events that were executed (which could be greater than the number of lines shown in the trace because some events may have no output), and the last indicates whether or not the trial was terminated by a break event. If it was, then the third value will be **t** otherwise it will be **nil**.

Run-step can be a useful function for debugging a model because it allows one to walk through the events one at a time and stop to inspect the state of the system before or after any one.

Examples:

For these examples the count model from unit 1 of the ACT-R tutorial is the only model defined.

```
> (run-step)
```

```
0.000
                         NONE
                                                 CHECK-FOR-ESC-NIL
Next Event:
[A]bort (or [q]uit)
[D]elete
[S]how event queue
[W]aiting events
[B]uffer contents
[V]isicon
[R]eport buffer status
[E]xecute
Next Event:
                 0.000
                         GOAL
                                                 SET-BUFFER-CHUNK GOAL FIRST-GOAL NIL
[A]bort (or [q]uit)
[D]elete
[S]how event queue
[W]aiting events
[B]uffer contents
[V]isicon
[R]eport buffer status
[E]xecute
RETRIEVAL: empty
IMAGINAL: empty
MANUAL: empty
GOAL: empty
IMAGINAL-ACTION: empty
VOCAL: empty
AURAL: empty
PRODUCTION: empty
VISUAL-LOCATION: empty
AURAL-LOCATION: empty
TEMPORAL: empty
VISUAL: empty
                 0.000
Next Event:
                                                 SET-BUFFER-CHUNK GOAL FIRST-GOAL NIL
                         GOAL
[A]bort (or [q]uit)
[D]elete
[S]how event queue
[W]aiting events
B uffer contents
[V]isicon
[R]eport buffer status
[E]xecute
q
     0.000
                                    Stepping stopped
0.0
1
NIL
```

Scheduling Events

The event system that drives ACT-R models is also available to the modeler for use in writing experiments or other interactive actions for the models. In fact, because ACT-R relies on the events to trigger actions such as conflict-resolution, this is the recommended mechanism for creating experiments or making other run-time changes. It is also essential when adding new modules. That is because for other modules to be able to detect that a change has occured (especially the <u>procedural module</u>) those changes need to happen during an event. Therefore any change to a buffer, change of the internal state of a module, or outside action performed by a module should be done through a scheduled event.

When writing experiments for a model, one useful approach is to have the model's actions trigger the events that make changes in such a way that one only needs to call one of the ACT-R "run" functions to execute both the model and the task. That has the benefit of not introducing any discrepancies into the model timing relative to the task and also allows for the task to be run using the provided stepping tools or continued after a break in the model. That is not always practical for a simple model/task and often one may instead use a run, stop, change, run again approach (sometimes referred to as runstop-run or "trial at a time"). However, even when using the run-stop-run approach for a task, it is still important to schedule any direct effects that one makes to buffers or chunks so that the model properly notes the changes.

In general, most of the module commands will schedule some event as a response, but many of the general commands which perform similar actions may not. For example, <u>mod-chunk</u> (a general command) does not generate an event, but <u>mod-focus</u> (a similar command provided by the <u>goal module</u> for updating its buffer) does.

Details of events

Each event has several attributes associated with it that are specified when the event is created with one of the scheduling functions provided. Most of the time the user will not need to work with the events directly, but there are some situations where access to the details of an event may be useful (for instance the event hooks allow one to add functions which see each event before or after it is executed). Here are the attributes which an event has that are accessible by the user.

time

The simulation time at which the event will occur. All times are rounded to the millisecond when the event is created.

priority

When multiple events are scheduled to occur at the same time they are ordered by their priorities. The priority is either a number or one of the keywords :max or :min. An event with a priority of :max will occur before any event at the same time which has a priority other than :max. An event with a priority of :min will occur after any event at the same time which has a priority other than :min. An event with a numeric priority will be executed before any other events at the same time which have a lower numeric priority i.e. numeric priorities are ordered from highest to lowest with no bounds on the numbers given. Events which have both the same time and same priority will occur in the order which they were scheduled --- the earlier scheduled item will occur before the later scheduled one.

action

The function that will be called when this event is executed.

parameters

The list of values which will be passed to the action function when the event is executed.

model

The name of the model in which the event was generated and in which the action will be evaluated.

module

The name of the module which generated the event or the keyword **:none** if no module was specified when the event was created.

destination

If this action is to be sent *to* a specific module, then that module's name can be given as the destination and the instance of that module will be passed as the first parameter to the action. Using this is can be simpler and more informative than just making the instance of the module the first element in the parameters list. However, it is only useful for modules which are defined directly in Lisp at this time.

details

The details can be a string which will be output in the trace for the event. If details are specified that

is all that is printed after the time, model and module. If the details are not specified then the action

and parameters are printed in the trace.

output

Output controls under which trace-detail levels the event will be displayed. It can have a value of t,

high, medium, **low**, or **nil**. A value of **t** or **high** means it will be displayed only for the high trace

detail setting. Nil means not to show it at all. Medium means that it should be shown under both

medium and high trace details, and a value of **low** means it will be shown for any trace detail setting.

The output value effectively specifies the lowest detail setting for which the output will be displayed.

Event Implementation

The specific implementation of an event is not part of the API for ACT-R. The value returned when

creating an event and the values passed through a hook function that provide events will be an integer

that can be used to access the information about that event (referred to as an event-id). There is no

way to modify an event directly once it has been created.

Event Accessors

To access the information from an event using the event-id, a set of accessors are provided. Because

all of the accessors operate the same way they are all presented in one description, and there is a

remote version of each one.

Syntax:

evt-time event-id -> [time | nil], valid

evt-mstime event-id -> [mstime | nil], valid

evt-priority event-id ->[priority | nil], valid

evt-action event-id -> [action | nil], valid

evt-params event-id -> [parameters | nil], valid

evt-model event-id -> [model | nil], valid

evt-module event-id -> [module | nil], valid

evt-destination event-id -> [destination | nil], valid

evt-details event-id -> [details | nil], valid

evt-output event-id -> [output | nil], valid

Arguments and Values:

event-id ::= an integer

time ::= the time of the event in seconds

152

```
mstime ::= the time of the event in milliseconds
priority ::= the event's priority
action ::= the event's action
parameters ::= the event's parameters list
model ::= the name of the model in which the event was generated or nil
module ::= the name of the module which generated the event or :none
destination ::= the name of the module which is the destination for the event or nil
details ::= the details string of the event or nil
output ::= the output value of the event
valid ::= [t | nil ]
```

Description:

Each of the event accessors returns two values. The second one indicates whether there was an event which corresponds to the id provided. If it is **t** then the first value provided will be the appropriate attribute from that event. If there is no event with the event-id provided then both return values will be **nil**.

For the remote version of evt-action the result will always be a string (if there is one), but that string will not always correspond to a valid command. Because it is possible to specify Lisp functions directly in the events using some of the scheduling functions below when reporting such an item to a remote call of evt-action a string which starts with "internal" will be given and the rest of the string will contain the printed form of that function which might be its name or some other output.

```
T

8> (evt-module 7)
:VISION
T

9> (evt-destination 7)
NIL
T

10> (evt-params 7)
(VISUAL-LOCATION CHUNK1)
T

11> (evt-details 7)
NIL
T

> (evt-output 7)
LOW
T

E> (evt-time -4)
NIL
NIL
```

General Event Commands

These commands allow for getting additional information about events related to whether they will be displayed in the trace and how their output will look.

event-displayed-p

Syntax:

event-displayed-p event-id -> [t | nil]

Remote command name:

event-displayed-p

Arguments and Values:

event-id ::= an integer

Description:

Event-displayed-p can be used to determine whether or not an event will be printed in the trace given the current setting of the trace-detail and trace-filter parameters for the model in which it was generated. If the event indicated by the given id will be printed with the current settings of that model's parameters, then **t** is returned and if not then **nil** is returned. If the id does not reference a valid event then **nil** is returned.

This command might be useful when working with the event hooks or for developing an interactive stepper or tracing tool.

Examples:

```
> (let ((event (schedule-event 30 (lambda ()) :output 'medium)))
      (no-output (sgp :trace-detail high))
      (format t "trace-detail high output medium: ~S~%" (event-displayed-p event))
      (no-output (sgp :trace-detail medium))
      (format t "trace-detail medium output medium: ~S~%" (event-displayed-p event))
      (no-output (sgp :trace-detail low))
      (format t "trace-detail low output medium: ~S~%" (event-displayed-p event)))
trace-detail high output medium: T
trace-detail medium output medium: T
trace-detail low output medium: NIL
E> (event-displayed-p 'not-an-event)
NIL
```

format-event

Syntax:

format-event event-id -> [event-string | nil]

Remote command name:

format-event

Arguments and Values:

```
event-id ::= an integer identifying an ACT-R event event-string ::= a string that contains the text that would be printed for this event in the trace
```

Description:

Format-event can be used to get a string with the representation of what the provided event will look like in the trace when it is executed. If the event-id does not correspond to a valid ACT-R event then **nil** is returned.

This would likely be used with the development of additional stepping tools or a data logger which was tied into the event hooks to be able to record and/or display an event independently of the trace.

Scheduling Commands

Events can be generated using a variety of scheduling functions described here, as well as automatically by certain module commands. There are three different types of events that can be generated: model events, maintenance events, and break events. Model events are actions which are generated by the cognitive modules or outside actions which the model may need to detect. Maintenance events are used for actions which are not of importance to the model itself. Break events are a special type of maintenance event which have no actions other than to terminate the current run of the model.

Events can be scheduled immediately based for a specified time, or their scheduling can be delayed until a specified condition is met (referred to as waiting events). A waiting event may also specify whether it should respond to only the first event that satisfies its condition or whether it will continue to respond to new events that are scheduled and possibly change its scheduling as new events occur. A waiting event which continues to update its scheduled position as new events occur is referred to as a dynamic event. A dynamic event will always follow the earlest event (closest to the current time) which satisfies its waiting condition.

There are two differences between model and maintenance events. The first is an indirect difference. Waiting events can be specified to consider any event or only model events when determing whether to stop waiting and be scheduled. The events which are scheduled by the cognitive modules that might need to wait for other events (in particular the conflict-resolution event of the procedural module) will only consider model events because those are the actions which are meaningful to the model(s) being run. The other difference is that a maintenance event may specify a command as a precondition to determine whether or not it will occur. When a maintenance event with a precondition is the next event in the queue its precondition is called with the parameters for the event. If the precondition returns a value other than **nil** then the event is executed as normal. If the precondition returns **nil** then the event is removed from the queue and not executed. That is another reason why waiting events should typically only check model events. With the current implementation of the scheduling system, a waiting event stops waiting and gets scheduled when an event which satisfies its waiting condition is scheduled. If the event which caused the waiting event to be scheduled is a maintenance event and its precondition causes it to be ignored when it is its time to be executed the scheduler does not currently have a way to "unschedule" the event which had been waiting and was scheduled because of that maintenance event.

When a new event is scheduled all of the waiting events will be tested to determine if the new event satisfies the conditions for which those events are waiting and may schedule them to occur. If any were scheduled, then the waiting events will be tested again based on those scheduled events, and that will continue until no new events are scheduled. In addition to that, any waiting event which was marked as being dynamic and which has already been scheduled will test the new events to see if the dynamic event should be rescueduled because of the new events.

When an event's action is executed the current model will be set to the model which generated the event if there was one (only break events can be created without a current model). When working with a single model that does not make a difference, but in the context of multiple models it means that the action function does not typically need to use <u>with-model</u> or make any explicit checks to ensure that it is working in the proper context.

The Lisp versions of the scheduling functions take keyword parameters for providing the features of the event and the remote commands use an options list.

schedule-event, schedule-event-relative, schedule-event-now

Syntax:

```
schedule-event time action {:module module-value} {:destination destination-value} {:priority priority-value} {:params params-value} {:time-in-ms time-units} {:details details-value} {:maintenance maintenance-value} {:precondition precondition-value} {:output output-value} -> [ event-id | nil ] ]

schedule-event-relative delta-time action {:module module-value} {:destination destination-value} {:priority priority-value} {:params params-value} {:time-in-ms time-units} {:details details-value} {:maintenance maintenance-value} -> [ event-id | nil ] ]

schedule-event-now action {:module module-value} {:destination destination-value} {:priority priority-value} {:params params-value} {:details details-value} {:priority priority-value} {:params params-value} {:details details-value} {:precondition-value} {:pre
```

Remote command name:

```
schedule-event time action { < module module-value, destination destination-value, priority priority-value, params params-value, time-in-ms time-units, details details-value, maintenance maintenance-value, precondition precondition-value, output output-value > }

schedule-event-relative delta-time action { < module module-value, destination destination-value, priority priority-value, params params-value, time-in-ms time-units,
```

precondition precondition-value, output output-value > }

schedule-event-now action { < module module-value, destination destination-value, priority priority-value,

details details-value, maintenance maintenance-value,

params params-value, details details-value,
maintenance maintenance-value, precondition precondition-value,
output output-value > }

Arguments and Values:

```
time ::= a number representing an absolute time for the event in seconds or milliseconds delta-time ::= a number in seconds or milliseconds indicating the delay before executing the event action ::= a valid command indicating the action to be evaluated module-value ::= the module's name which is scheduling the event (default :none) destination-value ::= the name of a module priority-value ::= [:max | :min | a number] (default 0) params-value ::= a list of values to pass to the action (default nil) time-units ::= a generalized boolean indicating whether the time is set in milliseconds (default is nil) maintenance-value ::= generalized boolean indicating whether this is a maintenance event (default nil) precondition-value ::= [ nil | precondition ] (default nil) precondition ::= a valid command with a pretest to try before the action details-value ::= a string to output in the trace or nil (default nil) output-value ::= [t | high | medium | low | nil] (default t) event-id ::= an integer which can be used to reference the event created
```

Description:

These functions sechedule events to occur at particular times in the current model using the attributes provided, and an id which can be used to access the event will be returned. Schedule-event creates the event at the specific time provided, schedule-event-relative creates the event to occur at the indicated time from the current time, and schedule-event-now creates the event at the current time.

If any of the parameters are invalid or there is no current model then a warning is printed, no event is scheduled, and **nil** is returned.

```
1> (mp-time)
3.0

2> (mp-show-queue)
Events in the queue:
0

3> (schedule-event 3.5 'goal-focus-fct :priority :min :params '(new-goal) :output nil)
5

4> (schedule-event 3.5 'define-chunks-fct :priority 0 :params '((new-goal)))
6

5> (schedule-event-relative 1.0 (lambda()) :details "Dummy function" :maintenance t)
7

6> (schedule-event-now (lambda()))
8

7> (mp-show-queue)
Events in the queue:
```

```
3.000
             NONE
                                    #<Interpreted Function (unnamed)>
    3.000
            PROCEDURAL
                                    CONFLICT-RESOLUTION
                                    DEFINE-CHUNKS-FCT (NEW-GOAL)
     3.500
            NONE
    3.500
            NONE
                                    GOAL-FOCUS-FCT
    4.000
            NONE
                                    Dummy function
5
E> (schedule-event 'bad-time (lambda ()))
#|Warning: Time must be non-negative number. |#
E> (schedule-event 0 'bad-function-name)
#|Warning: Can't schedule BAD-FUNCTION-NAME not a function or function name. |#
E> (schedule-event 10 'goal-focus :priority :min :params '(new-goal-chunk) :output nil)
#|Warning: Can't schedule GOAL-FOCUS because it is a macro and not a function. |#
E> (schedule-event 0 (lambda ()) :priority 'value)
#|Warning: Priority must be a number or :min or :max. |#
E> (schedule-event 0 (lambda (x)) :params 10)
#|Warning: params must be a list. |#
NIL
E> (schedule-event 0 'pprint)
#|Warning: schedule-event called with no current model. |#
NIL
```

schedule-event-after-module

Syntax:

```
schedule-event-after-module action {:module module-value} {:destination destination-value} {:params params-value} {:details details-value} {:delay delay-value} {:maintenance maintenance-value} {:dynamic dynamic-value} {:precondition precondition-value} {:output output-value} {:include-maintenance include-maintenance-value} -> [ event-id | nil ] {[ t | nil | :abort]}
```

Remote command name:

```
schedule-event-after-module action { < module module-value, destination destination-value, params params-value, details details-value, delay delay-value, maintenance maintenance-value, dynamic dynamic-value, output output-value, precondition precondition-value, include-maintenance include-maintenance-value > }
```

Arguments and Values:

```
after-module ::= the name of a module action ::= a valid command indicating the action to be evaluated module-value ::= the name of the module scheduling the event (default :none) destination-value ::= the name of a module params-value ::= a list of values to pass to the action (default nil)
```

```
maintenance-value ::= generalized boolean indicating whether this is a maintenance event (default nil) precondition-value ::= [ nil | precondition ] (default nil) precondition ::= a valid command for a pretest to evaluate before the action details-value ::= a string to output in the trace or nil (default nil) output-value ::= [t | high | medium | low | nil] (default t) delay-value ::= [t | nil | :abort ] (default t) include-maintenance-value ::= a generalized boolean indicating whether to consider maintenance events when determining when to schedule this event (default nil) dynamic-value ::= generalized boolean indicating whether to allow rescheduling (default nil) event-id ::= an integer which can be used to reference the event created
```

Description:

Schedule-event-after-module creates a new event using the supplied parameters for its corresponding attributes and the current model for its model.

If there is an event currently in the event queue with the module name of after-module and the same model as the current model and either include-maintenance-value is true or the event is not a maintenance event, then this new event is placed into the event queue at the time of the next such matching event (lowest time) with a priority of **:min**.

If there is no event in the event queue that matches on model and module of the appropriate event type (model or maintenance), then the value of delay-value determines what happens to the new event.

If delay-value is **t** then the new event is placed into the set of waiting events to be scheduled after an event which matches the conditions necessary to schedule this new event.

If delay-value is **nil** then the new event is added to the event queue for immediate execution. Its time will be set to the current time and its priority will be **:max**.

If delay-value is **:abort** then the new event is discarded without being scheduled or placed into the waiting queue.

A successful schedule-event-after-module returns two values. The first value will be the event id and the second value will be **t** if the event is in the waiting queue, **nil** if it is in the event queue, and **:abort** if it was not scheduled. If there is no current model or any of the parameters are invalid, then no event is scheduled and a single value of **nil** is returned.

```
1> (mp-show-queue)
Events in the queue:
     0.000
             PROCEDURAL
                                     CONFLICT-RESOLUTION
2> (schedule-event-after-module 'procedural (lambda ()) :details "Matches event")
NIL
3> (mp-show-queue)
Events in the queue:
     0.000
             PROCEDURAL
                                      CONFLICT-RESOLUTION
     0.000
             NONE
                                     Matches event
2
4> (schedule-event-after-module :vision (lambda()) :details "no event and wait" :delay t)
Т
5> (mp-show-queue)
Events in the queue:
                                     CONFLICT-RESOLUTION
     0.000
             PROCEDURAL
     0.000
                                     Matches event
             NONE
2
6> (mp-show-waiting)
Events waiting to be scheduled:
   NONE
                           no event and wait Waiting for: (:MODULE :VISION NIL)
1
7> (schedule-event-after-module :motor (lambda()) :details "go now" :delay nil)
NIL
8> (mp-show-queue)
Events in the queue:
     0.000
            NONE
                                     go now
                                     CONFLICT-RESOLUTION
     0.000
             PROCEDURAL PROCEDURAL
     0.000
             NONE
                                     Matches event
3
9> (schedule-event-after-module :motor (lambda()) :details "aborted" :delay :abort)
NIL
: ABORT
E> (schedule-event-after-module 'bad-name (lambda()))
#|Warning: after-module must name a module. |#
NIL
schedule-event-after-change
Syntax:
schedule-event-after-change action {:module module-value} {:destination destination-value}
                           {:params params-value} {:details details-value} {:delay delay-value}
                           {:maintenance maintenance-value} {:dynamic dynamic-value}
```

{:precondition precondition-value} {:output output-value} {:include-maintenance include-maintenance-value}

-> [event-id | nil] {[t | nil | :abort]}

Remote command name:

```
schedule-event-after-change action { < module module-value, destination destination-value, params params-value, details details-value, delay delay-value, maintenance maintenance-value, dynamic dynamic-value, output output-value, precondition precondition-value, include-maintenance include-maintenance-value > }
```

Arguments and Values:

Description:

Schedule-event-after-change creates a new event using the supplied parameters for its corresponding attributes and the current model for its model. If there is any event currently in the event queue with the same model as the current model and either include-maintenance-value is true or the event is not a maintenance event, then this new event is placed into the event queue at the time of the next such matching event (lowest time) with a priority of **:min**.

If there is no event in the event queue that matches on model and is of the appropriate event type (model or maintenance), then the value of delay-value determines what happens to the new event.

If delay-value is **t** then the new event is placed into the set of waiting events to be scheduled after an event which matches the conditions necessary to schedule this new event.

If delay-value is **nil** then the new event is added to the event queue for immediate execution. Its time will be set to the current time and its priority will be **:max**.

If delay-value is **:abort** then the new event is discarded without being scheduled or placed onto the waiting queue.

A successful schedule-event-after-change returns two values. The first value will be the event id and the second value will be **t** if the event is in the waiting queue, **nil** if it is in the event queue, and **:abort** if it was not scheduled. If there is no current model or any of the parameters are invalid, then no event is scheduled and a single value of **nil** is returned.

Examples:

see <u>schedule-even-after-module</u> for similar examples

schedule-periodic-event

Syntax:

```
schedule-periodic-event period action {:module module-value} {:destination destination-value} {:params params-value} {:details details-value} {:initial-delay initial-delay-value} {:priority priority-value} {:maintenance maintenance-value} {:output output-value} {:time-in-ms time-units} -> [ event-id | nil ] {[ t | nil | :abort]}
```

Remote command name:

```
schedule-periodic-event period action { < module module-value, destination destination-value, params params-value, details details-value, initial-delay initial-delay-value, maintenance maintenance-value, priority priority-value, output output-value, time-in-ms time-units > }
```

Arguments and Values:

```
period ::= a number indicating the time after which this action should be evaluated again action ::= a valid command indicating the action to be evaluated module-value ::= the name of the module which is scheduling the event (default :none) destination-value ::= the name of a module priority-value ::= [:max |:min | a number] (default 0) params-value ::= a list of values to pass to the action (default nil) time-units ::= a generalized boolean indicating whether the time is set in milliseconds (default nil) maintenance-value ::= generalized boolean indicating whether this is a maintenance event (default nil) details-value ::= a string to output in the trace or nil (default nil) output-value ::= [t | high | medium | low | nil] (default t) initial-delay-value ::= a number indicating time before the first such event (default 0) event-id ::= an integer which can be used to reference the event created
```

Description:

Schedule-periodic-event creates a new event with a time that is equal to the current time plus initial-delay and using the other supplied parameters for its corresponding attributes and the current model for its model. After that event occurs a new event will automatically be scheduled to occur period seconds (or milliseconds if :time-in-ms is specified as true) after that time with the same parameters as the initial one. That rescheduling will continue every period seconds (or milliseconds) until the event id this function returned is deleted.

If any of the parameters are invalid or there is no current model or current meta-process then a warning is printed, no event is scheduled, and **nil** is returned.

Note that there are actually two events generated for each occurrence of the event described. The first is a maintenance event with the priority provided. It schedules the actual event described with the parameters specified with a priority of **:max** (so that it should be the next event to execute) and also schedules the next periodic event at the appropriate delay.

Examples:

```
1> (schedule-periodic-event 1 (lambda () (model-output "now")) :initial-delay .5)
2> (mp-show-queue)
Events in the queue:
     0.000
             NONE
                                     CHECK-FOR-ESC-NIL
                                     CONFLICT-RESOLUTION
     0.000
             PROCEDURAL
     0.500
             NONE
                                     Periodic-Action Unnamed function 1
3
3> (run 3)
     0.000
             PROCEDURAL
                                     CONFLICT-RESOLUTION
now
     0.500
             PROCEDURAL
                                     CONFLICT-RESOLUTION
now
     1.500
             PROCEDURAL
                                     CONFLICT-RESOLUTION
now
     2.500
                                     CONFLICT-RESOLUTION
             PROCEDURAL
     3.000
                                     Stopped because time limit reached
3.0
11
NIL
E> (schedule-periodic-event nil (lambda ()))
#|Warning: period must be greater than 0. |#
NİL
```

schedule-break, schedule-break-relative

Syntax:

schedule-break time {:details details-value}{:priority priority-value}{:time-in-ms time-units} -> [event-id | nil]
schedule-break-relative delta-time {:details details-value}{:priority priority-value}{:time-in-ms time-units}
-> [event-id | nil]

Remote command name:

schedule-break time {< details details-value, priority priority-value, time-in-ms time-units >} schedule-break-relative delta-time {< details details-value, priority priority-value, time-in-ms time-units >}

Arguments and Values:

```
time ::= a number representing an absolute time for the event delta-time ::= a number representing a time delay before executing the event details-value ::= a string to output in the trace or nil (defaults to nil) priority-value ::= [ :max | :min | a number] (defaults to :max) time-units ::= a generalized boolean indicating whether the time is in milliseconds (default nil) event-id ::= an integer which can be used to reference the event created
```

Description:

Schedule-break creates a new break event at the specified time with the priority-value and details-value provided. Schedule-break-relative creates a new break event at the specified amount of time from the current time with the priority-value and details-value provided. The model of those events will be **nil** (a break event does not exist within a specific model), the module is set to :none, and the output for that event is set to low. A break event does not have an action and is only used to stop the scheduler. That new event is then added to the event queue and its id is returned.

If any of the parameters are invalid then a warning is printed, no event is scheduled, and **nil** is returned.

```
1> (schedule-break 5.5 :details "Stop by this break")
2> (mp-show-queue)
Events in the queue:
     0.000
            NONE
                                    CHECK-FOR-ESC-NIL
     0.000
             PROCEDURAL
                                    CONFLICT-RESOLUTION
     5.500
                                    BREAK-EVENT Stop by this break
3
3> (run-full-time 10)
     0.000 PROCEDURAL
                                    CONFLICT-RESOLUTION
     5.500
                                    BREAK-EVENT Stop by this break
5.5
Т
E> (schedule-break 'bad)
#|Warning: Time must be non-negative number. |#
```

```
NIL
```

```
E> (schedule-break 10 :priority 'bad)
#|Warning: Priority must be a number or :min or :max. |#
```

schedule-break-after-module

Syntax:

```
schedule-break-after-module after-module {:details details-value} {:delay delay-value} {:dynamic dynamic-value} -> [event-id | nil ] {[ t | nil | :abort ]}
```

Remote command name:

```
schedule-break-after-module after-module {< details details-value, delay delay-value, dynamic dynamic-value >}
```

Arguments and Values:

```
after-module ::= the name of a module
details-value ::= a string to output in the trace or nil (defaults to nil)
delay-value ::= [ t | nil | :abort ] (defaults to t)
dynamic-value ::= generalized boolean indicating whether to allow rescheduling (defaults to nil)
event-id ::= an integer which can be used to reference the event created
```

Description:

Schedule-break-after-module creates a new event using the supplied parameters for its corresponding attributes and the current model as its model. That event will be scheduled to occur after the next event of the specified module in the same model as the current one.

If there is an event currently in the event queue with the module name of after-module for the current model then this new break event is placed into the event queue at the time of the next such matching event (lowest time) with a priority of **:min**.

If there is no event in the event queue that matches the model and module, then the delay value determines what happens to the new break event.

If delay-value is **t** then the new break event is placed into the set of waiting events to be scheduled after an event which matches the conditions necessary to schedule this new event.

If delay-value is **nil** then the new break event is added to the event queue for immediate execution. Its time will be set to the current time and its priority will be **:max**.

If delay-value is **:abort** then the new break event is discarded without being scheduled or placed onto the waiting queue.

A successful schedule-break-after-module returns two values. The first value will be the event id and the second value will be **t** if the event is in the waiting queue or **nil** if it is in the event queue. If the event is aborted, the first value will be **nil** and the second value will be **:abort**. If there is an invalid parameter provided then no event is scheduled, a warning is output, and a single value of **nil** is returned.

```
1> (mp-show-queue)
Events in the queue:
    0.000
             NONE
                                    CHECK-FOR-ESC-NIL
     0.000
             PROCEDURAL
                                    CONFLICT-RESOLUTION
2> (schedule-break-after-module 'procedural :details "after procedural")
NIL
3> (mp-show-queue)
Events in the queue:
                                    CHECK-FOR-ESC-NIL
    0.000
            NONE
    0.000
             PROCEDURAL
                                    CONFLICT-RESOLUTION
    0.000
                                    BREAK-EVENT after procedural
             _ _ _ _ _ _
3
4> (schedule-break-after-module :vision :details "waiting for vision")
Т
5> (mp-show-queue)
Events in the queue:
    0.000
            NONE
                                    CHECK-FOR-ESC-NIL
    0.000
             PROCEDURAL
                                    CONFLICT-RESOLUTION
     0.000
                                    BREAK-EVENT after procedural
3
6> (mp-show-waiting)
Events waiting to be scheduled:
                          BREAK-EVENT waiting for vision Waiting for: (:MODULE :VISION T)
1
7> (schedule-break-after-module :vision :details "not waiting on vision" :delay nil)
NIL
8> (mp-show-queue)
Events in the queue:
    0.000
             NONE
                                    CHECK-FOR-ESC-NIL
                                    BREAK-EVENT not waiting on vision
    0.000
    0.000
             PROCEDURAL
                                    CONFLICT-RESOLUTION
    0.000
                                    BREAK-EVENT after procedural
             -----
9> (schedule-break-after-module :vision :delay :abort)
```

```
NIL
: ABORT
10> (mp-show-queue)
Events in the queue:
    0.000 NONE
                                    CHECK-FOR-ESC-NIL
    0.000
                                    BREAK-EVENT not waiting on vision
    0.000
            PROCEDURAL
                                    CONFLICT-RESOLUTION
                                    BREAK-EVENT after procedural
    0.000
11> (mp-show-waiting)
Events waiting to be scheduled:
                          BREAK-EVENT waiting for vision Waiting for: (:MODULE :VISION T)
   _ _ _ _ _
1
E> (schedule-break-after-module :bad)
#|Warning: after-module must name a module. |#
```

schedule-break-after-all

Syntax:

schedule-break-after-all {details} -> event-id

Remote command name:

schedule-break-after-all

Arguments and Values:

```
details ::= a string to output in the trace or nil (defaults to nil) event-id ::= an integer which can be used to reference the event created
```

Description:

Schedule-break-after-all creates a new break event with the provided details. The time for this new event is the greatest time of any event currently in the event queue and its priority is :min. It will be inserted into the event queue such that it will occur after all of the events currently scheduled. The id of the event created is returned.

```
1> (mp-show-queue)
Events in the queue:
    0.000 NONE CHECK-FOR-ESC-NIL
    0.000 PROCEDURAL CONFLICT-RESOLUTION
    9.000 NONE future event

3
2> (schedule-break-after-all "at the end")
```

delete-event

Syntax:

delete-event event-id -> [t | nil]

Remote command name:

delete-event

Arguments and Values:

event-id ::= an integer which was returned by one of the scheduling functions to represent an event

Description:

If event-id represents an event which is currently in either the event queue or the waiting queue then delete-event removes that event from the queue it is in and returns **t**.

If the item is not in either event queue no action is taken and **nil** is returned. If an invalid value is provided a warning is printed and **nil** is returned.

```
1> (schedule-event 4 (lambda ()) :details "the event")
2> (mp-show-queue)
Events in the queue:
    0.000 NONE
                                    CHECK-FOR-ESC-NIL
             PROCEDURAL PROCEDURAL
                                    CONFLICT-RESOLUTION
    0.000
    4.000 NONE
                                    the event
3
3> (delete-event 3)
4> (mp-show-queue)
Events in the queue:
    0.000 NONE
                                    CHECK-FOR-ESC-NIL
    0.000
           PROCEDURAL
                                    CONFLICT-RESOLUTION
5> (delete-event 3)
```

```
NIL
E> (delete-event -1)
NIL
E> (delete-event 'bad)
#|Warning: BAD is not a valid event identifier. |#
```

Event Hooks

In addition to being able to schedule events it is possible to add functions which can monitor the events as they are executed. One can add what is called an "event hook" function which will be passed the event id of each event in the queue either before or after it is executed. The event hook can be used for recording information about what has happened in the model (for instance if one wanted to add an alternate tracing mechanism) or for checking for particular events to occur for data collection or other purposes. When created, a hook function is added to the meta-process and persist across a reset. They are only removed if they are explicitly deleted with the <u>delete-event-hook</u> command and when a call to <u>clear-all</u> happens.

add-pre-event-hook, add-post-event-hook

Syntax:

```
add-pre-event-hook hook-fn {warn-for-duplicate} -> [ hook-id | nil ]
add-post-event-hook hook-fn {warn-for-duplicate} -> [ hook-id | nil ]
```

Remote command name:

add-pre-event-hook add-post-event-hook

Arguments and Values:

```
hook-fn ::= a function name, function, or string of a command which accepts one parameter hook-id ::= a number which is the reference for the hook function that was added warn-for-duplicate ::= a generalized boolean which indicates whether or not to show a warning if the same function is attempted to be put on the event hook again (default is t)
```

Description:

If hook-fn is a valid function or command string which is not already in the set of event hooks indicated (either pre or post) for the meta-process then it will be added to the appropriate set of event hooks. The functions for the pre-event hooks will be called before each event on the queue is

evaluated and the post-hook functions will be called after each event is evaluated. The hook function will be passed the event id of that event as its only parameter.

If the hook function is added to one of the meta-process event hook sets, then a unique hook-id is returned which can be used to explicitly remove that function from the set of event hooks.

If hook-fn is invalid then a warning is printed and **nil** is returned. If hook-fn is already in the indicated set of event hooks then **nil** is also returned and a warning is printed unless warn-for-duplicate is provided as **nil**.

Examples:

This example assumes that the count model from unit 1 of the tutorial is loaded.

```
1> (defun show-event (id)
      (model-output "Hook sees event from module: ~s" (evt-module id)))
SHOW-EVENT
2> (add-pre-event-hook 'show-event)
3> (run .05)
Hook sees event from module: :NONE
Hook sees event from module: GOAL
                                    SET-BUFFER-CHUNK GOAL FIRST-GOAL NIL
     0.000
             GOAL
Hook sees event from module: PROCEDURAL
     0.000
             PROCEDURAL
                                    CONFLICT-RESOLUTION
Hook sees event from module: PROCEDURAL
             PROCEDURAL
                                    PRODUCTION-SELECTED START
     0.000
Hook sees event from module: PROCEDURAL
Hook sees event from module: PROCEDURAL
     0.000
             PROCEDURAL
                                    BUFFER-READ-ACTION GOAL
Hook sees event from module: GOAL
Hook sees event from module: PROCEDURAL
                                    PRODUCTION-FIRED START
    0.050
             PROCEDURAL
Hook sees event from module: PROCEDURAL
             PROCEDURAL
                                    MOD-BUFFER-CHUNK GOAL
    0.050
Hook sees event from module: PROCEDURAL
                                    MODULE-REQUEST RETRIEVAL
     0.050
             PROCEDURAL
Hook sees event from module: PROCEDURAL
    0.050
             PROCEDURAL
                                    CLEAR-BUFFER RETRIEVAL
Hook sees event from module: DECLARATIVE
    0.050
           DECLARATIVE
                                    start-retrieval
Hook sees event from module: PROCEDURAL
    0.050
            PROCEDURAL
                                    CONFLICT-RESOLUTION
     0.050
                                    Stopped because time limit reached
0.05
13
NIL
4> (add-pre-event-hook 'show-event)
#|Warning: SHOW-EVENT is already on the pre-event-hook list not added again |#
5> (add-pre-event-hook 'show-event nil)
NIL
```

```
E> (add-pre-event-hook 'bad)
#|Warning: parameter BAD to add-pre-event-hook is not a function |#
NTL
```

delete-event-hook

Syntax:

delete-event-hook hook-id -> [hook-fn | nil]

Remote command name:

delete-event-hook

Arguments and Values:

```
hook-id ::= a hook function id returned by one of the add event hook functions hook-fn ::= the function, function name, or command string that was removed from the event hook
```

Description:

If the event hook function associated with hook-id is still a member of the set of event hooks in the current meta-process then it is removed from the set of hook functions and the function or function name that was used to create the event hook is returned.

If hook-id does not correspond to the id of an event hook or the event has already been removed from the set of event hooks then **nil** is returned.

Examples:

This example assumes that the count model from unit 1 of the tutorial is loaded.

```
1> (defun show-event (id)
      (model-output "Hook sees event from module: ~s" (evt-module id)))
SHOW-EVENT
2> (add-post-event-hook 'show-event)
3> (run .01)
Hook sees event from module: :NONE
                                    SET-BUFFER-CHUNK GOAL FIRST-GOAL NIL
    0.000
           GOAL
Hook sees event from module: GOAL
    0.000
           PROCEDURAL
                                    CONFLICT-RESOLUTION
Hook sees event from module: PROCEDURAL
    0.000
           PROCEDURAL
                                    PRODUCTION-SELECTED START
Hook sees event from module: PROCEDURAL
Hook sees event from module: PROCEDURAL
           PR0CEDURAL
                                    BUFFER-READ-ACTION GOAL
     0.000
Hook sees event from module: PROCEDURAL
Hook sees event from module: GOAL
Hook sees event from module: :NONE
```

```
Stopped because time limit reached
    0.010
           ----
0.01
7
NIL
4> (delete-event-hook 0)
SHOW-EVENT
5> (run .05)
    0.050
            PROCEDURAL
                                   PRODUCTION-FIRED START
    0.050
            PROCEDURAL
                                   MOD-BUFFER-CHUNK GOAL
    0.050
            PROCEDURAL
                                   MODULE-REQUEST RETRIEVAL
    0.050
            PROCEDURAL
                                   CLEAR-BUFFER RETRIEVAL
    0.050
            DECLARATIVE
                                   start-retrieval
    0.050
            PROCEDURAL
                                   CONFLICT-RESOLUTION
                                   Stopped because time limit reached
    0.060
            ----
0.05
6
NIL
6> (delete-event-hook 0)
NIL
E> (delete-event-hook 'bad)
NIL
```

About the Included Modules and Components

The modules that are included with ACT-R fall into three general categories. The first is system or control modules and components which are not based on the theory and only serve to provide functionality in the software. The second and third categories are the cognitive modules which represent the theory of ACT-R. Those are subdivided into modules which provide the perceptual and motor actions which allow models to interact with an environment and modules which represent cognitive capabilities completely within the model. The only reason for distinguishing between the two types of cognitive modules is that the perceptual and motor modules include an interface for interacting with the world whereas the purely cognitive modules do not.

In addition to the modules there are also <u>components</u> which provide important functionality for the software. The components operate independently of models (unlike modules where each model has its own instance of a module) and are not based on the ACT-R theory – they are all purely a construct of the software system.

Most of the remaining sections of this manual will be describing the modules and components of the system. When describing those items the general operation will be provided along with any parameters and commands that it makes available. For the modules, it will also indicate the buffers which the module has (if any) and the requests and queries which are available through those buffers.

Printing module

The printing module provides the modeler with some control over the level of output which the system provides as well as some options for redirecting output instead of using the standard <u>trace signals</u>. That control is provided through several parameters to configure the output. The commands available for outputting information are described in the <u>Printing and Output</u> section. This is a software module and thus does not have a buffer or affect the results of a model's operation.

Parameters

:cbct

The copy buffer chunk trace parameter. This parameter controls whether or not an event will be shown in the trace indicating that a buffer has made a copy of a chunk. It can take a value of **t** or **nil**.

The default is **nil**.

If it is set to **t** then an event like this will be shown in the trace each time a buffer makes a copy of a chunk:

```
0.135 BUFFER Buffer VISUAL copied chunk TEXTO to TEXTO-0
```

It is always attributed to a module named "buffer" and indicates which buffer made the copy along with the name of the original chunk and the name of the copy. Those events will be shown with the high and medium <u>trace detail</u> settings.

:cmdt

The command trace parameter controls where the <u>command output</u> is displayed.

The possible values for :cmdt are:

- **nil** this turns off the command output for this model
- **t** send the command output to the <u>command trace</u>
- a string it attempts to open a file using that string as the name and if successful appends all command output to that file
- a Lisp stream the command output is sent to that stream

a Lisp pathname – it attempts to open the specified file and if successful it appends all
command output to that file

The default value is t.

If a file is used, it will be opened when the parameter is set and closed when either the parameter is changed again or the model is deleted. Note that for file output the actual output to the file may be buffered in Lisp before being written. Thus, that output file should not be opened or read until the model is done with its output. Resetting or deleting the model will signal that it is done as will setting the condt parameter to some other value.

:model-warnings

The model-warnings parameter controls whether or not <u>model warnings</u> are displayed. It can be set to **t** or **nil**. If it is set to **t**, then the model warnings are shown and if it is set to **nil** then they are not.

The default value is t.

:trace-detail

The trace-detail parameter controls which events are shown in the model's trace. It can be set to one of the values: **high**, **medium**, or **low**. The default value is **medium**.

If it is set to **high**, then all events which have a non-**nil** <u>output setting</u> are displayed. If it is set to **medium** then only those events with a **medium** or **low** output setting are shown, and if it is set to **low**, then only those events with a **low** output setting are shown.

:trace-filter

The trace-filter parameter allows one more detailed control over which events are displayed in the trace. It can be set to a function, function name, string which names a command, or **nil**.

The default is nil.

If it is set to a function or command (which we will referr to as the trace-filter) then the trace-filter must accept one parameter. For each event that will be displayed in the trace given the current :trace-detail setting the trace-filter will be called with the event id of that event as its parameter. If

the trace-filter returns **nil** then that event will not be displayed in the trace. Otherwise, the event will be displayed as usual.

There is one filtering function available with the system which is often useful, called **production-firing-only**. If that is set as the value of :trace-filter it will restrict the trace output to only the production-fired events.

:v

The verbose parameter. The :v parameter controls where the <u>model output</u> is displayed. The trace of the model is included in model output.

The possible values for :v are:

- **nil** this turns off the model output for this model
- **t** send the command output to the <u>model trace</u>
- a string it attempts to open a file using that string as the name and if successful appends all
 model output to that file
- a Lisp stream the model output is sent to that stream
- a Lisp pathname it attempts to open the specified file and if successful it appends all model output to that file

The default value is t.

If a file is used, it will be opened when the parameter is set and closed when either the parameter is changed or the model is deleted. Note that for file output the actual output to the file may be buffered in Lisp before being written. Thus, that output file should not be opened or read until the model is done with its output. Resetting or deleting the model will signal that it is done as will setting the :v parameter to some other value.

Naming Module and Component

There is both a naming module and a naming component to provide the system with a consistent means of generating names of things, particularly chunks. The module is used within models to create names and the component is available outside of the context of a model for generating names. These items guarantee that the system does not duplicate names within a model and that the name returned does not already name a chunk. It also allows for the appropriate garbage collection of names (the uninterning of the underlying symbols) that were generated when the model is reset or deleted if they are not also in use in other models. This module and component only provide functionality for the system – it is not a cognitive module.

The names are generated by appending an increasing counter to the end of a provided name prefix (each prefix has its own counter). An additional benefit of the naming module is that the counters are reset to 0 when the model is reset. Thus, a deterministic model will always result in the same sequence of names being created when it is run after being reset, which can be very useful for debugging a model. Because the <u>random module</u> allows one to set the seed for the pseudo-random numbers the model generates, one can also temporarily make a stochastic model deterministic for debugging.

Parameters

:dcnn

The dynamic chunk name normalizing parameter. The :dcnn parameter works in conjunction with the :ncnar parameter to normalize chunk names. If :ncnar is set to **t** or **delete** then :dcnn controls whether the model will normalize the chunk names while the model runs in addition to normalizing at the end of the run. If :dcnn is set to **t** then the chunk names stored in slots of chunks will be automatically updated whenever chunks are merged such that all chunks hold only the true chunk names of chunks in their slots. It essentially spreads the normalizing out during the run instead of performing it all at the end, but it will not delete any chunks until the end of the run if :ncnar is set to do so. This may be more efficient for some models and may also make debugging easier when a model breaks or while stepping through a run. If :ncnar is set to **nil** then the setting of the :dcnn parameter has no effect on the system.

The default value is t.

:dcsc-hook

The dynamic chunk slot change hook parameter. The :dcsc-hook parameter provides a way for modules or other code to be notified if a chunk is dynamically changed as a result of chunk normalizing. This parameter can be set with a function or command string, and any number of such functions or commands may be set. The reported value of this parameter is a list of all the items which have been set. Whenever a chunk is modified by normalizing, after the normalizing has changed a slot value, each of the items set for this parameter will be called with the name of the chunk that had a slot modified through normalizing regardless of what triggered the normalizing (whether it was automatic or explicitly called).

If the parameter is set to **nil** then all items are removed from the dcsc-hook.

The default value is **nil**.

:ncnar

The normalize chunk names after run parameter. The :ncnar parameter controls whether the model will call <u>normalize-chunk-names</u> after every call to one of the model running functions. If it is set to then normalize-chunk-names will be called (without specifying the unintern parameter). If it is set to the value **delete** then normalize-chunk-names will be called with the unintern parameter true. If it is set to **nil** then normalize-chunk-names will not be called.

Having normalize-chunk-names called can be useful for debugging, but if the model generates a lot of chunks it may take a significant amount of time to complete. Thus for models that generate a lot of chunks, or for which there are several calls to model running functions, setting this parameter to **nil** may improve the system performance.

The value of **delete** is provided as an option for extreme cases where the model is exhausting the computer memory and unable to run. Setting it to **delete** is not recommended for general use because some modules may have internal references to the chunk names which will be made invalid when the uninterning option is used. Extra caution should therefore be used when specifying a value of **delete** for :ncnar.

The default value is t.

:short-copy-names

The :short-copy-names parameter controls how chunk names are created when a chunk is copied. The most common place for this to occur is when a chunk is placed into a buffer and it gets copied automatically. If the parameter is set to **nil** then the copy will have a hyphen and a number appended to it. The number is typically 0, but if that would conflict with another name it will be incremented until it is "safe" (see the new-name command). If this parameter is set to **t** then instead of adding a new hyphen and number when copying a chunk which is itself a copy only the number will be incremented as needed.

Assuming there are no conflicts, with this parameter set to **nil** if a chunk named "chunk" is copied it will be named chunk-0 and if chunk-0 is copied that new chunk will be named chunk-0-0. If this parameter is set to **t** then copying chunk will still result in chunk-0, but copying chunk-0 will result in the name chunk-1. In either case, if a chunk named chunk-0 is created explicitly by the model (it is not a copy of a chunk named chunk) then a copy of that chunk will be named chunk-0-0.

This parameter only really matters if copies of chunks are being made from copies – either directly or through the actions of modules like declarative or vision which may reuse copies of chunks. Its setting should not affect how the model operates with the standard modules because they do not rely on specific chunk names.

The default value is **nil**.

Commands

new-name

Syntax:

new-name {prefix} -> [name-symbol | nil]
new-name-fct {prefix} -> [name-symbol | nil]

Remote command name:

new-name

Arguments and Values:

prefix ::= if provided should be a string or symbol (defaults to "CHUNK" if not given) name-symbol ::= a symbol created by appending a number onto the prefix

Description:

New-name is used to generate unique name symbols (which have been interned) within a model, similar to the Lisp function gentemp. Unlike gentemp, it does not guarantee that the symbol does not already exist. What it does guarantee is that it was not previously returned by new-name within the current run of the model and that it is not currently used to name a chunk in the current model.

When the module is deleted or reset it clears its name space and uninterns any symbols it has generated which are no longer "necessary". By necessary, it means that no instance of the naming module has generated such a name, nor was that symbol interned prior to new-name generating it for the first time.

If there is no current model or a parameter other than a symbol or string is provided then a warning is printed and **nil** is returned.

Anywhere a modeler working in Lisp would consider using gentemp, new-name should probably be used instead to guarantee the automatic cleanup upon reset or model deletion. Note that it is typically not necessary to generate a name for a new chunk because omitting a name in the call to define-chunks results in the chunk getting a name generated by new-name automatically.

```
> (new-name)
CHUNK0
> (new-name temp)
TEMP0
1> (new-name-fct 'fact)
FACT0
2> (new-name-fct "FACT")
FACT1
1> (new-name "temp")
TEMP1
2> (define-chunks (temp2 isa chunk))
(TEMP2)
3> (new-name "temp")
TEMP3
E> (new-name 10)
#|Warning: Invalid parameter passed to new-name. Must be a string or symbol. |#
NIL
E> (new-name)
#|Warning: get-module called with no current model. |#
#|Warning: No naming module available cannot create new name. |#
NIL
```

release-name

Syntax:

```
release-name name -> [t | nil] release-name-fct name -> [t | nil]
```

Remote command name:

release-name

Arguments and Values:

name ::= a symbol which was generated by new-name

Description:

Release-name can be used to possibly unintern symbols which have been generated by new-name. This is the same process which occurs on a reset or deletion of the naming module for symbols generated by new-name, but in some circumstances one may want to perform such a cleanup without resetting. Thus, if the symbol given in name was generated by the new-name command and no instance of the naming module other than the one in the current model has generated such a name and that symbol was not interned prior to new-name generating it for the first time then it is uninterned.

If the symbol is uninterned, then **t** is returned otherwise **nil** is returned.

If there is no current model then a warning is printed and **nil** is returned.

Generally, this command is not necessary because a reset or clear-all will automatically clear out the symbols. However, if one is generating an extremely large number of temporary names with newname it can lead to issues with the size of the symbol table in Lisp and explicitly removing names prior to a reset may be useful.

```
1> (find-symbol "CHUNK0")
NIL
NIL
2> (new-name)
CHUNK0
3> 'chunk1
CHUNK1
4> (find-symbol "CHUNK1")
CHUNK1
: INTERNAL
```

```
5> (new-name)
CHUNK1
6> (release-name-fct 'chunk0)
T
7> (release-name chunk1)
NIL
8> (release-name-fct 'chunk0)
NIL
E> (release-name chunk0)
#|Warning: get-module called with no current model. |#
#|Warning: No naming module available cannot release name CHUNK0. |#
NIL
```

new-symbol

Syntax:

```
new-symbol {prefix} -> [ new-symbol | nil ]
new-symbol-fct {prefix} -> [ new-symbol | nil ]
```

Remote command name:

new-symbol

Arguments and Values:

prefix ::= if provided should be a string or symbol (defaults to "CHUNK" if not given) new-symbol ::= a newly interned symbol created by appending a number onto the prefix

Description:

New-symbol is used to generate and intern a unique symbol, similar to the Lisp function gentemp and the <u>new-name</u> command. Like gentemp, it guarantees that the symbol does not already exist. Unlike the command new-name, it does not guarantee that the numbering is reset within a model because new-symbol operates outside of the context of a model.

When a clear-all happens all of the symbols generated by new-symbol are uninterned.

New-symbol should only be used when one needs a completely new symbol and the name of that symbol is not meaningful to a model (for instance something that might show up in the trace should use new-name), or when names are needed outside of the context of a model.

```
> (new-symbol)
CHUNK-0

1> (new-symbol "temp")
TEMP-0

2> (new-symbol-fct 'temp)
TEMP-1

3> (let (temp-2 temp-3))
NIL

4> (new-symbol temp)
TEMP-4
```

Random module

The random module provides a consistent pseudorandom number generator for the system. It is not dependent on the Lisp random function or the Lisp *random-state* global variable. This makes it consistent across all instances of ACT-R regardless of the Lisp application or OS being used. This is very useful for teaching because it guarantees the output of the tutorial material will be the same for all users. It also makes models and modules easier to debug and verify because the random state can be set with an ACT-R parameter for testing. It also serves to protect the model from any potential weaknesses in the random function of a particular Lisp.

The particular pseudorandom number generator chosen is the Mersenne Twister (as implemented by the mt19937ar.c code) because it is designed for Monte-Carlo simulations. Details can be found at:

http://www.math.sci.hiroshima-u.ac.jp/~m-mat/MT/emt.html

That algorithm is used by some Lisps for the random function already. However, because the internal representations of state differ among Lisps it is still necessary to use the ACT-R random module implementation for consistency of ACT-R across systems.

Parameters

:randomize-time

This parameter can be set to **t**, **nil**, or an integer. It is used by the <u>randomize-time</u> command to determine the range in which a specified time will be randomized. The randomize-time command is used mainly by the perceptual and motor modules to add noise to the action times.

The default value is **nil** which means not to randomize the times. A value of **t** is the same as setting the value to 3.

:seed

This is the current seed for the pseudorandom number generator. It must be a list of two numbers. The first is used to initialize the array used by the Mersenne Twister algorithm and the second is an offset from that starting point where the model should start (or where it currently is if the value is read after the model has been run). Thus, if one is specifying a seed explicitly, the second number

should probably be kept "small" because that many pseudorandom numbers will be generated when the parameter is set to get to the offset point.

There is no default value for the seed parameter. When the module is created in a model it generates a new seed based on the current result of get-internal-real-time. Resetting the model does not return the seed to that point – the random module will continue generating new pseudorandom numbers from the point where it last left off.

Commands

act-r-random

Syntax:

act-r-random limit -> [value | nil]

Remote command name:

act-r-random

Arguments and Values:

limit ::= a positive number (either an integer or floating point)
value ::= a pseudorandom number which is non-negative and less than limit

Description:

Act-r-random will operate like random as defined in the ANSI Lisp specification, except without the optional parameter for a random-state. It uses the seed value from the current model to generate the next random number. Thus unless models explicitly set the same seed value each model will have a different sequence of pseudorandom numbers returned by act-r-random.

It returns a pseudorandom number that is a non-negative number less than limit and of the same type as limit. An approximately uniform choice distribution is used. If limit is an integer, then each of the possible results occurs with (approximate) probability 1/limit.

If an invalid value is passed to act-r-random then a warning is printed and **nil** is returned.

If there is no current model a warning will be printed and a pseudorandom number generated from a special instance of the random module will be returned.

```
1> (sgp :seed)
:SEED (94875970549 0) (default NO-DEFAULT) : Current seed of the random number generator
((94875970549 0))
2> (act-r-random 100)
3> (act-r-random 34.5)
11.947622
4> (act-r-random 1000)
679
5> (act-r-random 0.5)
0.31684825
6> (sgp :seed (94875970549 1))
((94875970549 1))
7> (act-r-random 34.5)
11.947622
8> (act-r-random 1000)
9> (act-r-random 0.5)
0.31684825
E> (act-r-random 'a)
#|Warning: Act-r-random called with an invalid value A |#
E> (act-r-random 2)
#|Warning: get-module called with no current model. |#
act-r-noise
```

Syntax:

```
act-r-noise s -> [ value | nil ]
```

Remote command name:

act-r-noise

Arguments and Values:

```
s ::= a non-negative number
value ::= a pseudorandom number generated as described below
```

Description:

Act-r-noise generates a value from a logistic distribution (approximation of a normal distribution) with a mean of 0 and an s value as given. It does this using the <u>act-r-random</u> function. The s value is related to the variance of the distribution, σ_2 , by this equation:

$$\sigma^2 = \frac{\pi^2}{3} s^2$$

If s is invalid a warning is printed and **nil** is returned.

If there is no current model a warning will be printed and the noise will be based on a pseudorandom number generated from a special instance of the random module (as indicated by act-r-random).

Examples:

```
> (act-r-noise 0)
0.0
> (act-r-noise .5)
0.15807568
> (act-r-noise .5)
1.4271247
E> (act-r-noise 'a)
#|Warning: Act-r-noise called with an invalid s A |#
NIL
E> (act-r-noise .5)
#|Warning: get-module called with no current model. |#
-1.131652
```

randomize-time, randomize-time-ms

Syntax:

```
randomize-time time -> [ time | rand-time ]
randomize-time-ms ms-time -> [ ms-time | ms-rand-time ]
```

Remote command name:

act-r-noise

Arguments and Values:

```
time ::= a number
rand-time ::= a randomized time value
ms-time ::= an integer
ms-rand-time ::= an integer randomized time value
```

Description:

Randomize-time and randomize-time-ms are used to return a number randomly chosen from a uniform distribution around the provided time. They depend on the setting of the <u>:randomize-time</u>

parameter in the current model. If the parameter is set to **nil** then no randomization is done and the given time is returned.

If the :randomize-time parameter is a number or **t** (which means use the default value of 3) then a number randomly chosen from the uniform distribution in the range of:

$$\left[time*\frac{n-1}{n}, time*\frac{n+1}{n}\right)$$

where n is the value of :randomize-time, will be returned. The difference between randomize-time and randomize-time-ms is that the latter requires an integer value an will return an integer result with the bounds being rounded and inclusive of the upper bound.

If time is not a number or there is no current model or meta-process, then a warning is printed and time is returned.

```
1> (sgp :randomize-time nil)
(NIL)
2> (randomize-time 10)
1> (sgp :randomize-time t)
(T)
2> (randomize-time 50)
65.277435
3> (randomize-time 50.0)
58.443718
1> (sgp :randomize-time 100)
(100)
2> (randomize-time 100)
100.1965
3> (randomize-time 100)
99.349
4> (randomize-time-ms 100)
101
5> (randomize-time-ms 100)
6> (randomize-time-ms 100)
E> (randomize-time 'a)
#|Warning: Invalid value passed to randomize-time: A |#
```

```
E> (randomize-time-ms 1.0)
#|Warning: Invalid value passed to randomize-time-ms: 1.0. Value must be an integer. |#
1.0

E> (randomize-time 10)
#|Warning: get-module called with no current model. |#
10
```

History Recorder

There is a module and component in the system which provide a mechanism which modules and components can use to provide the user access to information which has been recorded in some way as well as a mechanism for saving and retrieving that information to/from files. These are not cognitive mechanisms of the system, but may be used by cognitive modules to allow users to access their data.

The basic usage of the history recording is for a module to create a named history source to make that data available. Using that name the modeler can start or stop the recording as needed and get any currently available recorded data from that source, save that data to a file, or read the data from a file. The specific format of the returned or saved data is dependent upon the creator of the history source, but it will be encoded in a string using JSON when returned or saved. [Note however, that when the system is in single-threaded mode JSON encoding will not be used because it does not load the Quicklisp libraries for JSON parsing. Also, writing data to files and reading saved files will not be available in single-threaded mode to avoid any inconsistency in the data files between encodings.]

When the data is saved to a file that data will always be encoded in a JSON object of this form:

```
{"name": "<history-name>",
  "date": "YYYY/MM/DD HH:MM:SS",
  "comment": "<comment>",
  "data": <data>}
```

Where <history-name> is the name of the history source, the date information is the current time when the file is saved, the comment attribute is only included if a comment string was provided when saving the data, and <data> is the JSON string of the current data in the same format as is normally returned for that history source.

Modules and components which have history data that can be recorded will provide the details of that information in their sections of this manual.

Commands

define-history

Syntax:

```
define-history name enable disable status get \{model\text{-based}\} \rightarrow [t \mid nil] define-history-fct name enable disable status get \{model\text{-based}\} \rightarrow [t \mid nil]
```

Remote command name:

define-history

Arguments and Values:

name ::= a string which is used to access this history information
enable ::= a function, function name, or valid command string
disable ::= a function, function name, or valid command string
status ::= a function, function name, or valid command string
get ::= a function, function name, or valid command string

model-based ::= a generalized boolean which indicates whther the data is saved separately by model

Description:

Define-history is used to create a new history source for recording information. It must be passed a string which indicates the name for this history source. It also requires four functions/commands for using that data source. The enable command will be called with no parameters when the record-history command is called for this history source, and the disable command will be called with no parameters when the stop-recording-history command is called. The return value from those commands is ignored and they should start and stop the recording of the history data as appropriate. The status command must return three values which are generalized booleans that represent whether the history source is currently enabled, whether there is any data recorded, and whether the underlying data source is still available. It will be called with no parameters when record-history and stop-recording-history are called to determine if the source is still alive and whether it is currently active. It will be called with all of the optional parameters provided to history-data-available and gethistory-data to determine if there is any data available. The get command will be called with all of the optional parameters passed to get-history-data and it must return a list of data, where each item in that list is also a list with the first item in each list being a number (which is typically a timestamp, but that is not required). That data must also be encodeable in JSON.

If a data source, data processor, or data source constituent part with the given name exists or one or more of the interface parameters is not a valid function or command then no new history source is created, a warning is printed, and **nil** is returned. Otherwise, the new data source is created and a value of **t** is returned.

Examples:

See the examples/history-source directory for real examples. Only the warning messages for invalid use are shown here.

```
E> (define-history 2 valid-fn valid-fn valid-fn valid-fn)
#|Warning: Name for a history source must be a string, but given 2. |#
NIL

E> (define-history "test" bad-fn valid-fn valid-fn valid-fn)
#|Warning: Enable function for a history source must be a valid command, but given BAD-FN. |#
NIL

E> (define-history "test" valid-fn bad-fn valid-fn valid-fn)
#|Warning: Disable function for a history source must be a valid command, but given BAD-FN. |#
NIL

E> (define-history "test" valid-fn valid-fn bad-fn valid-fn)
#|Warning: Status function for a history source must be a valid command, but given BAD-FN. |#
NIL

E> (define-history "test" valid-fn valid-fn bad-fn)
#|Warning: Get data function for a history source must be a valid command, but given BAD-FN. |#
NIL

1> (define-history "test" valid-fn valid-fn valid-fn valid-fn)
T

E> (define-history "test" valid-fn valid-fn valid-fn valid-fn)
#|Warning: Cannot create a history source with name TEST because it is already used. |#
NIL
```

define-history-constituent

Syntax:

define-history-constituent *history name enable disable status* \rightarrow [$t \mid nil$] **define-history-constituent-fct** *history name enable disable status* \rightarrow [$t \mid nil$]

Remote command name:

define-history-constituent

Arguments and Values:

```
history::= a string which is the name of a history source name ::= a string which names a new constituent of the indicated history source enable ::= a function, function name, or valid command string disable ::= a function, function name, or valid command string status ::= a function, function name, or valid command string
```

Description:

Define-history-constituent is used to create a new sub-component of a history source for recording information. It must be passed a string which indicates the name of the history source and a name for this new constituent. It also requires three functions/commands for using that constituent part of the history source. The enable command will be called with no parameters when the record-history command is called for this constituent, and the disable command will be called with no parameters

when the stop-recording-history command is called. The return value from those commands is ignored and they should start and stop the recording of the indicated constutuent part of the history source as appropriate (starting or stopping a constituent part does not automatically start or stop the parent history source). The status command must return three values which are generalized booleans that represent whether the constutuent part is currently enabled, whether there is any data recorded, and whether the underlying data source is still available (currently the second result is never used by any of the history data commands because the parent source is always consulted instead). It will be called with no parameters when record-history and stop-recording-history are called to determine if the source is still alive and whether it is currently active. It will be called with all of the optional parameters provided to history-data-available and get-history-data to determine if there is any data available.

There is no function for getting the data from a constituent part directly. Only the history source can be used to get data, and attempting to get data using a constituent will get the data for its parent history source.

If history does not name an existing data source, a data source, data processor, or constituent with the given name exists, or one or more of the interface parameters is not a valid function or command then no new constituent is created, a warning is printed, and **nil** is returned. Otherwise, the new data source constituent is created and a value of **t** is returned.

Examples:

See the examples/history-source directory for real examples. Only the warning messages for invalid use are shown here.

```
E> (define-history-constituent 3 "new" valid-fn valid-fn valid-fn)
#|Warning: Name for a history stream must be a string, but given 3. |#
NIL

E> (define-history-constituent "buffer-trace" not-string valid-fn valid-fn valid-fn)
#|Warning: Name for a history stream constituent must be a string, but given NOT-STRING. |#
NIL

E> (define-history-constituent "bad" "new-part" valid-fn valid-fn valid-fn)
#|Warning: Cannot create a history stream constituent with name NEW-PART for history stream
BAD because that stream does not exist. |#
NIL

E> (define-history-constituent "buffer-trace" "buffer-trace" valid-fn valid-fn valid-fn)
#|Warning: Cannot create a history stream constituent with name BUFFER-TRACE because it is already used. |#
NIL

E> (define-history-constituent "buffer-trace" "new" bad-fn valid-fn valid-fn)
```

```
#|Warning: Enable function for a history stream constituent must be a valid command, but
given BAD-FN. |#
NIL

E> (define-history-constituent "buffer-trace" "new" valid-fn bad-fn valid-fn)
#|Warning: Disable function for a history stream constituent must be a valid command, but
given BAD-FN. |#
NIL

E> (define-history-constituent "buffer-trace" "new" valid-fn valid-fn bad-fn)
#|Warning: Status function for a history stream constituent must be a valid command, but
given BAD-FN. |#
NIL
```

define-history-processor

Syntax:

define-history-processor *history processor-name processor* \rightarrow [$t \mid nil$] **define-history-processor-fct** *history processor-name processor* \rightarrow [$t \mid nil$]

Remote command name:

define-history-processor

Arguments and Values:

```
history::= a string which is the name of a history source processor-name ::= a string which names a new processor for that history source data processor ::= a function, function name, or valid command string
```

Description:

Define-history-processor is used to create a data processor for history source data. It must be passed a string which indicates the name of the history source and a name for this new processor. It also requires a function for processing the data of the history source. When getting data from a history source using a processor the processor function will be called with the current data from that source and the result of that processing will be returned. Additional parameters can also be passed to that processor function if the process-history-data command is used.

If history does not name an existing data source, a data source, processor, or constituent with the given name exists, or the processor is not a valid function or command then no new processor is created, a warning is printed, and **nil** is returned. Otherwise, the new data source processor is created and a value of **t** is returned.

See the examples/history-source directory for real examples. Only the warning messages for invalid use are shown here.

```
E> (define-history-processor 4 "new" valid-fn)
#|Warning: Name for a history source must be a string, but given 4. |#
NIL
E> (define-history-processor "bad" "new" valid-fn)
#|Warning: Cannot create a history source processor named NEW for stream BAD because that
stream is not defined. |#
NIL
E> (define-history-processor "buffer-trace" bad valid-fn)
#|Warning: Name for a history source processor must be a string, but given BAD. |#
NIL
E> (define-history-processor "buffer-trace" "goal" valid-fn)
#|Warning: Cannot create a history source processor with name GOAL because that is already
the name of a history source item. |#
NIL
E> (define-history-processor "buffer-trace" "new" bad-fn)
#|Warning: Processor function for a history source processor must be a valid command, but
given BAD-FN. |#
NIL
```

history-data-available

Syntax:

```
history-data-available history {param*} -> [t | nil ]
history-data-available-fct history {param*} -> [t | nil ]
```

Remote command name:

history-data-available

Arguments and Values:

```
history::= a string which is the name of a history source, history constituent, or processor param ::= parameter to pass to the history source
```

Description:

History-data-available is used to check whether there is currently any data available from a data source. Any parameters provided are passed to the status function of that data source to determine if there is data available. If the given history name is the name of a processor or a constituent then it is the source which is associated with those items which is checked.

If history does not name an existing data source, processor, or constituent or the data source requires a current model and there is not one then a warning is printed, and **nil** is returned.

If the status function of the named history source (or associated history source when a processor or constituent is given) returns a true second value then **t** is returned, otherwise **nil**. is returned.

Examples:

See the examples/history-source directory for real examples. Only the warning messages for invalid use are shown here.

```
E> (history-data-available 3)
#|Warning: History-data-available given name 3 but names must be strings. |#
NIL

E> (history-data-available "bad")
#|Warning: BAD does not name a history data item in call to history-data-available. |#
NIL

E> (history-data-available "buffer-trace")
#|Warning: Model based history BUFFER-TRACE requires a current model to check for available data. |#
NIL
```

record-history

Syntax:

```
record-history {history*} -> [ t | nil ]*
record-history-fct {history*} -> [ t | nil ]*
```

Remote command name:

record-history

Arguments and Values:

history::= a string which is the name of a history source, history constituent, or processor

Description:

Record-history is used to indicate that one wants data sources to record history information. For each valid name provided the given source (or associated source if a processor is given) will be enabled if it is not already enabled, and the history system will increment its count of requests to record that source. Recording a constituent of a source does not automatically trigger the recording of that source itself, and a warning will be printed if a constituent is enabled to record when the parent source is not enabled. A source will stay enabled until an equal number of stop-recording-history calls are made for it or until a clear-all happens – reset does not stop the recording but may clear the data depending upon the source.

Record-history will return as many values as names it is given, with each return value being associated with the corresponding given item. If a given item is a valid name and that source is successfully enabled then that return value will be **t**. Otherwise it will be **nil** and a warning as to why it was not enabled will be printed.

Examples:

See the examples/history-source directory for real examples. Only the warning messages for invalid use are shown here.

```
E> (record-history 1)
#|Warning: Record-history given name 1 but names must be strings. |#
NIL

E> (record-history "bad")
#|Warning: "bad" does not name a history data source in call to record-history. |#
NIL

E> (record-history "buffer-trace" "bad")
#|Warning: "bad" does not name a history data source in call to record-history. |#
T
NIL

E> (record-history "goal")
#|Warning: Data source constituent GOAL enabled but parent source BUFFER-TRACE is not. |#
T

E> (record-history "buffer-trace")
#|Warning: Cannot enable model-based history data source BUFFER-TRACE when no model is available. |#
NIL
```

stop-recording-history

Syntax:

```
stop-recording-history {history*} -> [t | nil ]* stop-recording-history-fct {history*} -> [t | nil ]*
```

Remote command name:

stop-recording-history

Arguments and Values:

history::= a string which is the name of a history source, history constituent, or processor

Description:

Stop-recording-history is used to indicate that one no longer wants data sources to record history information. For each valid name provided the given source (or associated source if a processor is

given) will have its count of enabling requests (from record-history) decremented, and if there are no longer any pending requests it will be disabled. Stopping the recording a constituent of a source does not affect the recording of that source itself.

Stop-recording-history will return as many values as names it is given, with each return value being associated with the corresponding given item. If a given item is a valid name and that source is now disabled then that return value will be **t**, otherwise it will be **nil**. If there are any problems or unusual situations while stopping a history source a warning will be printed.

Examples:

See the examples/history-source directory for real examples.

```
1E> (stop-recording-history "buffer-trace")
#|Warning: Attempting to stop recording history source BUFFER-TRACE but it hasn't explicitly
been started. |#
2> (record-history "buffer-trace")
3> (record-history "buffer-trace")
4> (stop-recording-history "buffer-trace")
NIL
5> (stop-recording-history "buffer-trace")
E> (stop-recording-history 5)
#|Warning: Stop-recording-history given name 5 but names must be strings.|#
NIL
E> (stop-recording-history "bad")
#|Warning: "bad" does not name a history data source in call to stop-recording-history. |#
NIL
E> (stop-recording-history "buffer-trace")
#|Warning: Cannot disable model-based history data source BUFFER-TRACE when no model is
available. |#
NIL
```

get-history-data

Syntax:

```
get-history-data history {file {param*}} -> [ data | nil ] {comment}
get-history-data-fct history {file {param*}} -> [ data | nil ] {comment}
```

Remote command name:

get-history-data

Arguments and Values:

history ::= a string which is the name of a history source, history constituent, or processor

file ::= a string containing a pathname for a file, a Lisp pathname, or nil

param ::= parameter to pass to the history source

data ::= a string containing a JSON encoding of the data

comment ::= a string

Description:

Get-history-data is used to get the current data from a data source or the saved data from that source that was written to a file. If the name of a data source constituent is provided the parent source is used to get the data, and if a history processor name is provided the data is processed as described for process-history-data with no processor parameters.

If history does not name an existing data source, processor, or constituent or the data source requires a current model and there is not one then a warning is printed, and **nil** is returned.

If the file name is provided as a non-nil value then that value will be used to attempt to open a file and read the data. If there is an error attempting to open or read that file a warning will be printed and **nil** returned. If the file can be read and it contains valid data for the history source indicated then one or two values will be returned. The first value returned will be the data read from that file. If that data was saved with a comment then a second value will be returned which contains the string of that comment. If the file cannot be read or the data it contains is not valid then a warning is printed and **nil** will be returned.

If a file name is not provided or provided as **nil** then the data source is tested to see if it has data available. If it does not have data available a warning is printed and **nil** is returned. If it does have data available then the get data function for that source is passed any parameters which were provided and if that returns valid data then it is converted to a JSON string and returned. Otherwise, a warning will be printed and **nil** returned.

Examples:

See the examples/history-source directory for real examples. Only the warning messages for invalid use are shown here.

```
E> (get-history-data "buffer-trace")
#|Warning: Model based history BUFFER-TRACE requires a current model to get data. |#
NIL
E> (get-history-data 1)
```

```
#|Warning: Get-history-data given name 1 but names must be strings. |#
NIL

E> (get-history-data "bad")
#|Warning: BAD does not name a history data source in call to get-history-data. |#
NIL

E> (get-history-data "buffer-trace" bad)
#|Warning: Error #<TYPE-ERROR BAD cannot be converted to a pathname.> encountered while trying to open file BAD for get-history-data. |#
NIL

E> (get-history-data "buffer-trace" "bad-name")
#|Warning: File "bad-name" could not be found in attempt to get-history-data for BUFFER-TRACE. |#
NIL

E> (get-history-data "buffer-trace")
#|Warning: There is no data available for history data source BUFFER-TRACE because recording was never started. |#
NIL
```

process-history-data

Syntax:

```
process-history-data processor {file {(data-param*) {(processor-param*)}}} -> [ data | nil ]
process-history-data-fct processor {file {(data-param*) {(processor-param*)}}}-> [ data | nil ]
```

Remote command name:

process-history-data

Arguments and Values:

```
processor ::= a string which is the name of a history source processor file ::= a string containing a pathname for a file, a Lisp pathname, or nil data-param ::= a parameter to pass to the history source get data function processor-param ::= a parameter to pass to the processors processing function data ::= a string containing a JSON encoding of the processed data comment ::= a string
```

Description:

Process-history-data is used to get a processed form of the current data from a data source or the saved data from that source that was written to a file. If the name of a data source processor is provided the current data from the parent source is acquired using get-history-data passing it the file and list of data-param values (if provided).

If history does not name an existing data source processor or no valid history data is available then a warning is printed, and **nil** is returned.

If valid data is available then that data along with any processor-params provided is passed to the processors function. If that function returns valid data then it is returned otherwise a warning is printed and **nil** is returned.

Examples:

See the examples/history-source directory for real examples. Only the warning messages for invalid use are shown here.

```
E> (process-history-data 2)
#|Warning: Process-history-data given name 2 but names must be strings. |#
NIL

E> (process-history-data "bad")
#|Warning: BAD does not name a history data processor in call to process-history-data |#
NIL

E> (process-history-data "production-graph-utility")
#|Warning: There is no data available for history data source PRODUCTION-HISTORY because recording was never started. |#
#|Warning: No history data available from the source for processor PRODUCTION-GRAPH-UTILITY |#
NIL
```

save-history-data

Syntax:

```
save-history-data history file {comment {param*}} -> [t | nil ]
save-history-data-fct history file {comment {param*}} -> [t | nil ]
```

Remote command name:

save-history-data

Arguments and Values:

```
history ::= a string which is the name of a history source, history constituent, or processor file ::= a string containing a pathname for a file or a Lisp pathname comment ::= a string param ::= parameter to pass to the history source
```

Description:

Save-history-data is used to save the current data from a data source to a file. If history names an existing data source, processor, or constituent then that name and any parameters provided are passed to get-data-history along with **nil** for the file parameter to get the current data for that item. If it returns valid data then it attempts to open the file indicated for writing (superseding an existing file if

there is one) and if that is successful it writes a JSON object to that file with this format (omitting the comment if one is not provided):

```
{"name": "<history>",
  "date": "YYYY/MM/DD HH:MM:SS",
  "comment": "<comment>",
  "data": <data>}
```

and returns **t**. Otherwise it will print a warning and return **nil**.

Examples:

See the examples/history-source directory for real examples. Only the warning messages for invalid use are shown here.

```
E> (save-history-data 1 "file")
#|Warning: Save-history-data given name 1 but names must be strings. |#
NIL

E> (save-history-data "bad" "file")
#|Warning: BAD does not name a history data source item in call to save-history-data. |#
NIL

E> (save-history-data "buffer-trace" "file")
#|Warning: There is no data available for history data source BUFFER-TRACE because recording was never started. |#
#|Warning: No history data available for BUFFER-TRACE in call to save-history-data. |#
NIL
```

start-incremental-history-data, get-incremental-history-data

Syntax:

```
start-incremental-history-data-fct history size \{file \{param^*\}\} -> [id | nil ] get-incremental-history-data-fct id -> [data-segment | nil ]
```

Remote command name:

start-incremental-history-data get-incremental-history-data

Arguments and Values:

```
history ::= a string which is the name of a history source, history constituent, or processor size ::= a number indicating approximate maximum size of data to send file ::= a string containing a pathname for a file, a Lisp pathname, or nil param ::= parameter to pass to the history source id ::= an integer for accessing data incrementally data-segment ::= a string containing a JSON encoding of a portion of the data
```

Description:

Start-incremental-history-data and get-incremental-history-data can be used to access the data from a data source in segments. That may be necessary when the data from a data source is very large – it is used by the ACT-R Environment because the JSON encoding of some of the history tools' data is several mega-bytes long and difficult to send via the RPC interface.

Calling start-incremental-history-data will pass the history, file, and any parametes to get-history-data to acquire the current data. If that is successful then an integer id value is returned, otherwise it returns **nil**. When that id is passed to get-incremental-history-data it will return a segment of the data where that segment is the next n elements. To compute n, first compute how many segments there are by taking the ceiling of the length of the JSON encoding and dividing by the given size, then n is the floor of the number of elements in the data divided by the number of segments. Thus, it does not guarantee that only size characters will be sent at a time because the individual elements may vary in size, but on average it will send size characters per increment. Once all the data is sent further calls will result in a value of **nil**.

If a file is provided then the first call to get-incremental-history-data with the id will return only the comment string from that file or the empty string if it does not have a comment, and after that it will return the data subsegments.

If an invalid id is provided to get-incremental-history-data then a warning is printed and **nil** is returned.

Examples:

See the examples/history-source directory for real examples. Only the warning messages for invalid use are shown here.

```
E> (start-incremental-history-data-fct 1 10)
#|Warning: Start-incremental-history-data given name 1 but names must be strings. |#
NIL

E> (start-incremental-history-data-fct "bad" 10)
#|Warning: BAD does not name a history data source in call to get-history-data. |#
NIL

E> (get-incremental-history-data-fct 1)
#|Warning: Invalid id 1 given for get-incremental-history-data. |#
NIL
```

Buffer trace module

The buffer trace module provides a history source called "buffer-trace" which records the actions which occur through the buffers while a model runs. It also includes a history constituent for each of the buffers of the system that controls whether the data for that buffer is recorded. By default none of the buffers will be recorded.

The data is recorded at each time in the model at which some event occurs for a buffer. The data format for each record is a list of two items. The first is the time-stamp of the data in milliseconds, and the second is a list of buffer record lists for each of the buffers being recorded. Each buffer record list consists of 11 items:

- A string with the name of the buffer
- A Boolean indicating whether the buffer was busy (as indicated by a 'state busy' query)
- A Boolean indicating whether the buffer was cleared
- A Boolean indicating whither the buffer transitiond from busy to free ('state busy' was true and after that 'state free' became true)
- A Boolean indicating whether the buffer reported an error ('state error' query)
- A Boolean indicating whither the buffer transitiond from error to no error ('state error' was true and after that 'state error' was not true)
- A Boolean indicating whether there was a chunk in the buffer ('buffer full' query)
- A Boolean indicating whether there was a change to the chunk in the buffer (a mod-buffer-chunk action)
- A string containing the details of the last request made to the buffer at that time
- A string containing the name of the last chunk set in the buffer at that time
- A string containing the last buffer notes which were recorded at that time

That history information is used by the graphic tracing tools of the ACT-R Environment and the BOLD computation module, but is also available for the modeler to use as needed.

There are two optional parameters available when getting the buffer-trace data which can be specified as times in seconds to restrict the range of data returned to only those which occurs between those times (inclusive).

Commands

add-buffer-trace-notes

Syntax:

add-buffer-trace-notes buffer notes -> [notes | nil]

Remote command name:

add-buffer-trace-notes Arguments and Values:

```
buffer ::= a string or symbol which should be the name of a buffer notes ::= data which one wants to have stored in the buffer-trace history
```

Description:

The add-buffer-trace-notes command takes two parameters. The first is a symbol or string which should name a buffer and the second is some data to store in the buffer-trace history of the current model at the current time. If buffer is the name of a buffer in the current model then the given notes will be recorded in the buffer-trace history for the named buffer at the current time and notes will be returned. If there is no current model or buffer does not name a valid buffer then the command will print a warning and return **nil**.

If multiple notes are added for the same buffer at the same time only the last one added will be recorded by the buffer-trace. Any notes which are added will also be displayed in the graphic tracing tools of the ACT-R Environment when one places the cursor over an event box in the image.

Examples:

This example was run after loading the count model from unit 1 of the ACT-R tutorial.

```
1> (record-history "buffer-trace" "goal")
Т
2> (run 1)
     0.000
             GOAL
                                     SET-BUFFER-CHUNK GOAL FIRST-GOAL NIL
     0.000
             PROCEDURAL
                                     CONFLICT-RESOLUTION
                                    CLEAR-BUFFER GOAL
     0.300
             PROCEDURAL
     0.300
             PROCEDURAL
                                     CONFLICT-RESOLUTION
     0.300
                                     Stopped because no events left to process
0.3
50
NIL
3> (get-history-data "buffer-trace")
```

```
"[[0,[[\"GOAL\",null,null,null,null,true,null,\"\",\"FIRST-GOAL\",\"\"]]], [50,
[[\"GOAL\", null, null, null, null, true, true, \"\", \"\", \"\"]]], [100, [\"GOAL\", null, null, null, null, true, true, \"\", \"\", \"\"]]], [150, [\"GOAL\", null, null, null, null, true, true, \"\", \"\", \"\"]]], [200, [\"GOAL\", null, null, null, null, true, true, \"\", \"\", \"\"]]], [250, [\"GOAL\", null, null, null, null, true, true, \"\", \"\", \"\"]]], [300, [\"GOAL\", null, true, null, null, true, true, \"\", \"\", \"\"]]]]
4> (reset)
5> (add-buffer-trace-notes 'goal "Added notes")
"Added notes"
6> (run .1)
                                                      SET-BUFFER-CHUNK GOAL FIRST-GOAL NIL
       0.000
                   GOAL
       0.000
                   PROCEDURAL
                                                      CONFLICT-RESOLUTION
       0.000
                   PROCEDURAL
                                                     PRODUCTION-SELECTED START
       0.100
                   PROCEDURAL
                                                     BUFFER-READ-ACTION RETRIEVAL
       0.100
                                                      Stopped because time limit reached
0.1
21
NIL
7> (get-history-data "buffer-trace")
"[[0,[[\"GOAL\",null,null,null,null,true,null,\"\",\"FIRST-GOAL\",\"Added notes\"]]],
[50,[[\"GOAL\",null,null,null,null,true,true,\"\",\"\",\"\"]]], [100,
[[\"GOAL\",null,null,null,null,true,null,\"\",\"\",\"\"]]]]"
8> (reset)
Т
9> (add-buffer-trace-notes 'goal "Lost note")
"Lost note"
10> (add-buffer-trace-notes 'goal "Stored note")
"Stored note"
11> (run .1)
       0.000
                                                      SET-BUFFER-CHUNK GOAL FIRST-GOAL NIL
                   GOAL
       0.000
                   PROCEDURAL
                                                      CONFLICT-RESOLUTION
       0.000
                   PROCEDURAL
                                                      PRODUCTION-SELECTED START
       0.100
                   PROCEDURAL
                                                      BUFFER-READ-ACTION RETRIEVAL
       0.100
                   -----
                                                      Stopped because time limit reached
0.1
22
NIL
12> (get-history-data "buffer-trace")
"[[0,[[\"GOAL\",null,null,null,null,true,null,\"\",\"FIRST-GOAL\",\"Stored note\"]]],
[50,[[\"GOAL\",null,null,null,null,true,true,\"\",\"\",\"\"]]], [100,
[[\"GOAL\",null,null,null,null,true,null,\"\",\"\",\"\"]]]]"
E> (add-buffer-trace-notes 'badname nil)
#|Warning: BADNAME does not name a buffer in the current model no notes added. |#
NIL
E> (add-buffer-trace-notes 'goal "note")
#|Warning: No current model so cannot add notes. |#
NTI
```

Central Parameters Module

This module maintains three parameters of the system and provides no other model relevant components. These parameters are used by more than one of the cognitive modules to control how they operate. Thus, they need to exist outside of any one of them in particular, and may also be referred to by new modules as well. It also provides a system parameter which can be used to effectively overwrite the default value for any parameter.

Technically, this module is not automatically loaded by ACT-R because it is provided in the support directory of the distribution and thus only loaded when needed. Therefore, any module or other file which uses the parameters in this module should ensure that it is available by making a require-compiled call to be safe:

```
(require-compiled "CENTRAL-PARAMETERS" "ACT-R-support:central-parameters")
```

Since the declarative and procedural modules also currently require it that is not actually necessary, but still recommended if one is using these parameters when defining a new module.

This module provides a way for other modules to register that they are using the :esc parameter and note which of their parameters rely on :esc being set to **t**. It will output a warning if :esc is **nil** at the start of a model run when any of those registered parameters have been changed from their default values – the assumption is that for a parameter which uses :esc that parameter's default value is valid when :esc is set to **nil** and any other setting would require :esc to be **t**.

This section will provide the basic details of these parameters. The specific modules which use them will describe the details of how these parameters modify their operations.

This module has no buffer.

Parameters

:er

This is the enable randomness parameter. It specifies how deterministically modules should operate. It can be set to **t** which means act non-deterministically or **nil** which means act deterministically. The default value is **nil**. Generally, the setting of this parameter is used to determine how to break "ties" in a module's processing and it has more impact when :esc is **nil** because when the subsymbolic

parameters are enabled there are not often ties that need to be broken because of noise in the computations.

:esc

This is the enable subsymbolic computations parameter. It specifies whether modules should work in a purely symbolic fashion or whether they should use their full subsymbolic processing. The default value is **nil** which means that modules should be purely symbolic. If it is set to **t**, then modules should use whatever subsymbolic computations they provide.

:ol

This is the optimized learning parameter. It specifies whether modules should use their full computational forms of subsymbolic quantities or use some simplified approximation. Currently, it is only used by the declarative system to control the base-level learning equation, but other modules could also check it as a guide. It can be set to **t**, which means use the optimized (or simplified) form of the computation, **nil**, which means use the full computation, or a positive number, which can be used as a parameter specifying how much optimization to apply. The default value is **t**.

System Parameters

:starting-parameters

The :starting-parameters parameter allows one to set parameters which will be applied at the start of all models that are defined. It can be set to a list of parameter values which are valid for passing to sgp-fct and those parameter values will be set before the code in a model definition is evaluated. If this parameter is set in a .lisp file that is placed into the user-loads directory then those settings will always be made, and that is the recommended use for this parameter.

To be completely safe, one should also make sure that the central-parameters module is loaded using this call before setting the parameter:

```
(require-compiled "CENTRAL-PARAMETERS" "ACT-R-support:central-parameters")
```

particularly if it is being done within the context of a module or extension that is loaded prior to the user-loads directory being processed. However, since the declarative and procedural modules currently also use the central-parameters module it should always be available even without explicitly requiring it.

Commands

register-subsymbolic-parameters

Syntax:

register-subsymbolic-parameters { param*} -> nil

Remote command name:

register-subsymbolic-parameters Arguments and Values:

param ::= a keyword or string containing a keyword which should name a valid parameter

Description:

The register-subsymbolic-parameters command is used to indicate when a module's parameters depend on the :esc parameter being set to **t**. When a model first starts running (time 0) if :esc is set to **nil** and any of the parameters which have been registered in this way have a value other than their default value a warning will be printed like this:

```
#|Warning: Subsymbolic parameters have been set but :esc is currently nil. |#
```

This command only needs to be called once for a given parameter. It does not need to go into the creation or reset functions of a module, and should be called directly after the module definition.

It always returns nil.

```
> (register-subsymbolic-parameters :ul :alpha)
NIL
```

The Procedural System

The procedural system implements the procedural cognitive module of the theory. The procedural system is implemented as three separate modules in the code. Those three modules are the procedural module, the utility module, and the production-compilation module. The procedural module handles the productions' specification and matching at the symbolic level and the conflict resolution among productions which relies on the utility module. The utility module handles the computation of the subsymbolic quantity Utility for the productions and maintains the parameters and history information necessary to do so. Finally, the production-compilation module is responsible for the learning of new productions by the model when it is enabled.

Procedural Module

The procedural module implements the procedural memory system. It provides the commands for specifying productions, a pattern matcher that works in conjunction with the <u>utility module</u> to choose which production to fire, and tools for inspecting and debugging the productions of a model. This module holds a central role in the system because the productions coordinate the interaction between all of the other modules of the theory.

A production is a condition-action pair. The condition consists of a conjunction of patterns to match against the current contents of the buffers and the states of the buffers and modules, and the action is a set of actions to perform which typically consists of modifications to the chunks in the buffers and requests to modules. When all of the constraints in the condition of a production are satisfied it may be selected to fire, and when it fires all of its actions are executed. See the ACT-R tutorial for more details on specifying and using productions.

Conflict Resolution

Only one production can be selected and fired at any time. The process by which the next production to fire is chosen is called conflict resolution. When conflict resolution occurs all productions have their conditions checked to determine which ones match the current state (see the <u>p command</u> and ACT-R tutorial unit 1 for more information on how the matches occur). Among those that match, the one that has the highest utility value will be chosen (see the <u>utility module</u> for details on the utility calculations). If there is a tie for the highest utility value then the setting of the <u>:er parameter</u> determines how that tie is broken. If :er is **t** then the tie is broken randomly. If :er is **nil** then a deterministic process is used such that the same production will be chosen for a given model each time the same tie condition occurs. However, that deterministic process is not specified as part of the procedural module's definition because it is not intended to be a process which one relies on for production ordering or model control, and any change to a model's definition could affect that choice.

The procedural module will automatically schedule conflict-resolution events to perform the conflict resolution process. The first one is scheduled at time 0 and a new one is scheduled after each production fires. If no production is selected during a conflict-resolution event then a new conflict-resolution event is scheduled to occur after the next change occurs. A change in this context is any other <u>non-maintenance event</u>. The module also schedules production-selected and production-fired events as a result of conflict resolution. Those events will indicate the specific production which was selected and fired and will look like this in the trace:

0.000	PROCEDURAL PROCEDURAL	CONFLICT-RESOLUTION
0.000	PROCEDURAL PROCEDURAL	PRODUCTION-SELECTED START
0.050	PROCEDURAL PROCEDURAL	PRODUCTION-FIRED START

There is also a procedural module request event scheduled after the production-selected event. That event will not be shown in the trace and serves to indicate that the procedural module has started an action for purposes of the <u>buffer trace module</u> (the event itself performs no actions). Several other events are scheduled as a result of the production selection and production firing processes. Those will be described under the production creation command \underline{p} .

The production-fired event is scheduled based on the production's specified action time. That defaults to 50ms, but can be changed with parameters (see the <u>utility module</u>). In addition, if one sets the <u>:vpft parameter</u> to **t** then that time has noise added to it using the <u>randomize-time</u> command.

Parameters

:conflict-set-hook

This parameter allows one to specify commands which can intervene in the production selection process. This parameter can be set with a function, function name, or a string naming a command which must accept one parameter, and any number of such items may be set (the reported value of this parameter is a list of all items which have been set). Note, when setting the parameter remotely an embedded string will be required to name a command. During conflict-resolution, after all productions have been matched and have had their utilities calculated, a list of the names of the productions which matched in order of utility (highest first – thus the first production on the list is the one which will be selected unless something intervenes) will be passed to each of the items on the conflict-set-hook list. The return values from the items on the conflict-set-hook list are used as follows:

- If it is the name of a production (either a string or symbol) in the conflict set then that production will be the one selected regardless of the normal conflict resolution mechanism.
- If it is an embedded string, no production will be selected and a warning will be output to the trace indicating that conflict resolution was canceled and the embedded string returned will be provided as a reason in that warning. The next conflict resolution event will be scheduled to occur after the default action time (see the <u>:dat parameter</u>). Note, that because the names may be provided by
- If it is nil then the normal conflict resolution mechanism is used.
- If it is anything else, a warning will be output and the normal mechanism will be used.

If multiple hook functions are set and more than one returns a non-**nil** value a warning will be displayed and the result of one of those non-**nil** values will be used. Which one gets used is picked by an unspecified mechanism. No assumptions should be made as to which will be applied and it may vary from run to run. In general one should not have more than one conflict-set-hook function returning non-**nil**.

If the parameter is set to **nil** then all functions are removed from the conflict-set-hook list.

:crt

The conflict resolution trace parameter can be used to include the details of the conflict resolution process in the trace. If it is set to **t** then after each conflict-resolution event, for each production, it will print out either that the production matches the current state or that it fails to match along with the first condition which failed to match as would be shown by the whynot command.

:cst

The conflict set trace parameter can be used to print the details of the productions in the conflict set during conflict resolution. If it is set to **t** then after each conflict-resolution event the current instantiation of each production that matches is printed in the command trace. The instantiation of a production is the production text with the variables replaced by the specific values they have based on the current buffer contents.

:cycle-hook

This parameter allows one to specify functions to be called automatically when productions fire. This parameter can be set with a function, function name, or a string naming a command which takes one parameter and any number of such functions may be set (the reported value of this parameter is a list of all functions which have been set). Note, when setting the parameter remotely an embedded string will be required to name a command. During the production-fired event each of the functions on the cycle-hook list will be called with the name of the production that is firing as the parameter. The return values of those functions are ignored. If the parameter is set to **nil** then all functions are removed from the cycle-hook list. A function should only be set once. If a specific function is specified more than once as a value for the :cycle-hook parameter a warning will be displayed and a value of **nil** will be returned as the current value in that call to sgp.

:dat

The default action time parameter specifies the default time that it takes to fire a production in seconds. That is the amount of time that passes between a production's selection and fired events. The default value is .05 (50ms) and generally that value is not changed.

:do-not-harvest

This parameter controls the strict harvesting mechanism of the productions. By default all buffers are subjected to the strict harvesting practice, but buffers can be exempted from that by specifying them with the :do-not-harvest parameter. The parameter is set one buffer at a time. The reported value for the parameter is a list of all the buffers which have been set using the parameter. If it is set to **nil** then all buffers will be subjected to strict harvesting. A particular buffer should only be set once and if it is specified again a warning will be displayed and **nil** will be returned as the current value.

:lhst

The left hand side trace parameter controls whether the matching conditions from the selected production are shown in the trace. If this parameter is set to **t** (which is the default) and the trace-detail parameter is set to high then the matching conditions are displayed. If this parameter is set to **nil** or the :trace-detail is medium or low, then such events are not shown.

:ppm

The procedural partial matching parameter controls whether productions are allowed to be selected and fired even if they are not a perfect match to the buffers' current contents. If this parameter is set to a number then production matching is allowed to occur for buffer tests which are not a perfect match to the chunk in the buffer. The default value is **nil** which means productions will only match when the buffer tests are exact matches.

If the procedural partial matching is enabled, then slots tested for equality (slots without a modifier and those with an explicit = modifier) in buffer tests of productions may be considered a match even if the value is not <u>chunk-slot-equal</u> to the current value in the slot of the chunk in the buffer. The partial match will occur if there is a similarity value between the value specified for the slot in the production and the value currently in that slot of the buffer and that similarity is greater than the maximum similarity difference as returned from the declarative module's <u>similarity command</u>.

A production which is not a perfect match will have its utility value decremented for purposes of determining which production to fire, but the production's utility parameters and the learning of

utility are not affected by that decrementing. The default decrement will be that for each slot which is not a perfect match, the matching utility of the production will be adjusted by adding the similarity difference (a negative value) between the specification and the current buffer chunk's slot value multiplied by the value of the :ppm parameter. Thus, when the procedural partial matching is enabled the utility used to determine whether production i should be selected among those that match would be:

$$U'_{i}(t) = U_{i}(t) + \varepsilon + \sum_{j} ppm * similarity(s_{j}, v_{j})$$

Ui(t) is the production's current true utility value \mathcal{E} is the noise which may be added to the utility j is the set of slots for which production i had a partial match s_j is the specification for the slot j in production i v_j is the value in the slot j of the chunk in the buffer

Alternatively, one can use the :ppm-hook parameter to specify a function for computing a custom penalty for mismatched production tests. In that case the expression used in the summation above is overridden by a user specified function.

:ppm-hook

The procedural partial matching hook parameter allows one to specify a function that will compute the utility offset added to a production which does not match the current state exactly when procedural partial matching is enabled. The default value for the parameter is **nil** which results in the offset being computed as described for the :ppm parameter. However, if the parameter is set to a function or string naming a remote command then that item will be passed a production name and a list of mismatch lists, one for each mismatch which occurred while testing the named production. A mismatch list will be a 5 element list consisting of: a buffer name, a slot name, the specified slot value, the actual value in the slot of the chunk in the buffer, and the reported similarity between those two items. If the item called from the hook returns a number that will be added to the production's utility, any other return value will result in the default calculation being added.

:rhst

The right hand side trace parameter controls whether the actions from the fired production are shown in the trace. If this parameter is set to **t** (which is the default) and the <u>:trace-detail parameter</u> is set to high then the production's actions are displayed. If this parameter is set to **nil** or the :trace-detail is

medium or low, then such events are not shown. Note that this only controls the direct actions made by the procedural module. Whether any events generated by other modules as a result of those actions are displayed is controlled by those modules.

:style-warnings

The style warnings parameter controls whether the procedural module reports warnings about possible production issues which do not prevent the production from being created, like requests to a buffer without querying it in the conditions or multiple requests to the same buffer. Style warnings also indicate possible issues among the productions, like requests to a buffer which is not tested in the conditions of other productions or setting/modifying slots which are never tested in any production. If the parameter is **t** (the default value) then additional warnings may be displayed when a model is defined and reset (they will be output using the <u>model-warning command</u>). If it is set to **nil** then those additional warnings will not be displayed.

:use-tree

The use tree parameter controls whether a decision tree is created to use during production matching. If the parameter is **nil** (the default value) then each production is tested individually to determine if it matches. If :use-tree is set to **t**, then when the model is loaded a decision tree is created based on the conditions among the productions and that tree is consulted first in production matching to potentially reduce the set of productions that need to be tested further. This should result in a faster model run time, but does have an initial tree creation cost and requires additional memory to store the tree. That additional time and space used are typically insignificant relative to what it takes to run a model, but in some situations may become a factor.

:vpft

The variable production firing time parameter controls whether the time of a production's firing is constant or variable. If the parameter is **nil** (the default value) then each production takes its specified action time exactly each time it fires. If :vpft is **t**, then the <u>randomize-time command</u> is used to randomize the production's action time. Note that randomize-time depends on the setting of the <u>:randomize-time parameter</u> and if it is **nil** then there will be no randomization.

Production buffer

The procedural module has a buffer called production. It exists for the purpose of allowing the

module to have its state tracked. It never has any chunks placed into it and practically speaking it

does not accept any requests. There is no reason to use the production buffer other than for tracking

the state of the procedural module (typically through the buffer trace module).

Activation spread parameter: :production-activation

Default value: 0.0

Queries

The production buffer only responds to the default queries.

'State busy' will be t when a production is firing (the time between the production-selected and

production-fired events). It will be **nil** at all other times.

'State free' will be **nil** when a production is firing and **t** at all other times.

'State error' will always be **nil**.

Requests

{slot value}*

The production buffer will accept any request without a warning or error, but the request is

completely ignored – no actions are performed regardless of the slots specified.

Commands

p/define-p

Syntax:

p production-definition -> [p-name | **nil**]

p-fct (production-definition) -> [p-name | nil]

define-p production-definition -> [p-name | nil]

define-p-fct (production-definition) -> [p-name | nil]

Arguments and Values:

production-definition ::= p-name {doc-string} condition* ==> action*

p-name ::= a symbol that serves as the name of the production for reference

doc-string ::= a string which can be used to document the production

218

```
condition ::= [buffer-test | query | eval | binding | multiple-value-binding]
action ::= [buffer-modification | request | buffer-clearing | modification-request | buffer-overwrite | eval |
           binding | multiple-value-binding | output | !stop!]
buffer-test ::= =buffer-name> {isa chunk-type} slot-test*
buffer-name ::= a symbol which is the name of a buffer
chunk-type ::= a symbol which is the name of a chunk-type in the model
slot-test ::= {slot-modifier} [slot-name | strict-bound-variable] slot-value
slot-modifier ::= [= | - | < | > | <= | >=]
slot-name ::= a symbol which names a slot
slot-value ::= [ variable | value ]
value ::= any Lisp value
guery ::= ?buffer-name> guery-test*
query-test ::= {-} queried-item query-value
queried-item ::= a symbol which names a valid query for the specified buffer
query-value ::= [ bound-variable | value ]
buffer-modification ::= =buffer-name> [ direct-value | {isa chunk-type} slot-value-pair*]
direct-value ::= [ variable | Lisp symbol ]
slot-value-pair ::= [slot-name | strict-bound-variable] bound-slot-value
bound-slot-value ::= [ bound-variable | value ]
request ::= +buffer-name> [direct-value | (direct-value request-spec*) | {isa chunk-type} request-spec*]
request-spec ::= {slot-modifier} [slot-name | strict-bound-variable | request-parameter] slot-value
request-parameter ::= a Lisp keyword naming a request parameter provided by the specified buffer
buffer-clearing ::= -buffer-name>
modification-request ::= *buffer-name> [ direct-value | {isa chunk-type} slot-value-pair*]
buffer-overwrite ::= @buffer-name> [ direct-value | {isa chunk-type} slot-value-pair*]
eval ::= [!eval! | !safe-eval!] form
binding ::= [!bind! | !safe-bind!] variable form
multiple-value-binding ::= !mv-bind! (variable<sup>+</sup>) form
output ::= !output! [ output-value | ( format-string format-arg*) | (output-value*)]
output-value ::= [ bound-variable | value ]
format-string ::= a Lisp string which may contain format processing characters
format-arg ::= an output-value which will be processed by the format-string
variable ::= a symbol which starts with the character =
strict-bound-variable ::= [ a variable which is used in the slot-value position of a slot-test which has
                            either no slot-modifier or the = slot-modifier |
                         the variable naming a buffer at the head of a buffer-test ]
bound-variable ::= [ strict-bound-variable | a variable bound through binding or multiple-value-binding ]
form ::= [ a valid Lisp form | remote-form ]
remote-form ::= ("command" {argument}*)
command ::= the name of a command available through the remote dispatcher
argument ::= any values to pass to command
```

Description:

The p family of commands is used to create the productions for a model. The "define-" commands are provided as a convenience for those using Lisp editors which provide special operations for use

with Lisp forms that start with "define-", and do the same as the corresponding command without the "define-" on the front.

A production must be given a name and can be given an optional documentation string. Then it contains a set of conditions to be tested and a set of actions to be executed when the production is fired. If the specification of the production is syntactically correct, then that production is entered into the procedural memory of the current model, as maintained by the procedural module, and the production's name is returned.

If the name given for a production is already used by a production in the procedural memory of the current model then a warning is printed, the old production is removed, and it is replaced with the newly defined production.

If there is an error in parsing the production then one or more warnings will be output indicating what was wrong, no new production is entered into the procedural memory, and **nil** is returned.

Within a production there are many possible components and each will be described in detail below.

Variables

Productions contain variables to allow for more general matching and actions. The variables are symbols which start with an "=" character e.g. =slot, =answer, =goal. The variables are only relevant within the context of a single production and essentially serve three purposes. The first is to compare two or more values. The second is to copy a value from a condition into an action or specific query. The last is a process referred to as dynamic pattern matching and it allows a variable to be used in the specification of a slot for a buffer test, modification, modification request, or request. A single variable may be used for any/all of those purposes within a production i.e. it could compare two slots to determine that they are the same, copy that value into a request action, and modify a slot using that variable in a different action.

With respect to the dynamic pattern matching there are some restrictions on how the variables can be used. First, there is no search performed in the matching and all variable slot names must be "grounded" by being used as a slot value in an explicitly named slot condition. This means the dynamic pattern matching cannot be used to "find a slot which has a specific value" like this:

```
(p invalid
=buffer>
=slot 150
```

```
)
```

Also, there is only one level of indirection allowed in the use of variablized slot names. Thus it is not possible to do something like this:

However, one may go one level deep across multiple buffers:

Constants

Any symbols used in the production for values which are not variables are assumed to be the names of chunks. If there is not a chunk with such a name at the time the production is created then a new chunk with no slots will automatically be created with that name. Other non-symbol values (strings, numbers, etc) are treated as the corresponding Lisp value.

Modifiers

When testing slot values in conditions and checking queries in a production there are several modifiers which can be used: =, -, <, >, <=, and >=. The = modifier is used to check that the value in the buffer chunk's slot and the value given in the production are equal as determined by the <u>chunk-slot-equal command</u>. If no modifier is provided, then the = modifier is assumed (one usually never sees the = modifier in a production). The – modifier means to negate the test. In a buffer test that means that the buffer chunk's slot does not equal the value specified in the production and for a query it means that the match should succeed if the specified query returns false. The inequality tests (<, >, <=, and =>) can only be used when the values are numbers (the test fails if either of the elements being tested is not a number). If the values are numbers then the test is true if the inequality holds

between the value in the specified slot of the chunk in the buffer and the value specified in the production in that order i.e. if the test is < slot1 10 then the condition matches if the value in the slot1 chunk of the buffer is less than 10.

isa

In many of the conditions and actions of a production it is possible to specify an optional chunk-type using the symbol isa. That chunk-type specification is only used during the definition of the production and does not directly affect the condition or action in which it occurs. It is effectively a declaration for the slots to be used, and unless the chunk-type has default slot-value pairs the same production would result without the chunk-type being specified.

When a chunk-type is specified in that way it allows the production to perform additional syntax checking to determine if the slots specified for that condition or action conform to the slots available for the chunk-type indicated. It also adds any default slot-value pairs specified for that chunk-type into the corresponding condition or action if such a slot is not specified explicitly within the condition or action. If a slot which is not valid for a specified chunk-type is used in a condition or action that will result in a warning being output, but it does not prevent the production from being specified.

Conditions

The conditions of the production are also referred to as the production's left hand side (LHS). They are a conjunction of tests which must all be true for the production to be selected. The order in which the conditions are specified does not matter – there are no ordering constraints and the order in which the tests are performed will not necessarily be the same as they are specified in the production. The only ordering which will be maintained is that eval and binding conditions will be performed in the order specified if possible, and if they have to be reordered a warning will be displayed when the production is defined.

Here is the general description of the conditions that can be tested in a production. When a production is selected during conflict resolution it will generate an event to indicate each buffer match and buffer query condition that it contains and are shown in the trace under the conditions indicated with the <u>:lhst parameter</u>.

buffer test

The buffer-test is the primary condition used in productions. It is comparing the chunk currently in a specific buffer to a pattern provided in the production. Each buffer may have one test specified per production. The slot values in the buffer's chunk are compared to the values specified in the condition using the <u>chunk-slot-equal command</u>, and all of the slots must satisfy the conditions specified for the production to match (except when the <u>:ppm parameter</u> is set which allows imperfect matches). If a value of nil is specified for a slot in a buffer test that indicates a test for the absence of the slot – a slot cannot actually have a value of nil.

In a production which is selected, a buffer test is also referred to as "harvesting" the chunk in the buffer. Here is an example of a buffer-test:

```
=goal>
    slot1 =value
    state    start
- slot2 =value
```

Every buffer test starts with a variable that names the buffer followed by the '>' character. Thus, this is testing the chunk in the model's goal buffer. That variable will be bound to the chunk currently in the buffer and can be used like any other variable in the production. This condition requires that the chunk have slots named slot1 and state. The state slot must have the chunk start as its value and the slot1 slot can hold any value which will be bound to the =value variable. The other constraint here is that if the chunk has a slot named slot2 it must not have the same value as the slot1 slot.

In the trace a buffer test will show up as a buffer-read-action event like this:

```
0.000 PROCEDURAL BUFFER-READ-ACTION GOAL
```

indicating which buffer was tested by the production.

query

A query is one or more tests of a buffer and/or its owning module. There are several default queries which may be made for every buffer and a module may provide many more queries to which it will respond. Each query will produce either a true or false result. The production will only match if the result of each query is true, or if the result is false and the negative test modifier, '-', is used. The queries that can be specified for every buffer are:

buffer empty
buffer full
buffer failure
buffer requested
buffer unrequested
state free
state busy
state error
error t
error nil

The first five are tests of the buffer itself and the module is not contacted to determine the status. The rest, and any others which a module provides, are tests which are relayed to the module to get its response. For the first five, the semantics of the queries are the same for all buffers and are as follows:

- buffer full: is true if there is currently a chunk in the buffer
- buffer failure: is true if the failure flag has been set for the buffer and it does not hold a chunk
- buffer empty: is true if there is not a chunk currently in the buffer and the failure flag is clear
- buffer requested: is true only if there currently is a chunk in the buffer and the module has indicated that it was put there as a result of a request to the module
- buffer unrequested: is true only if there currently is a chunk in the buffer and it has been marked as not having been put there as a result of a request to the module

The other queries are dependent on the how the module responds to them and thus one needs to check the particular module description to determine how they are used. Generally, they have the following semantics, but some modules may not follow this convention:

- state free: is true if the module is ready for new requests
- state busy: is true if the module is currently handling a request
- state error: is true if the last request resulted in some sort of error
- error t: this is the same as a test of state error (which is the query which will actually be sent to the module) and is provided as a shorthand notation for production syntax
- error nil: this is the same as a query for "— state error" thus checking that the module is not currently reporting that "state error" is true and again is a shorthand notation in the production syntax

Here is an example query to the goal buffer:

?goal>
 state free
 buffer full

- state error

A query starts with a symbol composed of a '?', the name of the buffer being queried, and the symbol '>'. This query is testing that the goal module is currently reporting that its state is free, there is currently a chunk in the goal buffer, and that the goal module is not currently reporting an error.

In the trace each buffer queried by the selected production will show up as a query-buffer-action:

0.450 PROCEDURAL

QUERY-BUFFER-ACTION GOAL

eval

The !eval! condition is provided to allow the modeler to add any arbitrary conditions to the LHS of a production or to perform some side effects (like data collection or model tracking information). In the testing of the production's conditions the form provided to evaluate will be called during conflict resolution (if it is a list with the first item being a string then it will call that command through the dispatcher). If the result of the evaluation is **nil**, then the production cannot be selected, but any other return value will allow the production to continue with the pattern matching of the LHS. Using !eval! is something that should be considered carefully when modeling. Generally, they should be used for abstracting away components of the model or task which are unnecessary for the current modeling or for performing non-model related actions.

Here is an example of a call to !eval!:

```
!eval! (special-test =var1 =var2 start)
```

This would pass three parameters to the function called special-test. Those parameters will be the current bindings for the =var1 and =var2 variables in the production and the symbol start. If that function returns a non-**nil** value then this production can continue in conflict resolution, but if it returns **nil** then it will be removed from the current conflict set.

There are actually two forms of the eval condition !eval! and !safe-eval!. Both do the same thing, and the difference is only meaningful for the <u>production compilation mechanism</u>.

One note about using !eval! in conditions is that their evaluation may or may not occur during every conflict-resolution event. They will only be evaluated as needed to determine if a production matches. Thus not every !eval! within a production may be evaluated during a given conflict-

resolution event and possibly none of the !eval! actions in any of the productions may be evaluated during a conflict-resolution event. Of the !eval! actions which are evaluated the only guarantee on the order of their evaluation is that those provided within a production will be evaluated in the order specified, but there is no guarantee on the order in which the !eval! actions from different productions will be evaluated. Because of the uncertainty in when and whether or not !eval! conditions will be evaluated it is recommended that the functions called have no side effects.

binding

The !bind! condition is very similar to the !eval! condition. However, with !bind! the return value of the evaluation is saved in a variable of the production which can then be used like other variables in the production with the exception of not being able to use it in a slot name position. As with !eval! the return value must be non-nil for the production to successfully match. Here is an example of a ! bind!:

```
!bind! =test-value (convert-value =var)
```

This will pass the current binding of the =var variable to the function convert-value and then bind the result to the =test-value variable in the production if it is non-**nil**.

Just like !eval!, there is also a second binding condition !safe-bind! which operates exactly like the ! bind! condition for conflict resolution purposes, but has a difference with respect to how <u>production</u> compilation occurs.

It is also possible to bind multiple return values in a single test with the !mv-bind! condition. This works the same as !bind! except a list of variables is specified and each is bound to the corresponding return value from the evaluation. If there are fewer return values than variables to be bound the production will not match, and if any of the return values which are to be bound to a variable is **nil** then the production will also not match. Here is an example of !mv-bind!:

```
!mv-bind! (=value1 =value2) (split-values =var)
```

The same constraints on ordering and evaluation as described for eval conditions generally apply to binding conditions as well, and again the recommendation is to not have any side effects in the functions used. However, because the variables bound by a binding condition may be used in other eval or binding conditions, the ordering of binding conditions may be performed in an order other

than specified in the production if that is necessary to create the appropriate bindings e.g. these conditions in a production would have to be reordered as indicated to get the bindings necessary but the relative ordering of the !eval! conditions would be maintained:

```
(p bind-ordering
 !eval! (+ =y =x) ; 3rd
 !bind! =x (1+ =y) ; 2nd
 !bind! =y 3 ; 1st
 !eval! (= =x =y) ; 4th
 ==>)
```

Actions

When a production fires it executes all of its actions, which are also referred to as its right hand side (RHS). Those actions are executed in a specific order regardless of how they are specified within the production definition. Except for the eval, output, and bind actions, the actions are processed through individual events scheduled to occur at the same time as the production's firing. The ordering of those events is determined using the priority of the scheduling of the events. Whether those events will be shown in the trace is determined by the :rhst parameter. Those actions may result in other events being scheduled by the modules or otherwise with output not controlled by :rhst.

The ordering of the actions, along with their specific priorities, is as follows:

- 1. All eval, output, and bind calls occur during the production-fired event
- 2. The production-fired event schedules all of the other events
- 3. buffer modification actions [priority 100]
- 4. buffer overwrite actions [priority 90]
- 5. modification requests [priority 60]
- 6. module requests [priority 50]
- 7. buffer clearings [priority 10]
- 8. a !stop! action generates a break event [priority :min]

In general the production actions fall into three categories: cognitive actions performed directly by the production (those which begin with an =, @, or -), actions that are passed off to a module to handle (those that begin with a + or *), and debugging/modeler extension actions (those that begin with an !). The different actions possible are described in the following sections.

buffer modification

A buffer modification action is used to change the slot values of a chunk in a buffer. This is done directly by the production and works the same for every buffer (the buffer's module is not involved in the process). It is essentially the same as using the <u>mod-chunk command</u> on the chunk in the buffer. Here is an example of a buffer modification:

```
=goal>
    state next-step
    slot1 =value
```

The buffer modification must first name the buffer to be modified by using a symbol composed of the '=' character, the name of the buffer and the '>' character. That is followed by pairs of slot names and values. Thus, this example will change the state slot of the chunk in the goal buffer to now contain the chunk next-step and the slot1 slot will now hold whatever the variable =value is bound to in the production.

Alternatively, one can also specify what is referred to as an indirect modification. Instead of specifying the slots and values to modify, a chunk can be specified instead (either as a constant or through a variable). Specifying a chunk is equivalent to specifying all the slots and values of that chunk in the modification. Thus, if one has a chunk defined like this:

```
(define-chunks (test-chunk slot1 10 state finish))
then this modification action:
=goal> test-chunk
will do the same thing as this one:
=goal>
    slot1 10
    state finish
```

It is also possible to specify a modification with no slots and values:

```
=goal>
```

That will not change the chunk in the buffer, but may be useful to prevent the <u>strict harvesting</u> mechanism from automatically clearing the buffer.

In order to perform a buffer modification action that buffer must have also been tested with a buffertest in the conditions of the production to guarantee that it contains a chunk to be modified. The buffer modification actions will show up in the trace as mod-buffer-chunk events indicating the buffer that is modified:

0.050 PROCEDURAL

MOD-BUFFER-CHUNK GOAL

buffer clearing

A buffer clearing action is used to remove a chunk from a buffer. As with buffer modification actions, this is done directly by the production without consulting the buffer's module. However, modules may be monitoring for buffer clearing events and perform some action whenever a buffer is cleared (their own buffer or any other). Once the action completes the buffer will be empty. Here is an example that would clear the goal buffer:

-goal>

The action shows up in the trace as a clear-buffer event indicating which buffer was cleared:

0.150 PROCEDURAL

CLEAR-BUFFER GOAL

A buffer can be cleared regardless of whether or not it was tested on the production's LHS. Note that often one does not need to explicitly clear a buffer because there are two situations which result in buffers being cleared implicitly as described below in Implicit Production Actions.

buffer overwrite

A buffer overwrite action is used to replace the contents of a buffer without clearing it first. As with the buffer modification and buffer clearing actions, this is performed directly by the production without notifying the buffer's module. The chunk which was in the buffer is essentially lost when this action occurs. Here is an example of an indirect buffer overwrite action:

@goal> =value

This will replace the chunk in the goal buffer with the chunk that is bound to the =value variable (a constant chunk name could also be used in place of the variable). It will show up in the trace as an overwrite-buffer-chunk event indicating the buffer and the chunk being copied into it:

0.600 PROCEDURAL

OVERWRITE-BUFFER-CHUNK GOAL CHUNK-10 REQUESTED NIL

Even though the overwrite action was generated by a production, the resulting chunk in the buffer is still marked as being unrequested.

If the item provided is not a valid chunk name then a warning will be printed at run time and no change will be made to the buffer:

```
#|Warning: overwrite-buffer-chunk called with an invalid chunk name BAD-NAME |#
```

If slot and value pairs are provided for an overwrite action like this:

```
@goal>
slot1 10
state finish
```

Then a new chunk is created with only the slots and values specified and that chunk is used to overwrite the buffer in the same way as an indirect action does.

If an overwrite action does not have any components provided:

@goal>

then it performs a slightly different operation. In that case it will erase the buffer instead of overwritting it with a chunk that has no slots (which would be the consistent extension from providing slots and values). The difference is that when the buffer is erased it will be empty. That will show up in the trace like this:

```
0.150 PROCEDURAL ERASE-BUFFER GOAL
```

module request

A module request (usually just referred to as a request) is how the production asks a module to perform some action. It is indicated by specifying a buffer name with a "+" on the front and a ">" on the end. Syntactically, a request can be specified using any slots and values for any buffer. Semantically, what a request actually does is specific to the module. Some modules may not even accept requests through their buffers, or may have a more restrictive syntax than the general syntax available in the production (for example only allowing a slot to be specified once in the request). Thus, to know what can be requested, how it needs to be specified, and how that will then be processed one needs to know the details of the modules. A syntactically correct production may

make semantically invalid requests which would typically generate warnings at run time from the module receiving the request.

In the production, a module request can be specified in the same ways as a modification action. It may directly include all of the details of the request (which may include modifiers unlike the modification actions) or create the request indirectly by specifying a chunk. As far as the module which receives the request is concerned, there is no difference between the different specifications in the production i.e. the module does not know whether explicit slot and value specifications were provided or if the production specified a single chunk which resulted in the slot value pairs of the request.

In addition to specifying slots in the request one may also include additional labels called request parameters. A request parameter is used like a slot in the request, but it is not actually the name of a slot. It is a Lisp keyword which has been created by a particular module to allow additional information to be provided in a request without having to use slots in chunks.

Here is an example of specifying the details of a request:

```
+retrieval>
    slot1 =value
    - slot1 10
    slot2    start
    <= count =count
    :recently-retrieved nil</pre>
```

That request would be sent off to the retrieval buffer's module for handling, and what happens based on that request depends on the module which gets the request.

Here is an example of an indirect request:

```
+retrieval> =value
```

If =value is bound to a chunk name in the instantiation of the production being fired, then that chunk is essentially expanded to its slot value pairs to make the request. Thus, if =value were bound to the chunk A and the chunk A were defined like this:

```
(define-chunks (a state start slot2 10))
```

Then that would be equivalent to specifying this in the production:

```
+retrieval>
state start
slot2 10
```

It is also possible to include request parameters in an indirect request by specifying a list which has the chunk as the first element and the request parameters and values as the remaining items:

```
+retrieval> (=value :recently-retrieved t)
```

If a variable used in an indirect request is not bound to the name of a chunk in the production's instantiation, then warnings are printed and no request is made (note that the <u>implicit clearing</u> described below is still performed even if such a warning is encountered). The warnings will look like this in the trace:

```
\#|\mbox{Warning: define-chunk-spec's 1 parameter doesn't name a chunk: } (not-a-chunk) | \#|\mbox{Warning: schedule-module-request called with an invalid chunk-spec NIL } | \#|\mbox{Warning: schedule-module-request called with an invalid chunk-spec NIL } | \#|\mbox{Warning: schedule-module-request called with an invalid chunk-spec NIL } | \#|\mbox{Warning: schedule-module-request called with an invalid chunk-spec NIL } | \#|\mbox{Warning: schedule-module-request called with an invalid chunk-spec NIL } | \#|\mbox{Warning: schedule-module-request called with an invalid chunk-spec NIL } | \#|\mbox{Warning: schedule-module-request called with an invalid chunk-spec NIL } | \#|\mbox{Warning: schedule-module-request called with an invalid chunk-spec NIL } | \#|\mbox{Warning: schedule-module-request called with an invalid chunk-spec NIL } | \#|\mbox{Warning: schedule-module-request called with an invalid chunk-spec NIL } | \#|\mbox{Warning: schedule-module-request called with an invalid chunk-spec NIL } | \#|\mbox{Warning: schedule-module-request called with an invalid chunk-spec NIL } | \#|\mbox{Warning: schedule-module-request called with an invalid chunk-spec NIL } | \#|\mbox{Warning: schedule-module-request called with an invalid chunk-spec NIL } | \#|\mbox{Warning: schedule-module-request called with an invalid chunk-spec NIL } | \#|\mbox{Warning: schedule-module-request called with an invalid chunk-spec NIL } | \#|\mbox{Warning: schedule-module-request called with an invalid chunk-spec NIL } | \#|\mbox{Warning: schedule-module-request called with an invalid chunk-spec NIL } | \#|\mbox{Warning: schedule-module-request called with an invalid chunk-spec NIL } | \#|\mbox{Warning: schedule-module-request called with an invalid chunk-spec NIL } | \#|\mbox{Warning: schedule-module-request called with an invalid chunk-spec NIL } | \#|\mbox{Warning: schedule-module-request called with an invalid chunk-spec NIL } | \#|\mbox{Warning: schedule-module-request called with an invalid chunk-spec NIL } | \#|\mbox{Warning: schedule-module-module-module
```

A valid request action will show up in the trace as a module-request event specifying the buffer to which the request was sent:

```
0.800 PROCEDURAL MODULE-REQUEST GOAL
```

Typically, that will be followed by events from the module to which the request was made performing the requested action.

modification request

A modification request is similar to both the module request and buffer modification actions, and it is another way for a production to ask a module to perform some action. The differences between a modification request and a module request are that a modification request does not include an implicit clearing of the buffer and it is restricted to the same specification style as a buffer modification (no slot modifiers are allowed, no request parameters are accepted, and the buffer to which this request is made must have been used in a buffer test on the production's LHS). As with a request, what the module does in response to a modification request is entirely up to the module.

To create a modification request the buffer name is preceded by the "*" character. Here is an example of a modification request:

```
*imaginal>
slot1 =value
slot2 start
```

This would send those slot and value pairs off to the imaginal buffer's module to process. It is also possible to make an indirect modification request just like an indirect buffer modification:

```
*imaginal> =chunk
```

A modification request will show up in the trace as a module-mod-request event specifying the buffer to which the request is made:

```
1.000 PROCEDURAL MODULE-MOD-REQUEST IMAGINAL
```

An empty modification request is also allowed syntactically, but may not be meaningful to the module which receives it.

If a module does not accept modification requests then a warning like this will be displayed when the production is fired:

```
#|Warning: Module XXXXX does not support buffer modification requests. |#
```

eval

The eval action works just like the eval condition except that the return value does not matter.

binding

The binding action works just like the binding condition except that a returned value of **nil** is allowed, but it will not be used as the binding for a variable. If a binding to **nil** is attempted then a warning will be printed and the variable will be bound to **t** instead. Additionally, if the binding actions must be reordered for proper evaluation a warning will be output when the production is defined.

output

The !output! action allows one to embed additional text in the model's trace. The output will be shown when the <u>:v parameter</u> is non-nil under any of the <u>:trace-detail</u> setting.

There are three ways to use the output action. It can be used to print a single value like this:

```
!output! =value
!output! started
```

In that case the item specified will be output followed by a newline in the trace. If the item is a variable then it is the binding of the variable which is output.

It can also output several items if they are placed into a list:

```
!output! (the value is =value)
```

In that case all of the items will be printed on one line followed by a newline. Again, variables will be replaced with their current bindings before outputting.

Finally, it can use the Lisp format control mechanisms to output the text. If the first item given in a list to an !output! action is a string then that string is assumed to be a format specification. It is used to generate the output text using the remaining arguments in the same way that the Lisp format command would:

```
!output! ("The count is \sim6,3f.\sim%The value is \sima\sim%" =count =value)
```

stop

The stop action is used to force the model to stop after firing that production. A stop action is created with this:

!stop!

A break event will be generated by the stop action that will cause the current run to terminate.

Implicit production clearing actions

In addition to the events specified in the production there are two situations where a buffer clearing action will be implicitly executed when the production fires. They are referred to as strict harvesting and implicit clearing.

strict harvesting

Strict harvesting means that when a production tests a buffer on its LHS (harvests the chunk) it will automatically clear that buffer in the actions of the production. That will occur unless either: a modification is performed on that buffer (either a buffer modification with an = or a modification request with a *) or the buffer has been specified as one which should not be strict harvested using the :do-not-harvest parameter.

request clearing

For each buffer which has a module request on the RHS of a production there is an implicit buffer clearing action performed on that buffer. There is no mechanism provided for suppressing this clearing action.

Examples:

For examples of productions in actual models see the example models in the ACT-R tutorial.

Here is an example production that assumes there are buffers named goal, retrieval, imaginal, visual, and visual-location, that the retrieval buffer has a request parameter called :recently-retrieved, that these chunk-types have been defined:

```
(chunk-type goal-type slot1 value test buffer state step)
(chunk-type visual-location screen-x screen-y color)
```

and that there are functions defined called check-value, get-a-state, and a dispatched command named record-results.

This production uses most of the available syntax and is purely for demonstration — it does not represent any particular usage from a real model.

```
(p example-production "a production showing most syntactic elements"
 =goal>
   isa goal-type
     state start
     test =test
      < value 4
     value =value
      - slot1 =test
      slot1 =last-loc
      buffer =check
 ?visual>
      state =check
      buffer empty
 =visual-location>
   isa visual-location
     >= screen-x =value
     <= screen-x 100
     > screen-y =value
      < screen-v =max-value
      =value =current-value
 =imaginal>
  !eval! (check-value =value)
  !bind! =max-value (+ =value 100)
  !mv-bind! (=quotient =remainder) (floor =max-value)
 !safe-bind! =new-state (get-a-state)
 =goal>
     =check =new-state
```

```
value =quotient
      step continue
  *visual-location>
    isa visual-location
    screen-x =max-value
 +retrieval>
      :recently-retrieved nil
     < screen-x =max-value
      - value =current-value
     color blue
 +visual-location> =last-loc
 +imaginal>
    isa goal-type
     state done
 @visual> =imaginal
  !output! (Moving to state =new-state with max-value of =max-value)
  !safe-eval! ("record-results" =check 75 =quotient =remainder)
  !stop!
)
```

The examples below will show some of the warnings which may result when trying to define productions. Only those examples which result in no production being defined are indicated as errors.

For these examples the following chunk-type is assumed to have been defined:

```
(chunk-type goal-type slot slot2 state)
```

and the <u>:style-warnings parameter</u> has been turned off to avoid the warnings which may result because of the productions being defined individually.

```
1> (p test
    "Automatically creating a chunk which is referenced"
    =goal>
        isa goal-type
        state start
    ==>
    )
#|Warning: Creating chunk START with no slots |#
TEST

2> (p test
    "Redefining the production test"
    =goal>
        isa goal-type
        state start
    ==>
    )
#|Warning: Production TEST already exists and it is being redefined. |#
TEST
```

```
E> (p test
    "No current model"
    =qoal>
     isa qoal-type
      state start
#|Warning: get-module called with no current model. |#
#|Warning: No procedural modulue found cannot create production. |#
> (p test2
    "Slot name doesn't match chunk-type specified"
     isa goal-type
     bad-slot t
  ==>
  )
#|Warning: Production TEST2 uses previously undefined slots (BAD-SLOT). |#
E> (p test2
    "Invalid buffer name in condition"
    =buffer>
     isa goal-type
      state start
    ==>
   )
#|Warning: No production defined for (TEST2 "Invalid buffer name in condition" =BUFFER>
ISA GOAL-TYPE STATE START ==>). |#
#|Warning: First item on LHS is not a valid command |#
#|Warning: --- end of warnings for undefined production TEST2 --- |#
NIL
E> (p test2
    .
"Invalid buffer in query after a valid buffer test"
     =goal>
       isa goal-type
     ?buffer>
       buffer empty
     ==>
   )
#|Warning: No production defined for (TEST2 "Invalid buffer in query after a valid buffer
test" =GOAL> ISA GOAL-TYPE ?BUFFER> BUFFER EMPTY ==>). |#
#|Warning: Invalid syntax in (=GOAL> ISA GOAL-TYPE ?BUFFER> BUFFER EMPTY) condition. |#
#|Warning: Invalid slot-name ?BUFFER> in call to define-chunk-spec. |#
#|Warning: --- end of warnings for undefined production TEST2 --- |#
NIL
E> (p test2
    "Buffer not tested on LHS for modification action"
     =goal>
       state start
    )
#|Warning: No production defined for (TEST2 "Buffer not tested on LHS for modification
action" ==> =GOAL> STATE START). |#
#|Warning: Buffer modification action for untested buffer (=GOAL> STATE START). |#
#|Warning: --- end of warnings for undefined production TEST2 --- |#
NIL
```

all-productions

Syntax:

all-productions -> (production-name*)

Remote command name:

all-productions

Arguments and Values:

production-name ::= a name of a production

Description:

The all-productions command takes no parameters. It returns a list of the names of all the productions defined in the current model. If there is no current model it prints a warning and returns **nil**.

Examples:

This example assumes the count model from unit 1 of the tutorial has been loaded.

```
> (all-productions)
(START INCREMENT STOP)

E> (all-productions)
#|Warning: get-module called with no current model. |#
NIL
```

pp

Syntax:

```
pp production-name* -> (production-name*)
pp-fct (production-name*) -> (production-name*)
```

Remote command name:

pp

Arguments and Values:

production-name ::= a name of a production

Description:

The pp command is used to print the procedural module's representation of a production. It takes any number of production names and for each one prints out the representation of the named production in the current model to the command trace. If no names are provided it prints out all of the productions in the current model (which can be useful when production compilation is enabled to see what productions the model has learned). It returns a list of the names of the productions that were printed.

Note that the representation printed for a production may not exactly match the text which was used to define the production. In particular, any chunk-types specified in the original definition will not be shown in the printed representation since the chunk-type information is only used for the definition and does not represent an actual component of the production.

If there is no current model a warning is printed and **nil** is returned. If an invalid production name is given a warning is printed.

Examples:

This example assumes the count model from unit 1 of the tutorial has been loaded.

```
> (pp)
(P START
   =GOAL>
       START = NUM1
       COUNT NIL
   =GOAL>
       COUNT = NUM1
   +RETRIEVAL>
       FIRST =NUM1
(P INCREMENT
   =GOAL>
       COUNT =NUM1
       END =NUM1
   =RETRIEVAL>
       FIRST =NUM1
       SECOND = NUM2
 ==>
   =GOAL>
       COUNT =NUM2
   +RETRIEVAL>
       FIRST =NUM2
   !OUTPUT! (=NUM1)
P STOP
   =GOAL>
       COUNT = NUM
       END =NUM
 ==>
   -GOAL>
   !OUTPUT! (=NUM)
(START INCREMENT STOP)
```

pbreak/punbreak

Syntax:

```
pbreak production-name* -> (break-production*)
pbreak-fct (production-name*) -> (break-production*)
punbreak production-name* -> (break-production*)
punbreak-fct (production-name*) -> (break-production*)
```

Remote command name:

pbreak punbreak

Arguments and Values:

```
production-name ::= a name of a production break-production ::= a name of a production which is currently set to generate a break event
```

Description:

The pbreak command can be used to force a <u>break event</u> to occur when particular productions are selected during conflict resolution. Each production which is specified in a call to pbreak will force a break event if it is selected. Before the break, the current instantiation of the production will be output to the model trace.

The punbreak command is used to remove the break status of productions. Each production passed to punbreak will no longer force a break event upon its selection. If no productions are specified for punbreak then all productions have their break status cleared.

Both commands return a list of all productions which currently have a break status set in the current model.

If there is no current model or a production name provided is invalid a warning is printed.

Examples:

This example assumes the count model from unit 1 of the tutorial has been loaded.

```
1> (pbreak)
NIL
2> (pbreak start)
(START)
3> (run 10)
    0.000
                                    SET-BUFFER-CHUNK GOAL FIRST-GOAL NIL
             GOAL
            PROCEDURAL
    0.000
                                    CONFLICT-RESOLUTION
    0.000
            PROCEDURAL
                                    PRODUCTION-SELECTED START
(P START
   =GOAL>
       START 2
       COUNT NIL
==>
  =GOAL>
      COUNT 2
  +RETRIEVAL>
      FIRST 2
0.000
      -----
                               BREAK-EVENT PRODUCTION START
4> (pbreak-fct '(start increment))
(INCREMENT START)
5> (punbreak start)
(INCREMENT)
6> (pbreak start stop)
(STOP INCREMENT START)
7> (punbreak-fct '(increment stop))
(START)
8E> (pbreak bad-name)
#|Warning: BAD-NAME is not the name of a production |#
(START)
9E> (punbreak-fct '(not-a-production))
#|Warning: NOT-A-PRODUCTION is not the name of a production |#
(START)
10> (punbreak)
NIL
11> (pbreak)
NIL
E> (pbreak)
#|Warning: There is no current model - pbreak cannot be used. |#
E> (punbreak start)
```

```
\#|\mbox{Warning: There is no current model} - punbreak cannot be used. |\#|\mbox{NIL}
```

pdisable/penable

Syntax:

```
pdisable production-name* -> (disabled-production*)
pdisable-fct (production-name*) -> (disabled-production*)
penable production-name* -> (disabled-production*)
penable-fct (production-name*) -> (disabled-production*)
```

Remote command name:

pdisable penable

Arguments and Values:

```
production-name ::= a name of a production disabled-production ::= a name of a production which is currently disabled
```

Description:

The pdisable command can be used to disable productions in the current model. A production which is disabled will not participate in conflict resolution. Each production which is specified in a call to pdisable will be disabled.

The penable command is used to enable productions which have been disabled in the current model. Each production passed to penable will no longer be disabled. If no productions are specified for penable then all productions will be enabled.

Both commands return a list of all productions which currently have been disabled in the current model.

If there is no current model or a production name is invalid a warning is printed.

Examples:

This example assumes the count model from unit 1 of the tutorial has been loaded.

```
1> (pdisable)
NIL
2> (pdisable start stop)
(STOP START)
3> (penable-fct '(start))
(STOP)
```

```
4> (pdisable-fct '(start increment))
(STOP INCREMENT START)

5> (penable)
NIL

E> (penable)
#|Warning: There is no current model - penable cannot be used. |#
NIL

E> (pdisable bad-name)
#|Warning: BAD-NAME is not the name of a production |#
NIL

E> (penable-fct '(not-a-production))
#|Warning: NOT-A-PRODUCTION is not the name of a production |#
NIL
```

whynot

Syntax:

```
whynot production-name* -> (matching-production*)
whynot-fct (production-name*) -> (matching-production*)
```

Remote command name:

whynot

Arguments and Values:

```
production-name ::= a name of a production matching-production ::= a name of a production which matches at the current time
```

Description:

The whynot command is a useful model debugging tool. For each of the named productions passed to it (or all productions if no names are provided) it will print out whether that production in the current model matches the current state or not. If it does match, then the instantiation of the production is printed to the command trace and if it does not match then the production is printed to the command trace and the first condition that is unsatisfied at the current time is also printed.

If the <u>:ppm parameter</u> is enabled to allow for imperfect matching then the instantiation of a production which is a partial match will indicate the current slot value, the imperfectly matching buffer slot value and the similarity between those values.

It returns a list of all the productions which do match the current state in the current regardless of whether they were passed into whynot for display.

If there is no current model then a warning is printed and **nil** is returned. If an invalid production-name is provided a warning will be displayed.

Examples:

This example assumes the count model from unit 1 of the tutorial has been loaded.

```
1> (reset)
DEFAULT
2> (whynot)
Production START does NOT match.
(P START
   =GOAL>
       START = NUM1
       COUNT NIL
 ==>
   =GOAL>
       COUNT =NUM1
   +RETRIEVAL>
       FIRST =NUM1
It fails because:
The GOAL buffer is empty.
Production INCREMENT does NOT match.
(P INCREMENT
   =GOAL>
       COUNT = NUM1
      END =NUM1
   =RETRIEVAL>
       FIRST =NUM1
       SECOND =NUM2
   =GOAL>
       COUNT =NUM2
   +RETRIEVAL>
       FIRST =NUM2
   !OUTPUT! (=NUM1)
It fails because:
The GOAL buffer is empty.
Production STOP does NOT match.
(P STOP
   =GOAL>
       COUNT = NUM
       END =NUM
   -GOAL>
   !OUTPUT! (=NUM)
It fails because:
The GOAL buffer is empty.
NIL
3> (run-n-events 2)
     0.000
                                     SET-BUFFER-CHUNK GOAL FIRST-GOAL NIL
             GOAL
     0.000
                                     Stopped because event limit reached
            -----
0.0
2
NIL
```

```
4> (whynot-fct '(increment))
(P INCREMENT
   =GOAL>
       COUNT =NUM1
       END =NUM1
   =RETRIEVAL>
       FIRST =NUM1
       SECOND = NUM2
 ==>
   =GOAL>
       COUNT =NUM2
   +RETRIEVAL>
       FIRST =NUM2
   !OUTPUT! (=NUM1)
It fails because:
The chunk in the GOAL buffer does not have slot COUNT.
(START)
5> (whynot start)
Production START matches:
(P START
   =GOAL>
       START 2
       COUNT NIL
   =GOAL>
       COUNT 2
   +RETRIEVAL>
       FIRST 2
(START)
```

This example uses a simple model definition to show a production which is a partial match with :ppm enabled:

```
1> (define-model test
     (sgp :esc t :ppm 1)
     (chunk-type test slot)
     (define-chunks (buffer-value) (production-test))
     (set-similarities (buffer-value production-test -.5))
     (set-buffer-chunk 'goal (car (define-chunks (slot buffer-value))))
     (p test
        =qoal>
           isa test
           slot production-test
      ==>))
TEST
2> (whynot)
Production TEST partially matches the current state:
Production TEST partially matches the current state:
(P TEST
   =GOAL>
       SLOT [PRODUCTION-TEST, BUFFER-VALUE, -0.5]
(TEST)
E> (whynot)
```

```
#|Warning: Whynot called with no current model. |#
NIL
E> (whynot bad-name)
BAD-NAME does not name a production.
(START)
```

production-firing-only

Syntax:

production-firing-only event -> production-firing-event?

Arguments and Values:

```
event ::= an ACT-R event
```

production-firing-event? ::= a generalized boolean that is true if event has an action of production-fired and is false otherwise

Description:

This is not a command which should be called by the modeler directly. It is provided as a possible value for the <u>:trace-filter parameter</u> to restrict the trace to only the production-fired events.

Examples:

This example assumes the count model from unit 1 of the tutorial has been loaded.

```
> (with-parameters (:trace-filter production-firing-only)
   (run 10))
     0.050
             PROCEDURAL
                                     PRODUCTION-FIRED START
             PROCEDURAL
     0.150
                                     PRODUCTION-FIRED INCREMENT
2
     0.250
             PROCEDURAL
                                     PRODUCTION-FIRED INCREMENT
3
     0.300
             PROCEDURAL
                                     PRODUCTION-FIRED STOP
4
     0.300
             _ _ _ _ _
                                     Stopped because no events left to process
0.3
50
NIL
```

un-delay-conflict-resolution

Syntax:

un-delay-conflict-resolution -> nil

Remote command name:

un-delay-conflict-resolution

Arguments and Values:

Description:

The un-delay-conflict-resolution command takes no parameters and will cause a new conflict-resolution event to be scheduled in the current model if the procedural module is currently waiting for some change in the system to schedule the next conflict-resolution event. If there is no current model then this command has no effect and a warning is output.

This is not a command which one will typically need to use. Right now, it is only used by the procedural system modules (procedural, utility, and production-compilation) to ensure that conflict resolution gets rescheduled if necessary when parameters are changed or new productions are created. However, in rare circumstances other modules could put the system in such situations and thus may need to use this command (though typically the other module should just be able to schedule an event which would allow conflict resolution to occur normally).

Examples:

```
> (un-delay-conflict-resolution)
NIL
E> (un-delay-conflict-resolution)
#|Warning: get-module called with no current model. |#
NIL
```

clear-productions

Syntax:

clear-productions -> nil

Remote command name:

clear-productions

Arguments and Values:

Description:

The clear-productions command will delete all of the productions from the current model. It is not recommended, but there may be times where one finds doing so necessary. It will also print out a warning indicating that it is not recommended. If there is no current model then a warning is printed.

It always returns nil.

Examples:

```
> (clear-productions)
#|Warning: Clearing the productions is not recommended |#
NIL

E> (clear-productions)
#|Warning: get-module called with no current model. |#
#|Warning: No procedural module was found. |#
NIL
```

declare-buffer-usage

Syntax:

```
declare-buffer-usage buffer type-name \{ [:all \mid slot^*] \} \rightarrow [t \mid nil] 
declare-buffer-usage-fct buffer type-name \{ [:all \mid (slot^*)] \} \rightarrow [t \mid nil]
```

Arguments and Values:

```
buffer ::= the name of a buffer
type-name ::= the name of a chunk-type
slot ::= a name of a slot of the chunk-type type-name
```

Description:

The declare-buffer-usage command is used to indicate a chunk-type and any slots from that chunk-type that are going to be used with a particular buffer but which are not created by the productions nor set initially in the model definition. By declaring those slots as used it will prevent style warnings from the production definitions for those slots. This will typically be needed when chunks are being placed into buffers from code. In that situation using this command in the model definition to indicate the items which are being set from outside of the model definition will avoid possible style warnings.

If buffer names a valid buffer, type-name names a valid chunk-type, and all slots specified are valid for the chunk-type given then style warnings related to those items will be avoided and a value of **t** will be returned. If the keyword **:all** is provided instead of slot names then that will be equivalent to specifying all the slots of the chunk-type given.

If any of the parameters are invalid or there is no current model then a warning will be printed and **nil** will be returned.

Examples:

```
> (declare-buffer-usage goal chunk)
```

```
> (declare-buffer-usage imaginal text screen-pos value)
> (declare-buffer-usage-fct 'imaginal 'visual-object '(value color))
> (declare-buffer-usage retrieval text :all)
> (declare-buffer-usage-fct 'imaginal 'visual-object :all)
E> (declare-buffer-usage not-a-buffer visual-location)
#|Warning: Cannot declare usage for NOT-A-BUFFER because it does not name a buffer in the
model. |#
NIL
E> (declare-buffer-usage-fct 'goal 'not-a-chunk-type)
#|Warning: Cannot declare usage for buffer GOAL because NOT-A-CHUNK-TYPE does not name a
chunk-type in the model. |#
NIL
E> (declare-buffer-usage goal chunk not-a-slot)
#|Warning: Cannot declare usage for buffer GOAL because the slots (NOT-A-SLOT) are not
valid for chunk-type CHUNK. |#
NIL
E> (declare-buffer-usage goal type)
#|Warning: get-module called with no current model. |#
#|Warning: No procedural module found. Cannot declare buffer usage. |#
NIL
```

Utility module

The utility module provides the support for the productions' subsymbolic utility value which is used in conflict resolution. Utility is a numeric quantity associated with each production that can be specified in advance for each production and/or learned while the model runs.

Each production has a utility value associated with it, which we will call U. Of the productions in the conflict set (those which match the current state) the one with the highest current U will be the one selected. When <u>utility learning is enabled</u>, the U value is based on the rewards that a production receives and will change as the model runs. The learning of utilities is controlled by the following equation for a production i after its nth usage:

$$U_i(n) = U_i(n-1) + \alpha [R_i(n) - U_i(n-1)]$$

 α is the learning rate set by the <u>:alpha parameter</u>

Ri(n) is the effective reward value given to production i for its nth usage

Ui(0) is either set by the modeler with the <u>spp</u> command or is the value of the <u>:iu</u> or <u>:nu</u> parameter

The learning occurs when a reward is triggered, at which time productions which have been used since the last reward may have their utility values updated (see the <u>trigger-reward</u> command for details on how the used productions are determined). The effective reward for a production i is the reward value received after its nth usage minus the time since that nth selection of production i.

When the <u>:esc parameter</u> is enabled the utility values may also have a noise component added to them (regardless of whether the learning mechanism is enabled). If :esc is enabled and the <u>:egs parameter</u> is set then each time a production's utility is calculated it will also have a noise component added to it. That noise is generated using the <u>act-r-noise command</u> with the s value being the current setting of the :egs parameter.

Parameters

:alpha

The α parameter in the utility learning equation. The default value is .2.

:egs

The expected gain s parameter. It specifies the s parameter for the noise added to the utility values. It defaults to 0 which means there is no noise in utilities.

:iu

The initial utility value for a user defined production. This is the U(0) value for a production if utility learning is enabled and the default utility if learning is not enabled. The default value is 0.

:nu

This is the starting utility for a newly learned production (those created by the <u>production compilation</u> mechanism). This is the U(0) value for such a production if utility learning is enabled and the default utility if learning is not enabled. The default value is 0.

:reward-hook

The reward-hook parameter allows the modeler to override the default calculation for effective reward, $R_i(n)$. It can be set to a function or command name string which must take three parameters. If the :reward-hook parameter is not **nil** (which is the default value) then each time a reward is propagated back to a production the reward-hook function will be called. It will be passed the name of the production as the first parameter, the reward value being propagated as the second, and the time since the production was selected (in seconds) as the third. If that function returns a number then that number is used as the $R_i(n)$ value in updating the production's utility instead of the normal calculation (which is the reward minus the time since the production's selection). If any other value is returned, then the standard calculation for $R_i(n)$ is used. Only one reward-hook function may be specified at a time and if the parameter is changed from one function to another a warning will be output.

:reward-notify-hook

This parameter is now depricated because the trigger-reward command can be monitored through the dispatcher, which is the recommended way to detect a reward. This parameter allows one to specify functions which will be called whenever there is a reward provided to the model. This parameter can be set to a function or command name string which takes one parameter and any number of such functions may be set (the reported value of this parameter is a list of all items which have been set). Whenever trigger-reward is called the items set with this parameter will be called during the propagate-reward event that gets generated as a result of that trigger-reward. Each of the items that

has been set for this parameter will be called with one parameter which is the reward value passed to trigger-reward. The return values from items called through this hook are ignored. If the parameter is set to **nil** then all items are removed from the reward-notify-hook list. A function should only be set once. If an item is specified more than once as a value for the reward-notify-hook a warning will be displayed and a value of **nil** will be returned as the current value.

:ul

This is the utility learning flag. If it is set to **t** then the utility learning equation shown above will be used to learn the utilities as the model runs. If it is set to **nil** then the explicitly set utility values for the productions are used (though the noise will still be added if :egs is non-zero). The default value is **nil**.

:ult

This is the utility learning trace flag. If it is set to **t** then when a reward is received and utilities are updated the corresponding changes will be output in the model trace. If it is set to **nil** then there will be no additional trace output from utility updating. The default value is **nil**.

:ut

This is the utility threshold. If it is set to a number then that is the minimum utility value that a production must have to compete in conflict resolution. Productions with a lower utility value than that will not be selected. The default value is **nil** which means that there is no threshold value and all productions will be considered.

:utility-hook

The utility-hook parameter allows the modeler to override or bypass the default utility calculation. It can be set to a function or command name string which must take one parameter. If the :utility-hook parameter is not **nil** (which is the default value) then each time a production's utility is to be calculated, first this hook function is called with the name of the production as the parameter. If that function returns a number then that number is used as the production's utility instead of using the normal mechanisms. Only one utility-hook function may be specified at a time and if the parameter is changed from one function to another a warning will be output.

:utility-offsets

This parameter allows one to specify functions which can extend the utility equation with new terms. This parameter can be set to a function or command name string which takes one parameter and any number of such functions may be set (the reported value of this parameter is a list of all values which have been set). Whenever a production's utility is computed each of the items that has been set for this parameter will be called with one parameter which is the name of the production. If an item called returns a number then that value will be added to the utility of the production. If an item returns any other value then no change is made to the utility of the production. If the parameter is set to **nil** then all items are removed from the utility-offsets list. An item should only be set once. If an item is specified more than once as a value for the utility-offsets a warning will be displayed and a value of **nil** will be returned as the current value.

Commands

trigger-reward

Syntax:

trigger-reward reward {maintenance} -> [t | nil]

Remote command name:

trigger-reward

Arguments and Values:

reward ::= [a number which indicates the amount of reward to apply | any non-nil value]
maintenance ::= a generalized boolean which indicates whether the propagate-reward event should be
marked as a maintenance event or not

Description:

The trigger-reward command allows the modeler to present rewards to the current model for the purposes of utility learning. If the reward specified is a number then that value is used in computing the updated utility for the productions which need to be updated. If the reward is any other non-nil value then no utilities are updated but this still indicates when the last reward was given – effectively an indication of an empty reward. This command can be called at any time to introduce a reward to the model – it does not need to be called synchronously with a production's firing. If there is a current model and the reward value is valid, then a propagate-reward event will be scheduled at the current time to perform the computations to update production utilities and t will be returned. The event will show the value of the reward being used like this:

If utility learning is not enabled, then that will be followed by a warning indicating that no change has occurred:

```
#|Warning: Trigger-reward can only be used if utility learning is enabled. |#
```

That event will be marked as a maintenance event if a non-**nil** maintenance value is provided otherwise it will be a model event. One may want to have the reward be a maintenance event if a single model is being used both with and withoug learning enabled to avoid the introduction of the rewards for the learning case adding additional changes relative to the non-learning situation.

If the <u>:ul parameter</u> is set to **t** then all productions which have been selected since the last reward was provided will receive an update. If there is no current model or the parameter provided is invalid then a warning is printed, no utilities are changed, and **nil** is returned.

Examples:

```
> (trigger-reward 10)
T
> (trigger-reward "No updates now.")
T
> (trigger-reward -1 t)
T

E> (trigger-reward nil)
#|Warning: Trigger-reward must be called with a non-null value -- nil does not indicate a null reward anymore. |#
T

E> (trigger-reward 10)
#|Warning: No current model. Trigger-reward has no effect. |#
NIL
```

spp

Syntax:

Remote command name:

Arguments and Values:

production-name ::= the name of a production in the current model

param-name ::= the name of a production parameter

param-value-pair ::= param-name new-param-value

new-param-value ::= a value to which the preceding param-name is to be set

param-values ::= [(param-value*) | (production-name*) | :error]

param-value ::= the current value of a requested production parameter or :error

Description:

Spp is used to set or get the value of the parameters of the productions in the current model. It is similar to the <u>spp command</u> which is used to set and get the module parameter.

Each production has six parameters associated with it. Two of them are read only, but the others can be adjusted by the modeler. Those parameters are:

:at

The action time of the production. This is how much time passes (in seconds) between the production's selection and when it fires. This can be set explicitly for each production and defaults to the value of the :dat parameter at the time the production was created.

:name

The name parameter returns the name of the production. This cannot be changed. Requesting this parameter is useful for annotating the results that are returned as shown in the examples.

:u

The u parameter returns the current U(n) value for the production. This may be set directly only when the <u>utility learning mechanism is not enabled</u>. It defaults to the value of the <u>:iu parameter</u> at the time the production is created unless it is created through <u>production compilation</u> in which case it defaults to the value of the <u>:nu parameter</u>.

:utility

The last computed utility value of the production during conflict resolution (including any noise which was added). This cannot be changed by the modeler. If the production has not yet been a member of the conflict set, then the value will be **nil**.

:reward

This is a reward value to apply when this production fires. The default is **nil** which means the production does not provide a reward. If it is set to a number or **t** then after this production fires a <u>trigger-reward</u> call will be made using that reward value.

:fixed-utility

This parameter can be set to exclude a production from having its utility updated by the utility learning mechanism. The default value is **nil** which means that the production's :u parameter will be adjusted when rewards are received. If it is set to **t** then this production's utility will not change and will remain fixed at the current :u parameter value.

If no parameters are provided to spp, then all of the current model's productions' parameters are output to the command trace and a list of all the production names is returned. For each production it prints the production's name followed by the parameters which are currently appropriate based on the settings of sesc and sul. If sesc is t, and sesc is t, and sesc is t, and sesc is t, and sesc is t, and sesc is t, and sul is t, then sul is t, and sesc is t and sesc is t and sesc is t and sesc is sesc is t is sesc is sesc is sesc is sesc is sesc</

If a production or list of productions is specified as the first parameter to spp then the parameters which follow that are set or retrieved from only those productions. If no production names are provided then the settings are applied to or retrieved from all productions that exist at the time of the call to spp.

If production names are specified but no specific parameters are specified then the parameters for those productions are printed and the list of those production names is returned. If any of the production names provided are invalid a warning will be printed and the corresponding element of the return list will be **:error**.

If all of the parameters passed to spp (after any production names) are keywords, then it is a request for the current values of the parameters named. Those parameters are printed for the productions specified and a list containing a list for each production specified is returned. Each sub-list contains the values of the parameters requested in the order requested and the sub-lists are in the order of the

productions which were requested. If an invalid parameter is requested, then a warning is printed and the value returned in that position will be the keyword **:error**.

If there are any non-keyword parameters in the call to spp and the number of parameters (not counting the production names) is even, then they are assumed to be pairs of a parameter name and a parameter value. For all of the specified productions (or all productions if none are specified) those parameters will be set to the provided values. The return value will be a list containing a list for each production specified. Each sub-list contains the values of the parameters set in the order they were set and the sub-lists are in the order of the productions which were specified. If a particular parameter value was not of the appropriate type, then a warning is printed and the value returned in that position will be the keyword **:error**.

It is also possible to pass lists of production-name and parameter settings to spp. Essentially, each list provided must be formatted as something that could be passed to spp on its own and they will each be processed as appropriate.

If there is no current model at the time of the call then a warning is displayed and **nil** is returned.

Examples:

This example assumes the count model from unit 1 of the tutorial has been loaded.

```
1> (sgp :esc nil :ul nil)
 (NIL NIL)
2> (spp)
Parameters for production START:
     0.000
 : u
 :at 0.050
Parameters for production INCREMENT:
      0.000
 :at 0.050
Parameters for production STOP:
 :u
     0.000
:at 0.050
(START INCREMENT STOP)
3> (sgp :esc t)
 (T)
4> (spp)
Parameters for production START:
 :utility
             NIL
     0.000
:at 0.050
Parameters for production INCREMENT:
 :utility
             NIL
     0.000
 :at 0.050
Parameters for production STOP:
 :utility
```

```
:u 0.000
:at 0.050
(START INCREMENT STOP)
5> (sgp :ul t)
(T)
6> (spp)
Parameters for production START:
 :utility
            NIL
 :u 0.000
:at 0.050
            NIL
 :reward
 :fixed-utility
                  NIL
Parameters for production INCREMENT:
:utility
            NIL
 :u 0.000
:at 0.050
 :reward
           NIL
 :fixed-utility
                  NIL
Parameters for production STOP:
 :utility
      0.000
 :u
 :at 0.050
 :reward
           NIL
 :fixed-utility
                  NIL
(START INCREMENT STOP)
7> (spp start)
Parameters for production START:
:utility
            NIL
 :u 0.000
 :at 0.050
 :reward
            NIL
 :fixed-utility
                  NIL
(START)
> (spp-fct '((increment stop) :name :u))
Parameters for production INCREMENT:
 :NAME INCREMENT
:U 0.000
Parameters for production STOP:
 :NAME STOP
 :U 0.000
((INCREMENT 0) (STOP 0))
1> (spp :at 10)
((10) (10) (10))
2> (spp-fct nil)
Parameters for production START:
 :utility
            NIL
     0.000
 :u
:at 10.000
 :reward
           NIL
:fixed-utility
                  NIL
Parameters for production INCREMENT:
 :utility
             NIL
     0.000
 :at 10.000
           NIL
 :reward
 :fixed-utility
                  NIL
Parameters for production STOP:
:utility
            NIL
 :u 0.000
 :at 10.000
 :reward
           NIL
```

```
:fixed-utility
                   NIL
(START INCREMENT STOP)
1> (sgp :esc t :egs 3)
(T 3)
2> (run 10)
0.3
50
NIL
4> (spp-fct '(:name :utility :u))
Parameters for production START:
 :NAME START
 :UTILITY -1.806
 :U 0.000
Parameters for production INCREMENT:
 :NAME INCREMENT
 :UTILITY -1.594
 :U 0.000
Parameters for production STOP:
 :NAME
        ST0P
 :UTILITY -3.252
:U 0.000
((START -1.80585 0) (INCREMENT -1.5941277 0) (STOP -3.2521996 0))
5> (spp (start) (stop :name :utility) (increment :at 10))
Parameters for production START:
 :utility -1.806
 :u 0.000
 :at 0.050
Parameters for production STOP:
 :NAME STOP
 :UTILITY -3.252
(START (STOP -3.2521996) (10))
E> (spp (start end))
Parameters for production START:
 :utility
            NIL
 :u
     0.000
 :at 10.000
 :reward
            NIL
 :fixed-utility
                   NIL
#|Warning: Spp cannot adjust parameters because production END does not exist |#
(START : ERROR)
E> (spp start :u :ve)
Parameters for production START:
:U 0.000
#|Warning: NO PARAMETER VE DEFINED FOR PRODUCTIONS. |#
:VE ERROR
((0 :ERROR))
E> (spp)
#|Warning: get-module called with no current model. |#
NIL
```

Production Compilation Module

The production compilation module implements the process of learning new productions. Only the basic mechanisms of the module will be described here. Additional details on the production compilation process can be found in tutorial unit 7, the document named "compilation" in the docs/notes directory of the source code, and the spreadsheet named compilation in the docs directory provides the details of all the possible uses of a buffer in the two productions and whether it can or cannot then be composed.

Production compilation works by composing two productions that fire in sequence into one new production. When enabled, it will attempt to create a new production for each pair of productions that fire. To determine if two productions can be composed into one production all of the buffers that are referenced in those productions (in any condition or action) are checked to see if they have a compatible usage between the two productions. If any buffer does not have a compatible usage between the two productions then the productions cannot be composed.

Compatible usage is determined by the "compilation type" of the buffer. The compilation type also controls how the usage of that buffer in the productions gets composed into the new production. The provided module specifies five different compilation types, and each of the buffers in the system is considered to be of one of those types. The five types are goal, imaginal, retrieval, perceptual, and motor. The details of what constitutes valid usage for those compilation types are described in the excel spreadsheet compilation.xls and the mechanism used to create the new production based on the compilation type is described in the compilation document. It is possible to change the compilation type of a buffer using the specify-compilation-buffer-type command and it is also possible to add new compilation types to the system. For the buffers provided in the default system this is the assignment of buffer to compilation type:

Buffer Name	Compilation Type
goal	Goal
imaginal	Imaginal
retrieval	Retrieval
aural	Perceptual
aural-location	Perceptual
visual	Perceptual
visual-location	Perceptual
temporal	Perceptual
imaginal-action	Motor
production	Motor

manual	Motor
vocal	Motor

Any buffer added with a new module will be of the motor compilation type by default, but may be changed with the <u>specify-compilation-buffer-type command</u>.

If all of the buffers have a compatible usage between two successive productions which fire then the following situations are checked. If any of these are true the productions cannot be composed:

- is the time between the productions greater than the threshold time?
- does either production have a !eval! condition or action?
- does either production have a !bind! or !safe-bind! condition?
- does either production have a !bind! action?
- does either production use !mv-bind! in either the conditions or actions?
- does either production have a buffer overwrite action?
- does either production use any indirect actions?
- does either production use slot modifiers other than = in its conditions?
- does the first production make multiple requests using the same buffer?
- does the first production have a RHS !stop! action?

If none of those situations are true, then the two productions are composed into one new production.

After creating the new production, it is compared against the other productions in the procedural memory of the model. If the new production is not semantically equivalent to an existing production then the new production is also added to the procedural memory of the model. The parameters for the new production are set as follows:

- The :utility is the value of the :nu parameter.
- The :at parameter is set to the max of the :at parameters from its two parent productions.
- If both of the parent productions have a numeric :reward
 - O The new production gets the max of those two as its :reward.
- If only one of the parents has a numeric :reward
 - O The new production gets that value as its :reward.
- If neither parent has a numeric :reward, but at least one has a value of **t** for the :reward
 - O The new production will get a value of **t**.
- If both parents have a nil :reward value
 - O The new production also gets a **nil** :reward value.

If the newly formed production is semantically equivalent to an existing production then what happens depends on whether the production to which it is equivalent was also created by production compilation or whether it was one of the explicitly specified productions of the model and also whether utility learning is enabled.

If the production is equivalent to one of the explicitly specified productions or utility learning is not enabled, then nothing happens and the newly created production is ignored.

If the production is equivalent to one which was previously created by production compilation and utility learning is enabled then that production receives an update to its utility. The effective reward which it receives is the current :u value of the first of the two productions which fired to create it.

Parameters

:epl

The enable production learning parameter controls whether the production compilation process is enabled or disabled. If :epl is set to **t** then the process is enabled and if it is set to **nil** then it is disabled. The default value is **nil**.

:pct

The production compilation trace parameter controls whether information about the production compilation process is output to the model trace. If it is set to **t** then after each production fires a notice about the production compilation process will be displayed. If a new production was created then that production will be printed along with its parameter values. If a new production was not created then information indicating why not will be displayed. If the parameter is set to **nil** then no output will be given for production compilation. The default value is **nil**.

:tt

The threshold time parameter specifies the maximum amount of time in seconds that is allowed to pass between the firing of two productions and still allow them to be composed through production compilation. The default value is 2 seconds.

Commands

show-compilation-buffer-types

Syntax:

show-compilation-buffer-types -> nil

Remote command name:

show-compilation-buffer-types

Description:

The show-compilation-buffer-types command can be used to print out the current assignments of all the buffers' compilation types in the current model to the command trace. If there is no current model a warning is printed.

Examples:

```
> (show-compilation-buffer-types)
  Buffer
                         Type
VISUAL
                       PERCEPTUAL
                       PERCEPTUAL
TEMPORAL
AURAL-LOCATION
                       PERCEPTUAL
VISUAL-LOCATION
                       PERCEPTUAL
PRODUCTION
                       MOTOR
AURAL
                       PERCEPTUAL
VOCAL
                       MOTOR
IMAGINAL-ACTION
                       MOTOR
MANUAL
                       MOTOR
GOAL
                       GOAL
IMAGINAL
                       IMAGINAL
RETRIEVAL
                       RETRIEVALNIL
E> (show-compilation-buffer-types)
#|Warning: get-module called with no current model. |#
#|Warning: No production compilation module found |#
NIL
```

compilation-buffer-type

Syntax:

```
compilation-buffer-type buffer-name -> [buffer-type | nil ]
compilation-buffer-type-fct buffer-name -> [buffer-type | nil ]
```

Remote command name:

compilation-buffer-type

Arguments and Values:

```
buffer-name ::= the name of a buffer buffer-type ::= the compilation type of buffer-name
```

Description:

Compilation-buffer-type will return the compilation type for a buffer in the current model. If there is no current model or the buffer name is invalid then **nil** is returned.

Examples:

specify-compilation-buffer-type

Syntax:

```
specify-compilation-buffer-type buffer-name buffer-type -> [t | nil ] specify-compilation-buffer-type-fct buffer-name buffer-type -> [t | nil ]
```

Remote command name:

specify-compilation-buffer-type

Arguments and Values:

```
buffer-name ::= the name of a buffer buffer-type ::= the name of a valid compilation type
```

Description:

Specify-compilation-buffer-type allows one to change the compilation type for the buffers of the current model. If buffer-name and buffer-type are both valid, then that buffer will now be treated as a buffer-type buffer for compilation purposes, and **t** will be returned. If either parameter is invalid or there is no current model then a warning is printed and **nil** is returned.

Note that this setting is only valid until the model is reset because the production compilation module will return all buffers to their default types when it is reset. For that reason, if one wants to make a new module's buffer's default type something other than motor without needing to specify this call in each model definition that uses the buffer then this setting must be placed into the secondary reset function for that module to ensure that the setting is not overwritten by the resetting of the production compilation module (it uses the primary reset function to set the default values).

Examples:

```
1> (specify-compilation-buffer-type goal motor)
2> (specify-compilation-buffer-type-fct 'visual-location 'retrieval)
3> (show-compilation-buffer-types)
 Buffer
                         Type
                       PERCEPTUAL
VISUAL
                       PERCEPTUAL
TEMPORAL
AURAL-LOCATION
                       PERCEPTUAL
VISUAL-LOCATION
                       RETRIEVAL
PRODUCTION
                       MOTOR
AURAL
                       PERCEPTUAL
VOCAL
                       MOTOR
IMAGINAL-ACTION
                       MOTOR
                       MOTOR
MANUAL
GOAL
                       G0AL
IMAGINAL
                       IMAGINAL
RETRIEVAL
                       RETRIEVAL
E> (specify-compilation-buffer-type visual bad-type)
#|Warning: Invalid compilation buffer type BAD-TYPE. |#
NIL
E> (specify-compilation-buffer-type-fct 'bad-buffer 'motor)
#|Warning: No buffer named BAD-BUFFER found. |#
NIL
E> (specify-compilation-buffer-type goal perceptual)
#|Warning: get-module called with no current model. |#
#|Warning: No production compilation module found |#
NIL
```

Goal Module

The goal module provides the system with a goal buffer which is typically used to maintain the

current task state of a model and to hold relevant information for the current task. The only action

which the goal module provides a model is the creation of new chunks.

Goal buffer

The goal module sets the goal buffer to **not** be strict harvested.

Activation spread parameter: :ga

Default value: 0.0

Queries

The goal buffer only responds to the default queries.

'State busy' will always be nil.

'State free' will always be t.

'State error' will always be nil.

Requests

All

{slot value}*

Each slot in the request should be specified at most once.

The request is used to create a new chunk which is placed into the goal buffer immediately. It will result in two events which look like this in the trace with the <u>:trace-detail parameter</u> set to high:

0.050 GOAL 0.050 GOAL

CREATE-NEW-BUFFER-CHUNK GOAL SET-BUFFER-CHUNK GOAL CHUNKO

266

There is also a third event generated which will not show up in the trace. It is a maintenance event with the action clean-up-goal-chunk which performs some system clean up and will occur after the set-buffer-chunk event.

Modification Requests

All

{slot value}*

The goal buffer accepts modification requests and those specified buffer modifications are passed to mod-buffer-chunk for the goal buffer at the time of the request. It is assumed that the chunk will still be there at that time.

The event below will show up in the trace as a result of such an action being made by a production (always at the same time as the procedural request):

0.050 GOAL MOD-BUFFER-CHUNK GOAL

If there are slots specified which are not valid slot names they will be added as <u>extended slots</u> prior to sending the modification request. If such a slot is explicitly specified in the production then the extension will occur when the production is defined, but if the extension occurs because of a variablized slot name it will happen when the production fires and result in an event which looks like this indicating that the procedural module extended the possible slots:

0.050 PROCEDURAL EXTEND-BUFFER-CHUNK GOAL

A modification request for the goal buffer is equivalent to performing the same buffer modification action in the production. The only difference is that by using a modification request to perform the change to the chunk the effort is attributed to the goal module instead of the procedural module which may be important for purposes of <u>predicting the BOLD response</u> or for tracing purposes.

Commands

goal-focus

Syntax:

```
goal-focus {chunk-name} -> [ goal-chunk | nil ]
goal-focus-fct {chunk-name} -> [ goal-chunk | nil ]
```

Remote command name:

goal-focus

Arguments and Values:

```
chunk-name ::= the name of a chunk
```

goal-chunk ::= the name of the chunk in the goal buffer or the chunk which will be in the goal buffer

Description:

If chunk-name is provided, then goal-focus will schedule an event to put that chunk into the goal buffer of the current model at the current time with a priority of :max. This will result in the unrequested query being true for the buffer because this chunk was not placed into the buffer as a result of a module request. There will also be a maintenance event scheduled with an action of clear-delayed-goal following the set-buffer-chunk event which updates some internal information for the goal module but which will not show up in the trace. If an event is created to place this chunk into the buffer then chunk-name is returned. If chunk-name is not a valid chunk or there is no current model then a warning is printed and **nil** is returned.

If chunk-name is not provided, then the chunk currently in the goal buffer is printed if there is one and that chunk's name is returned. If the buffer is empty, then a message stating that is printed and **nil** is returned. If there is a pending change to the chunk in the goal buffer (an event generated by goal-focus has been scheduled but not yet executed), then a notice of that is printed along with any chunk which may be in the buffer currently and the name of the chunk which will be in the buffer is returned.

This command typically occurs in a model to set the initial chunk in the goal buffer. If declarative learning of past goals is something that the model will be doing, then one should consider using <u>define-chunks</u> to create that initial goal instead of <u>add-dm</u> so that it is not in declarative memory prior to the start of the task.

Examples:

```
> (goal-focus)
Goal buffer is empty
NIL

1> (goal-focus black)
BLACK
```

```
2> (goal-focus)
Will be a copy of BLACK when the model runs
BLACK
  COLOR BLACK
BLACK
3> (run-n-events 2)
     0.000 GOAL
0.000 -----
                                     SET-BUFFER-CHUNK GOAL BLACK NIL
     0.000
                                     Stopped because event limit reached
0.0
2
NIL
4> (goal-focus)
BLACK-0
  COLOR BLACK
BLACK-0
5> (goal-focus-fct 'free)
FREE
6> (goal-focus-fct )
Will be a copy of FREE when the model runs
Currently holds:
BLACK-0
  COLOR BLACK
FREE
7> (run-n-events 1)
     0.000 GOAL
                                     SET-BUFFER-CHUNK GOAL FREE NIL
     0.000
                                     Stopped because event limit reached
0.0
NIL
8> (goal-focus)
FREE-0
  NAME FREE
FREE-0
E> (goal-focus notchunk)
#|Warning: NOTCHUNK is not the name of a chunk in the current model - goal-focus failed |#
NIL
E> (goal-focus black)
#|Warning: get-module called with no current model. |#
NIL
mod-focus
Syntax:
```

Remote command name:

mod-focus '{slot-name slot-value}'*

mod-focus {slot-name slot-value}* -> [chunk-name | nil]
mod-focus-fct ({slot-name slot-value}*) -> [chunk-name | nil]

Arguments and Values:

```
slot-name ::= the name of a slot
slot-value ::= the value to set for the value of the corresponding slot-name
chunk-name ::= the name of the chunk in the goal buffer
```

Description:

Mod-focus is used to modify the chunk currently in the goal buffer or the chunk which will be in the buffer as a result of a <u>goal-focus</u> call. It schedules an event with the action goal-modification and priority :max for the current model. That event calls <u>mod-buffer-chunk</u> for the goal buffer with the slot-name and slot-value pairs provided.

If there is a chunk in the buffer or a pending goal-focus and the modifications are valid for that chunk, then that chunk's name is returned after scheduling the event. If there is no current model, no chunk in the goal buffer and no pending goal-focus, or the modifications are invalid, then a warning is printed and **nil** is returned without scheduling the event.

Examples:

```
1> (define-model test
     (chunk-type test color state)
     (goal-focus-fct (car (define-chunks (state start) (start)))))
TEST
2> (run 1)
     0.000
             GOAL
                                     SET-BUFFER-CHUNK GOAL CHUNKO NIL
     0.000
             PR0CEDURAL
                                     CONFLICT-RESOLUTION
     0.000
                                     Stopped because no events left to process
0.0
NIL
3> (mod-focus color green)
CHUNKO-0
4> (goal-focus)
CHUNK0-0
   STATE START
CHUNKO-0
5> (run 1)
     0.000
             GOAL
                                     GOAL-MODIFICATION
             PROCEDURAL
     0.000
                                     CONFLICT-RESOLUTION
     0.000
             _ _ _ _ _ _
                                     Stopped because no events left to process
0.0
2
NIL
6> (goal-focus)
CHUNK0-0
```

```
STATE START
   COLOR GREEN
CHUNKO-0
7> (mod-focus-fct '(state busy))
CHUNKO-0
8> (goal-focus)
CHUNKO-0
  STATE START
   COLOR GREEN
CHUNK0-0
9> (run 1)
                                    GOAL-MODIFICATION
     0.000
             GOAL
     0.000
            PROCEDURAL
                                    CONFLICT-RESOLUTION
     0.000
                                    Stopped because no events left to process
0.0
2
NIL
10> (goal-focus)
CHUNKO-0
   STATE BUSY
   COLOR GREEN
CHUNK0-0
11> (clear-buffer 'goal)
CHUNKO-0
12E> (mod-focus color green)
#|Warning: No chunk currently in the goal buffer and no pending goal-focus chunk to be
modified. |#
NIL
E> (mod-focus slot)
#|Warning: Odd length modifications list in call to mod-focus. |#
NİL
E> (mod-focus bad-slot green)
#|Warning: Invalid slot name BAD-SLOT specified for mod-focus. |#
NIL
E> (mod-focus state start)
#|Warning: get-module called with no current model. |#
NİL
```

Imaginal Module

The imaginal module provides the system with an imaginal buffer which is typically used to maintain

context relevant to the current task and a buffer called imaginal-action which can be used to call user

functions for manipulating the contents of the imaginal buffer. The imaginal buffer's requests

operates like the goal buffer's request in creating new chunks. However, unlike the goal buffer,

requests to create chunks using the imaginal module take time. It also accepts modification requests

which it also handles the same way the goal buffer does, except again there is a cost for doing that

with the imaginal module.

Parameters

:imaginal-delay

The imaginal-delay parameter controls how long it takes a request or modification request to the

imaginal buffer to complete. It can be set to a non-negative time (in seconds) and defaults to .2.

:vidt

The variable imaginal delay time parameter controls whether the actions of the imaginal buffer take

exactly the amount of time specified by :imaginal-delay or if they are randomized with the

randomize-time command. If it is set to t, then randomize-time is used to adjust the delay time, and

if it is set to **nil**, which is the default, then the delay times are fixed at the :imaginal-delay time.

Chunk-types & Chunks

The imaginal module defines the following two chunk-type:

(chunk-type generic-action action slots result)
(chunk-type simple-action action slots (simple t)))

It creates no initial chunks.

Imaginal buffer

The imaginal buffer is typically used to create and hold task relevant information. It operates similar

to the goal buffer except that there is a time cost associated with creating and manipulating the

chunks.

Activation spread parameter: :imaginal-activation

272

Default value: 1.0

Queries

The imaginal buffer only responds to the default queries.

'State busy' will be **t** after a new request or modification request is received (through either of the module's buffers). If the request came through the imaginal buffer the state will return to **nil** once the request is completed. If the request came through the imaginal-action buffer then the busy state will

remain **t** until the <u>set-imaginal-free command</u> is used to clear the busy state back to **nil**.

'State free' will be t when the 'state busy' flag is nil i.e. when the module is not currently handling a

request, and it will be **nil** when the module is handling a request.

'State error' will be **nil** unless set by the user with the <u>set-imaginal-error command</u> which will cause

it to be t. If set with the command, it will stay t until the next request is made to either of the

module's buffers. When the error state is set the imaginal buffer's failure flag will also be set.

Requests

All

{slot value}*

Each slot should be specified at most once and no modifiers are allowed.

The request is used to create a new chunk which is placed into the imaginal buffer after <u>:imaginal-delay</u> seconds. That will result in two events showing up in the trace:

IMAGINAL

CREATE-NEW-BUFFER-CHUNK IMAGINAL

0.750 IMAGINAL

0.750

SET-BUFFER-CHUNK IMAGINAL VISUAL-OBJECT1

There are three other maintenance events generated which will occur at the same time as the two actions shown but will not show up in the trace. The first occurs before the create-new-buffer-chunk event and will have an action of goal-style-request. The second has an action of clean-up-goal-chunk which performs some system cleanup as happens for the goal module and will occur after the set-buffer-chunk event. The final event, which occurs after the clean-up-goal-chunk event, has the action set-imaginal-free and serves to set the module back to state free after it has created the new chunk.

273

The module can only handle one request at a time. If a request is made while the module is busy processing a previous request it will print a warning and ignore the newer request.

 $\#\$ | Warning: Imaginal request made to the IMAGINAL buffer while the imaginal module was busy. New request ignored. #

Modification requests

All

{slot value}*

The imaginal buffer accepts modification requests and those specified buffer modifications are passed to <u>mod-buffer-chunk</u> for the imaginal buffer after <u>:imaginal-delay</u> seconds have passed. It is assumed that the chunk will still be there at that time.

This event will show up in the trace as a result of such an action:

1.000 IMAGINAL MOD-BUFFER-CHUNK IMAGINAL

If there are slots specified which are not valid slot names they will be added as <u>extended slots</u> prior to sending the modification request. If such a slot is explicitly specified in the production then the extension will occur when the production is defined, but if the extension occurs because of a variablized slot name it will happen when the production fires and result in an event which looks like this indicating that the procedural module extended the possible slots:

0.800 PROCEDURAL EXTEND-BUFFER-CHUNK IMAGINAL

There will also be a maintenance event generated which will not be output to the trace. It will have the action of set-imaginal-free and occur after the mod-buffer-chunk event. It serves to set the module back to the free state after the buffer-modification is complete.

Imaginal-action buffer

The imaginal-action buffer is available for users to extend the capabilities of the imaginal module. It does not perform any actions on its own nor does the module place any chunks into the buffer. It

essentially provides a hook for the modeler to perform actions on the imaginal buffer's chunk which

are attributed to the imaginal module.

Activation spread parameter: :imaginal-action-activation

Default value: 0.0

Queries

The imaginal-action buffer only responds to the default queries.

'State busy' will be **t** after a new request or modification request is received (through either buffer).

If the request came through the imaginal buffer the state will return to nil once the request is

completed. If the request came through the imaginal-action buffer then the busy state will remain t

until the set-imaginal-free command is used to clear the busy state back to nil.

'State free' will be t when the 'state busy' flag is **nil** i.e. when the module is not currently handling a

request and it will be **nil** when the module is handling a request.

'State error' will be **nil** unless set by the user with the <u>set-imaginal-error command</u> which will cause

it to be t. If set with the command, it will stay t until the next request is made to either of the

module's buffers. When the error state is set the imaginal-action buffer's failure flag will also be set.

Requests

Generic action

action command-name

{**slots** (slot-name*)}

This request to the imaginal-action buffer requires the action slot be specified and its value must

name a command. An optional list of slot names may be provided as the value of the slots slot in the

request. Every slot-name provided must be the name of a slot of the chunk currently in the imaginal

buffer. When the request is received by the module the state busy query for the module will be set to

t, the state error query will be set to nil, and the command specified by command-name will be

called. If there is a list of slot names provided they will be passed to the command, otherwise the

command will be called with no parameters. No chunks will be placed into the buffer by default and

the command which is called must return the module to the state free using the set-imaginal-free

275

<u>command</u> either directly or by scheduling an event to do so at a later time. The command may also call the <u>set-imaginal-error command</u> to set the state error to **t** for the module if that is needed.

This action allows users to manipulate the chunk which is in the imaginal buffer via arbitrary code and have the action attributed to the imaginal module i.e. it is essentially the same as a call to !eval! in a production except that the request is marked as going to the imaginal module and the module indicates "state busy" during that time. This allows modelers to add commands which they feel should be attributed to the imaginal module (for example rotations, translations or other manipulations of the representation) without having to change the code for the module.

No events are explicitly generated by this request, but the function which is called should generate events for any changes it makes to the buffer and to schedule the call to set-imaginal-free.

Simple action

```
action command-name
simple t
{slots (slot-name*)}
```

This request to the imaginal-action buffer is very similar to the generic action described above. The distinction between the two is that the simple action requires that an additional slot named simple be specified with the value t in the request. The difference between the two is that the simple action handles some of the event scheduling automatically.

When the request is received by the module the state busy query for the module will be set to **t**, the state error query will be set to **nil**, and the command specified by command-name will be called. If there is a list of slot names provided the command will be passed those names, otherwise the command will be called with no parameters. That command should return either the name of a chunk or **nil**. If it returns the name of a chunk then after the current <u>:imaginal-delay</u> time passes that chunk will be copied into the imaginal buffer, and the module will be returned to the free state. If the function returns **nil** then after the imaginal-delay time passes the module will be set to the free state and it will be marked as also being in the error state. This request provides an easy way to have code create arbitrary chunks for the imaginal buffer without having to schedule any events or manage the internal imaginal state flags directly.

A valid request of this type will generate two events. One will be an event with the action of setimaginal-free. The other depends on whether the action function returned a chunk or **nil**. If it returns

a chunk then an event with the action set-buffer-chunk will be generated, but if **nil** was returned an event with the action set-imaginal-error will be created.

Commands

set-imaginal-free

Syntax:

set-imaginal-free -> [t | nil]

Remote command name:

set-imaginal-free

Description:

Set-imaginal-free is used to clear the busy state of the imaginal module in the current. It should only be used by commands that are called as a result of a generic action request to the imaginal-action buffer.

If there is a current model then it returns **t**. If there is no current model then it returns **nil** and no change is made.

Examples:

```
> (set-imaginal-free)
T

E> (set-imaginal-free)
#|Warning: get-module called with no current model. |#
#|Warning: Call to set-imaginal-free failed |#
NIL
```

set-imaginal-error

Syntax:

set-imaginal-error -> [t | nil]

Remote command name:

set-imaginal-error

Description:

Set-imaginal-error is used to set the error state of the imaginal module in the current model. It should only be used by commands that are called as a result of a generic action request to the imaginal-action buffer. It causes queries of either of the imaginal module's buffers for 'state error' to return **t** and also sets the failure flags for both buffers as requested failures using <u>set-buffer-failure</u>. The module's error state will remain until another request is made to either of the module's buffers.

If there is a current model then it returns **t**. If there is no current model then it prints a warning, returns **nil**, and no change is made.

Examples:

```
> (set-imaginal-error)
T

E> (set-imaginal-error)
#|Warning: get-module called with no current model. |#
#|Warning: Call to set-imaginal-error failed |#
NIL
```

Declarative module

The declarative module provides the model with a declarative memory which stores the chunks that are generated by the model and it provides a mechanism for retrieving those chunks through its retrieval buffer. The retrieval of chunks from the declarative memory depends on many factors that affect the accuracy and speed with which a chunk can be retrieved based on research of human memory performance.

The model's declarative memory (DM) consists of all the chunks which are explicitly added to it by the modeler as well as all of the chunks which are cleared from the buffers. Whenever a chunk is cleared from a buffer the declarative module merges that chunk into the model's DM. The merging process compares the chunk being added to the chunks already in DM. If the chunk being added is equivalent to a chunk which is already in DM, then the new chunk is merged with the existing chunk using the merge-chunks command and that chunk is strengthened by giving it another reference at the time of the merging. If the chunk being added is not equivalent to any chunk in DM then that chunk is added to DM.

Retrieval of chunks from DM is done through requests to the module. A request specifies a description of a chunk which is desired and if there are chunks in DM which match the specification request, then one of those chunks is placed into the retrieval buffer as a response. If no such chunk is found then it signals that a failure to retrieve occurred by signaling the state error, setting the buffer's failure flag, and leaving the buffer empty.

The time it takes to complete the request and how a single chunk is chosen among possibly many which match the request are controlled by several parameters. First, the setting of the <u>:esc parameter</u> determines very coarsely what process is used.

If the :esc parameter is **nil** then only the symbolic matching is considered. The chunks are always retrieved immediately and if there is more than one chunk which matches the request the setting of <u>:er</u> determines how a chunk is chosen. If :er is **t** then the choice is made randomly. If :er is **nil** then a deterministic process is used such that the same chunk will be chosen for that model each time the same set of possible chunks could be retrieved. However, that process is not specified as part of the declarative module's definition because it is not intended to be a process which one relies upon for chunk preferences.

If the :esc parameter is **t** then the selection of which chunk is retrieved and how long it takes is controlled by a quantity called activation. Each chunk in DM has an activation value associated with it and among the chunks which match the request the one with the highest activation value, above a parameterized threshold, is the one that will be retrieved. If no matching chunk has an activation above the threshold then a failure to retrieve occurs. The activation of the chunk retrieved also determines how long the request takes to complete. If multiple matching chunks have the same highest activation, then the :er parameter determines how one of those chunks is chosen in the same way it happens when :esc is **nil**.

Activation

How the activation of a chunk is computed is based on the setting of several parameters which determine which mechanisms are to be used and those will be discussed in the specific sections which follow. Here is the general equation for the activation (A) of a chunk i:

$$A_i = B_i + S_i + P_i + \varepsilon_i$$

 B_i : This is the <u>base-level activation</u> and reflects the recency and frequency of use of the chunk.

 S_{i} : This is the <u>spreading activation</u> value computed for the chunk which reflects the effect that the current contents of the buffers have on the retrieval process.

*P*_i: This is the <u>partial matching</u> value computed for the chunk which reflects the degree to which the chunk matches the specification requested.

 ε_i : A <u>noise</u> value with both a transient and permanent component.

Each of those components will be described in more detail below. Note that for each of those components it is possible for the modeler to replace the mechanism as described with their own mechanism using the hook function parameters available in the declarative module.

Base-level

The base-level component, B_i , is computed differently based on the setting of the $\underline{:bll}$ and $\underline{:ol}$ parameters.

If :bll is **nil** then the setting of :ol does not matter and the base-level is a constant value determined by the <u>:blc parameter</u> or specific user settings for the chunk.

$$B_i = \beta_i$$

 βi : A constant offset which is determined by the :blc parameter or the chunk's :base-level parameter.

If :bll is set to a number, then the setting of :ol determines how the base-level is computed.

If :ol is **nil** then this equation is used:

$$B_i = \ln(\sum_{i=1}^n t_j^{-d}) + \beta_i$$

n: The number of presentations for chunk *i*.

t_j: The time since the *jth* presentation. A presentation is either the chunk's initial entry into DM or when another chunk is merged with a chunk which is in DM (these are also called the chunk's references).

d: The decay parameter which is set using the :bll parameter.

 βi : A constant offset determined by the :blc parameter.

If :ol is **t** then this approximation to that equation is used which does not require recording the complete history of the chunk:

$$B_i = \ln(n/(1-d)) - d * \ln(L) + \beta_i$$

n: The number of presentations of chunk *i*.

L: The lifetime of chunk *i* (the time since its creation).

d: The decay parameter (the value of :bll).

 βi : A constant offset determined by the :blc parameter.

If :ol is set to a number, then a hybrid of those is used such that the specified number of true references are used and the approximation is used for any remaining references (if there are not more total references than the parameter setting for :ol ($n \le k$) then the full equation is used and the extra term in this equation is not computed):

$$B_{i} = \ln(\sum_{j=1}^{k} t_{j}^{-d} + \frac{(n-k) * (t_{n}^{1-d} - t_{k}^{1-d})}{(1-d) * (t_{n} - t_{k})}) + \beta_{i}$$

k: is the value of the :ol parameter.

 t_j : The time since the jth presentation (for this equation t_1 is the time since the most recent presentation and t_n the time since the first presentation)

n: The total number of presentations of chunk *i*.

d: The decay parameter (the value of :bll).

 βi : A constant offset determined by the :blc parameter.

Spreading Activation

Whether spreading activation is used is determined by the setting of the <u>:mas parameter</u>. If it is **nil**, which is the default value, then the value of S_i is 0 in the activation equation. If :mas is set to a number, then this equation determines the spreading activation component of chunk i's activation:

$$S_i = \sum_{k} \sum_{j} W_{kj} S_{ji}$$

The elements k being summed over are all of the buffers in the model which currently contain a chunk and which has a non-zero source activation setting.

The elements j being summed over are the chunks which are in the slots of the chunk in buffer k (these are referred to as the sources of activation).

 W_{kj} : This is the amount of activation from source j in buffer k. It is the source activation of buffer k divided by the number of sources j in that buffer by default.

 S_{ii} : This is the strength of association from source j to chunk i.

strength of association

The strength of association, S_{ji} , between two chunks is computed using the following equations by default, but can also be set explicitly by the modeler using the <u>add-sji command</u> or thorough the <u>sji-hook parameter</u>.

If chunks *j* and *i* are not the same chunk and *j* is not in a slot of chunk *i*:

$$S_{ji} = 0$$

If chunks *j* and *i* are the same chunk or chunk *j* is in a slot of chunk *i*:

$$S_{ii} = S - \ln(fan_{ii})$$

S: The maximum associative strength set with the :mas parameter.

*fan*_{ii}: a measure of how many chunks are associated with chunk j.

The fan is typically thought of as the number of chunks in which j is the value of a slot plus one for chunk j being associated with itself. However, because j may appear in more than one slot of the chunk i, this is the specific calculation which is used to compute the fan:

$$fan_{ji} = \frac{1 + slots_j}{slotsof_{ji}}$$

*slots*j: the number of slots in which j is the value across all chunks in DM. $slotsof_{ji}$: the number of slots in chunk i which have j as the value (plus 1 when chunk i is chunk j).

The S_{ji} value can become negative as the fan value grows, but that is generally an undesirable situation. By default the declarative module will print a warning if S_{ji} becomes negative due to that calculation and use 0.0 instead of the negative value, but that can be changed using the <u>:nsji</u> parameter.

Partial Matching

When the partial matching process is enabled it is possible for a chunk that is not a perfect match to the retrieval specification to be the one that is retrieved. To enable the partial matching one needs to set the \underline{mp} parameter to a number instead of its default of nil. When enabled, the similarity of the values requested to those in the slots of the chunks in DM are computed to determine the activation value. If partial matching is disabled then P_i is 0, but if it is enabled it is computed with this equation:

$$P_i = \sum_k PM_{ki}$$

The elements k being summed over are the slot values of the retrieval specification for slots with an = or – modifier only.

P: This is a match scale parameter (set with :mp) that reflects the amount of weighting given to the similarity.

 M_{ki} : The similarity between the value k in the retrieval specification and the value in the corresponding slot of chunk i.

similarities

The possible range of default similarity values is configurable using the maximum similarity parameter (:ms) and the maximum difference parameter (:md). The default range is from 0 to -1 with 0 being the most similar and -1 being the largest difference. In general, the similarity can be thought of more as a difference penalty because the concept is not to boost the similar items, but to penalize the different ones. Since it gets added to the activation value, the values should be negative for items that are not the same and using positive similarities is not recommended (though not prohibited).

By default, a chunk has a maximum similarity to itself and a maximum difference to all other chunks. Any other similarities must be set explicitly by the modeler either using the <u>set-similarities command</u> or the <u>sim-hook parameter</u>. For non-chunk slot values in a retrieval request, the similarity is the maximum similarity if the values are equal using the <u>chunk-slot-equal</u> command and the maximum difference if they are not. The only way to set non-default similarity values for items which are not chunks is through the sim-hook capability. Similarities set explicitly with the declarative commands or through the sim-hook function are not constrained by the :ms and :md parameters.

One final note on the computation of the M_{ki} values. If the retrieval specification is requesting the value using the negation modifier, then the M_{ki} value for that slot test k is not the specific similarity value between the items involved. If the similarity between those items is equal to the maximum similarity then M_{ki} is set to the maximum difference. Otherwise, M_{ki} is set to 0 for that slot. Essentially, if they are the same (or perfectly similar items), then the chunk is given the maximum penalty since the request specified that it not have that value and if they are different (any similarity other than a perfect match) then no penalty is applied.

Noise

The noise calculation has two components. There is a transient component which is computed each time a retrieval request is made and there is a permanent component which is associated with each chunk when it is entered into DM. The total noise added to the activation is the sum of the two components. Often, the transient component is sufficient for modeling and the permanent noise is left disabled.

Each one is generated using the <u>act-r-noise command</u>. Thus they are generated from a logistic distribution with a mean of 0 and an s as specified by the corresponding parameter of the declarative module. The parameter for the transient noise s value is <u>:ans</u> and the parameter for the permanent noise s value is <u>:pas</u>. The default value for each parameter is **nil**. For the transient noise that means to not generate any transient noise and for the permanent noise it means to leave the chunk's permanent noise set to 0. The permanent noise is always added to the activation of the chunk and can be set by the modeler using the <u>sdp command</u> for creating specific offset values when needed.

Retrieval time

The time that it takes the declarative module to respond to a request for a chunk, *i*, is determined by the activation that the chunk has using this equation when the subsymbolic computations are enabled:

$$RT = Fe^{-(f*A_i)}$$

RT: The time to retrieve the chunk in seconds

 A_i : The activation of the chunk i which is being retrieved

F: The <u>latency factor parameter</u>

f : The <u>latency exponent parameter</u>

If there is no chunk found in response to a request or the chunk with the highest activation is below the retrieval threshold then the time required to indicate a failure to retrieve any chunk is determined by this equation when subsymbolic computations are enabled:

$$RT = Fe^{-(f*\tau)}$$

RT: The time until the failure is noted in seconds.

τ : The retrieval threshold parameter

F: The <u>latency factor parameter</u>

f: The <u>latency exponent parameter</u>

Declarative finsts

The declarative module maintains a record of the chunks which have been retrieved and provides a mechanism which allows one to indicate whether a retrieval request should search only those which have or have not been so marked. This is done through the use of a set of finsts (fingers of instantiation) which mark those chunks. The finsts are limited in the number that are available and how long they persist specified by the parameters <u>:declarative-num-finsts</u> and <u>:declarative-finst-span</u>

respectively. If more finsts are required than are available, then the oldest one (the one marking the chunk retrieved at the earliest time) is removed and used to mark the most recently retrieved chunk. The details on how to use the finsts are found in the description of the <u>retrieval buffer requests</u>.

Parameters

The declarative module has a lot of parameters which can be set and they fall into four general categories. The first category contains the parameters which are used in the activation equations as described above. The next category contains the parameters which control basic functionality of the module. The third category is parameters which allow the user to adjust the chunk activation equation: each of the four primary components may be replaced by the user, the default computations for strengths of association and similarities can be replaced, and additional terms may be added to the equation. The final set of parameters allow the user to install commands to monitor the operations of the module.

Note on parameters for the declarative module. There are some parameters which should not be adjusted once chunks have entered DM. The reason for this is that the module does not attempt to reconcile differences in interpretations which may result due to such changes i.e. chunks which have had their internal parameters set under one set of parameters may no longer be valid under different settings. A warning will be printed if one does change such parameters after there are chunks in DM. That warning does not mean that things will necessarily break (there are some situations where the warning can be safely ignored), but one should be cautious when using things in that manner. The critical parameters are the <u>:bll</u> and <u>:mas</u> parameters of the declarative module as well as the parameters <u>:esc</u> and <u>:ol</u>.

:act

The activation trace parameter controls whether or not the declarative module should print the details of a chunk's activation computation when it is computed (whether during a retrieval request or otherwise). If it is set to **t** then all of the components of the equation are output to the model trace when a chunk's activation is computed, and if it is set to **nil** then no extra trace is generated. The default value is **nil**.

There are also two lesser output levels available for the activation trace if one specifies a setting of **medium** or **low** for the parameter value. The medium output level does not print the information

about chunks which did not match a retrieval request and the low level only prints the final activation values computed for the chunks.

:activation-offsets

This parameter allows one to specify functions which can extend the activation equation with new terms. This parameter can be set to a command which takes one parameter and any number of such commands may be set (the reported value of this parameter is a list of all commands which have been set). Whenever a chunk's activation is computed each of the commands that has been set for this parameter will be called with one parameter which is the name of the chunk. If a command called returns a number then that value will be added to the activation of the chunk and if the activation trace is enabled a line will be shown indicating the name of the command and the offset added. If a command returns any other value then no change is made to the activation of the chunk. If the parameter is set to **nil** then all commands are removed from the activation-offsets list. A commands should only be set once. If a commands is specified more than once as a value for the activation-offsets a warning will be displayed and a value of **nil** will be returned as the current value.

:ans

The activation noise s parameter specifies the s value used to generate the instantaneous noise added to the activation equation if it is set to a positive number. If it is set to **nil**, which is the default, then no instantaneous noise is added to the activations. Recommended values for the noise parameter are in the range [.2,.8].

:bl-hook

This parameter allows one to override the base-level calculation. If it is set to a command then that command will be passed one parameter which is the name of the chunk for which a base-level is needed. If the command returns a number then that will be the B_i value used in the activation equation, otherwise the standard base-level calculation will be used.

:blc

The base-level constant parameter specifies the default value for the βi component of the base-level equations. If base-level learning is disabled (:bll is **nil**) and the :base-level parameter for the chunk is set through the <u>sdp command</u> then that overrides the :blc setting. The default value is 0.0.

:bll

The base-level learning parameter controls whether base-level learning is enabled, and also sets the value of the <u>decay parameter</u>, d. It can be set to any positive number or the value **nil**. The value **nil** means do not use base-level learning and is the default value, a number means that base-level is enabled and the given value is the decay parameter. The recommended value for :bll is .5, and it is one of the few parameters which have a strong recommended value.

:cache-sim-hook-results

This parameter can be used to help improve the performance of the system when using a similarity hook function (set using the sim-hook parameter). If this parameter is set to t then results from calling a similarity hook function will be stored by the delcarative module and if a similarity is needed between those same values again it will use the recorded value instead of calling the function. That means this should only be set if the similarity hook always provides the same similarity value for a pair of items, and the set of items themselves are expected to be repeated/reused. Those cached values will persist across a reset as long as the same sim-hook value is set in the model. The default value is nil which means that similarity hook function values are not recorded for futue use.

:chunk-add-hook

This parameter allows one to specify commands to be called automatically when chunks are added to the current model's DM. This parameter can be set with a command which takes one parameter and any number of such commands may be set (the reported value of this parameter is a list of all commands which have been set). Whenever a chunk is added into DM each of the commands that has been set will be called with one parameter which is the name of the chunk that was added into DM. This call is made after the chunk has been added to DM and its declarative parameters updated appropriately. The return values of these commands are ignored. If the parameter is set to **nil** then all commands are removed from the chunk-add-hook. A command should only be set once. If a specific command is specified more than once as a value for the chunk-add-hook a warning will be displayed and a value of **nil** will be returned as the current value.

:chunk-merge-hook

This parameter allows one to specify commands to be called automatically when chunks are merged into to the current model's DM. This parameter can be set with a command which takes one parameter and any number of such commands may be set (the reported value of this parameter is a

list of all commands which have been set). Whenever a chunk is merged into DM each of the commands that has been set will be called with one parameter which is the name of the chunk that was merged into DM. This call is made after the chunk has been merged into DM and its declarative parameters updated appropriately. The return values of these commands are ignored. If the parameter is set to **nil** then all commands are removed from the chunk-merge-hook. A command should only be set once. If a specific command is specified more than once as a value for the chunk-merge-hook a warning will be displayed and a value of **nil** will be returned as the current value.

:declarative-finst-span

This parameter controls how long a finst can mark a chunk as having been recently retrieved. After a finst has been marking a chunk for this amount of time the finst is removed and the chunk is no longer marked as recently retrieved. It can be set to any positive number and defaults to 3.0.

:declarative-num-finsts

This parameter controls how many finsts are available in the declarative module. It can be set to any positive number and the default is 4.

:declarative-stuffing

This parameter controls whether or not the declarative module will place chunks into the retrieval buffer without a corresponding request i.e. stuff the buffer. The default value is **nil** which means to disable the mechanism. If it is set to a number that enables the mechanism and sets the period of time in seconds for the potential stuffing actions to occur.

When it is enabled, at time 0 and again whenever the module is not busy and either the buffer empties or the specified time period has passed a new stuffing attempt will occur. The chunk that will be stuffed into the buffer is the chunk with the current highest activation. That stuffing will not interrupt an ongoing retrieval request nor overwrite a requested chunk in the buffer. This mechanism is a very speculative bottom-up approach which needs further refinement based on use — if you use this parameter please let me know how it worked out and any recommendations or comments you have about it.

:le

The latency exponent value, f, in the <u>equation for retrieval times</u>. It can be set to any non-negative value and defaults to 1.0.

:lf

The latency factor value, F, in the <u>equation for retrieval times</u>. It can be set to any non-negative value and defaults to 1.0.

:mas

The maximum associative strength parameter controls whether the spreading activation calculation is used, and if so, what the S value in the <u>Sji calculations</u> will be. It can be set to any number or the value **nil**. The value **nil** means do not use spreading activation and is the default value, any number means that spreading activation is enabled.

:md

The maximum difference. This is the default similarity value between two items which are not <u>chunk-slot-equal</u>. It can be set to any number and defaults to -1.0.

:mp

The mismatch penalty parameter controls whether the partial matching system is enabled, and if so, specifies the value of the penalty parameter, P, in the <u>activation equation</u>. It can be set to any number or the value **nil**. The value **nil** means do not use partial matching (only exact matches can be retrieved), and is the default. If it is set to a number then partial matching is enabled.

:ms

The maximum similarity. This is the default similarity value between items which are <u>chunk-slot-equal</u>. It can be set to any number and defaults to 0.0.

:noise-hook

This parameter allows one to override the noise calculation. If it is set to a command then that command will be passed one parameter which is the name of the chunk for which a noise value is needed. If the command returns a number then that will be the noise value used in the activation equation.

:nsji

Whether or not to allow negative Sji values from the <u>strength of association calculation</u>. Can be set to **t** which means that they are allowed, **warn** which means that negative values will be treated as 0 and a warning will be displayed, or **nil** which means that negative values will be treated as 0 and no warning will be displayed. A value of **warn** or **nil** does not prevent the user from setting explicit negative values if desired. The default is **warn**.

:partial-matching-hook

This parameter allows one to override the partial matching calculation. If it is set to a command then that command will be passed two parameters. The first will be the name of the chunk for which a partial matching value is needed and the second will be the <u>chunk-spec id</u> of the request. If the function returns a number then that will be the P_i value used in the activation equation.

:pas

The permanent activation noise s parameter specifies the s value used to generate the permanent noise added to the activation equation of a chunk if it is set to a positive number. The permanent noise is only generated once when the chunk is added to DM. If :pas is set to **nil**, which is the default, then no permanent noise is automatically generated for the chunks, but it may still have such a value set explicitly using the <u>sdp command</u>.

:retrieval-request-hook

This parameter allows one to specify commands to be called automatically when a retrieval request is made. This parameter can be set with a command which takes one parameter and any number of such commands may be set (the reported value of this parameter is a list of all commands which have been set). When there is a start-retrieval event these commands will be called with the chunk-specid of the request as the only parameter. The return values of those commands are ignored. If the parameter is set to **nil** then all commands are removed from the retrieval-request-hook. A command should only be set once. If a specific command is specified more than once as a value for the retrieval-request-hook a warning will be displayed and a value of **nil** will be returned as the current value.

:retrieval-set-hook

This parameter allows one to specify commands to be called during the retrieval process. This parameter can be set with a command which takes one parameter and any number of such commands

may be set (the reported value of this parameter is a list of all commands which have been set). After the set of chunks which match have been determined and their activations are calculated these commands will be called with the list of the chunk names that match the request. The first chunk on the list is the one that will be retrieved (if its activation is above the threshold). These commands can be used to override the choice of which chunk to retrieve. If a command returns a list of a chunk name and a number, then that chunk will be the one placed in the retrieval buffer after that many seconds pass. If a command returns a number, then the declarative module will signal a retrieval failure after that many seconds pass. If a command returns anything else it is ignored, and the normal retrieval process will occur. If more than one command on the list for this parameter returns a value, then none of those values will be used and the default mechanisms will be applied. If the parameter is set to **nil** then all commands are removed from the retrieval-set-hook. A command should only be set once. If a specific command is specified more than once as a value for the retrieval-set-hook a warning will be displayed and a value of **nil** will be returned as the current value.

:retrieved-chunk-hook

This parameter allows one to specify commands to be called automatically when chunks are retrieved or a failure to retrieve occurs. This parameter can be set with a command which takes one parameter and any number of such commands may be set (the reported value of this parameter is a list of all commands which have been set). When there is a retrieved-chunk event these commands will be called with the name of the chunk which has been retrieved, and when there is a retrieval-failure event these commands will be called with **nil** as the parameter. The returned values from these commands are ignored. If the parameter is set to **nil** then all commands are removed from the retrieved-chunk-hook list. A command should only be set once. If a specific command is specified more than once as a value for the retrieved-chunk-hook a warning will be displayed and a value of **nil** will be returned as the current value.

:rt

The retrieval threshold. This is the minimum activation a chunk must have to be able to be retrieved, τ , in the <u>retrieval failure time equation</u>. It can be set to any number and defaults to 0.0.

:sact

The save activation trace parameter controls whether or not the declarative module should save the details of the activation computation when it is computed during a retrieval request. If it is set to a non-nil value then all of the components of the activation calculations are saved and a trace like the

one displayed when using the :act parameter can be printed out after a run using the <u>print-activation-trace</u> and <u>print-chunk-activation-trace</u> commands. The default value is **nil**.

The parameter can be set to values like :act i.e. **t**, **medium**, **low**, or **nil**. The output of the print-activation-trace and print-chunk-activation-trace commands will use the specific setting of this parameter to display the requested amount of detail in the traces shown.

This parameter is depricated now because the history stream "retrieval-history" is the recommended way to record and access the activation history data.

:sim-hook

This parameter allows one to override the similarity calculation. If it is set to a function then that function will be passed two parameters. The first will be the slot contents of the request specification, the k from the <u>partial matching equation</u>, and the second will be the considered chunk's value for that slot. If the function returns a number that will be the M_{ki} value used for that term in the partial matching equation. If the function returns **nil** or a non-numeric value the default M_{ki} value will be used.

:sji-hook

This parameter allows one to override the <u>strength of association calculation</u>. If it is set to a function then that function will be passed two parameters. The first will be the chunk j from a slot in a buffer chunk and the second will be the considered chunk i. If the function returns a number that will be the S_{ji} value used in the equation of S_{ij} for the chunk i. If the function returns **nil** or a non-numeric value the default S_{ij} value will be used.

:spreading-hook

This parameter allows one to override the spreading activation calculation. If it is set to a function then that function will be passed one parameter which is the name of the chunk for which a spreading activation value is needed. If the function returns a number then that will be the S_i value used in the activation equation. If the function returns **nil** or a non-numeric value the default spreading activation calculation will be used.

:w-hook

This parameter allows one to override the default values for W in the strength of association

<u>calculation</u>. If it is set to a function then that function will be passed two parameters. The first will

be the name of the buffer, the *k*, and the second will be the name of a slot for which the source of

activation, the j, is being spread. If the function returns a number that will be the W_{ki} value used in

the equation of S_{i} at that time. If the function returns **nil** or a non-numeric value the default W_{ki} value

will be used.

Retrieval buffer

The retrieval buffer is used to retrieve chunks from the model's declarative memory using the

mechanisms described above.

Activation spread parameter: :retrieval-activation

Default value: 0.0

Queries

In addition to the default queries the retrieval buffer can be queried with recently-retrieved which can

be checked for the values of t or nil.

'State busy' will be **t** while a retrieval request is being processed – the time between the start-retrieval

event and either the retrieved-chunk or retrieval-failure event. It will be **nil** at all other times.

'State free' will be **nil** while a retrieval request is being processed – the time between the start-

retrieval event and either the retrieved-chunk or retrieval-failure event. It will be t at all other times.

'State error' will be t if no chunk matching the most recent request was found (a retrieval-failure

event has occurred) and **nil** otherwise. Once it becomes **t** it will not change back to **nil** until the next

retrieval request is made.

'Recently-retrieved t' will be **t** if there is a chunk in the retrieval buffer and there is a chunk in DM

from which that chunk was copied which is currently marked with a declarative finst. Otherwise this

query will be nil.

294

'Recently-retrieved nil' will be **t** if there is a chunk in the retrieval buffer and there is a chunk in DM from which that chunk was copied which is currently not marked with a declarative finst. Otherwise this query will be **nil**.

Requests

All

```
{{modifier} slot value}*
{:recently-retrieved [t | nil | reset]}
{:mp-value [ nil | temp-value]}
```

A request to the retrieval buffer is a description of a chunk which the declarative module will try to find in DM and place into the retrieval buffer. For the declarative module to consider a chunk in DM as a possible candidate it must have all of the slots specified with non-**nil** values and not have any slots specified with a value of **nil**.

There are two request parameters which can be used to modify how that request is handled. The recently-retrieved request parameter can be used to test the declarative finsts associated with the chunks in addition to the chunks' contents. If recently-retrieved is specified as **t** then the request will only match to chunks which have a finst set for them at the time of the request. If recently-retrieved is specified as **nil** then the request will only match to chunks which do not have a finst set for them at the time of the request, and if recently-retrieved is specified as **reset** then all of the declarative finsts are removed before the request is processed. The imp-value request parameter allows one to temporarily change the setting of the declarative module's imp parameter while this request is processed. That can only be used if the imp parameter has been enabled (set to a number) for the model, and the value provided can be anything that is valid for imp (a number or **nil**).

If a chunk which matches the request is found it will be placed into the retrieval buffer. If no chunk is found, or no chunk which matches has an activation which is above the retrieval threshold when the :esc parameter is **t**, then the buffer is left empty, the module signals that its state is error, and the retrieval buffer's failure flag is set.

The declarative module will only process one request at a time. If a new request comes in prior to the completion of a previous request the older request is terminated immediately – no chunk will be placed into the buffer or error signaled as a result of that request. A warning will be output to the

trace indicating the early termination of the previous request and the module will remain busy while processing the new request.

A successful request to the declarative module will generate the events start-retrieval, retrievedchunk, set-buffer-chunk like this:

```
0.050 DECLARATIVE START-RETRIEVAL
...
0.100 DECLARATIVE RETRIEVED-CHUNK C
0.100 DECLARATIVE SET-BUFFER-CHUNK RETRIEVAL C
```

A failed request will generate the events start-retrieval and retrieval-failure:

```
10.250 DECLARATIVE START-RETRIEVAL
...
10.300 DECLARATIVE RETRIEVAL-FAILURE
```

If a request is terminated prematurely by a new request this is the warning that will show in the trace:

```
10.350 DECLARATIVE START-RETRIEVAL ... #|Warning: A retrieval event has been aborted by a new request |#
```

History Stream

retrieval-history

The declarative module provides one data history stream called retrieval-history. When it is enabled it will record information about every retrieval request which is made. The data will be recorded based on the time of the retrieval request, and one optional parameter is available when requesting the data to get the history from a specific time (in milliseconds) instead of all the history data.

Each list of the data returned will have three elements. The first will be the time of the retrieval request in milliseconds. The second will be a string with the text of the request which was made. The third will be a list of lists where each sublist contains four strings describing either a chunk which matched the request or an indication of a retrieval failure. The first item in that list will be the description of the chunk that was retrieved if there was one retrieved, or it will be a list of the string ":retrieval-failure" followed by three empty lists if there was not a chunk retrieved. The remainder of the items in that list will be descriptions of the chunks which matched the request but were not selected (in no particular order). The four strings in a chunk description list are: the name of the

chunk, the print out of that chunk, all of the relevant chunk parameters at the time of the request, and the activation trace for that chunk at the time of the request.

There is also a processor for the retrieval-history called retrieval-times which can be used to get just the times of the requests and the names of the chunks which were matched at that time from the recorded retrieval history.

Commands

add-dm

Syntax:

```
add-dm [chunk-description* | chunk-name*] -> (chunk*)
add-dm-fct (chunk-description* | chunk-name*) -> (chunk*)
```

Remote command name:

```
add-dm ' [chunk-description* | chunk-name*] '
add-dm-fct ' (chunk-description* | chunk-name*) '
```

Arguments and Values:

```
chunk-description ::= ({chunk-name}{[doc-string isa chunk-type | isa chunk-type]} {slot value}*)
chunk-name ::= the name of the chunk to create
doc-string ::= a string that will be the documentation for the chunk
chunk-type ::= a name of a chunk-type in the model
slot ::= a name of a slot for the chunk
value ::= a value which will be the contents of the correspondingly named slot for this chunk
chunk ::= the name of a chunk that was created
```

Description:

The add-dm command functions exactly like the <u>define-chunks command</u> to create new chunks for the model. In addition, add-dm places those chunks into the current model's declarative memory. It returns a list of the names of the chunks that were created.

If the syntax is incorrect or any of the components are invalid for a list describing a chunk then a warning is displayed and no chunk is created for that chunk description, but any other valid chunks defined will still be created.

If there is no current model then a warning is displayed, no chunks are created and **nil** is returned.

Add-dm is typically used to provide the model with a set of initial memories. It should not be used for the creation of general chunks. In particular, it should not be used by other modules to create the chunks to place into their buffers because those chunks will be added to DM automatically when the buffer is cleared and should not be placed there prior to that.

Examples:

```
1> (chunk-type number value)
NUMBER
2> (add-dm (isa number value 1)
           (two value 2))
 (NUMBERO TWO)
3> (add-dm-fct (list '(three "the number 3" isa number value 3)
                     '(value 4)))
(THREE CHUNKO)
> (add-dm a b c)
(A B C)
E> (add-dm (bad-chunk isa invalid-type)
           (bad-slot 10))
#|Warning: Invalid chunk definition: (BAD-CHUNK ISA INVALID-TYPE) chunk-type specified
does not exist. |#
#|Warning: Extending chunks with slot named BAD-SLOT because of chunk definition (BAD-SLOT
10) |#
(CHUNK1)
E > (add-dm(a))
#|Warning: get-module called with no current model. |#
#|Warning: Could not create chunks because no declarative module was found |#
NIL
```

dm

Syntax:

```
dm chunk-name* -> (chunk-name*)
dm-fct (chunk-name*) -> (chunk-name*)
```

Remote command name:

dm

Arguments and Values:

chunk-name ::= a symbol which names a chunk

Description:

The dm command is used to print out chunks which are in the declarative memory of the current model. For each chunk name provided that chunk will be printed to the current model's command trace. If no chunk names are provided then all of the chunks in DM will be printed. A list of the names of the chunks which are printed will be returned.

If there is no current model then a warning is printed and **nil** is returned.

Examples:

This example assumes the count model from unit 1 of the tutorial has been loaded.

```
> (dm)
FIRST-GOAL
  START 2
  END 4
F
   FIRST 5
  SECOND 6
Ε
   FIRST 4
   SECOND 5
   FIRST 3
  SECOND 4
С
   FIRST 2
   SECOND 3
В
   FIRST 1
  SECOND 2
(FIRST-GOAL F E D C B)
> (dm b d)
   FIRST 1
  SECOND 2
D
   FIRST 3
  SECOND 4
(B D)
> (dm-fct '(first-goal c))
FIRST-GOAL
  START 2
   END 4
С
   FIRST 2
   SECOND 3
```

```
(FIRST-GOAL C)
E> (dm bad-name)
NIL
E> (dm)
#|Warning: get-module called with no current model. |#
#|Warning: No declarative memory module found |#
NIL
```

sdm

Syntax:

```
sdm {isa chunk-type} slot-test* -> (chunk-name*)
sdm-fct ( {isa chunk-type} slot-test* ) -> (chunk-name*)
```

Remote command name:

```
sdm ' {isa chunk-type} slot-test* '
```

Arguments and Values:

```
chunk-type ::= a chunk-type name
slot-test ::= {slot-modifier} slot value
slot-modifier ::= [=|-| <| >| <=| >=]
slot ::= a slot name
value ::= a value
chunk-name ::= the name of a chunk
```

Description:

The sdm command is used to search the declarative memory of the current model and print out chunks which match the search specification. If no parameters are provided then all chunks in DM are printed. If parameters are provided then all chunks from DM which match the specification provided are printed. If the chunk-type is specified then the slots given must be valid for that chunk-type otherwise a warning will be printed and no chunks returned. As is the case elsewhere, the chunk-type itself is not a constraint in the search, but if it contains default slot values those will be included in the specification unless other values are provided. If no chunk-type is provided then any slots may be provided. A list of the names of the chunks which are printed is returned.

If there is an error in the specification or there is no current model a warning is printed and **nil** is returned.

Examples:

```
1> (chunk-type test (slot1 t))
```

```
TEST
2> (add-dm (t1 isa test slot1 t) (t2 isa test slot1 nil))
(T1 T2)
3> (sdm isa test)
  SLOT1 T
(T1)
1> (chunk-type type1 slot1 slot2)
2> (chunk-type number name value)
NUMBER
3> (chunk-type type2 name slot1)
TYPE2
4> (add-dm (one isa chunk)
           (a isa type1 slot1 1 slot2 a)
           (b isa type1 slot1 2 slot2 a)
           (c isa number name one value 1)
           (d isa type2 name one slot1 3))
(ONE A B C D)
5> (sdm isa type1)
   NAME ONE
   SLOT1 3
С
   NAME ONE
   VALUE 1
   SL0T1 1
   SLOT2 A
   SLOT1 2
   SLOT2 A
ONE
(D C A B ONE)
6> (sdm name one)
   NAME ONE
   SLOT1 3
С
   NAME ONE
   VALUE 1
(D C)
7> (sdm-fct '(< slot1 2))
   SL0T1 1
   SLOT2 A
(A)
8> (sdm - slot2 a)
```

```
D
  NAME ONE
  SLOT1 3
С
  NAME ONE
   VALUE 1
ONE
(D C ONE)
E> (sdm isa bad-type)
#|Warning: Element after isa in define-chunk-spec isn't a chunk-type. (ISA BAD-TYPE) |#
#|Warning: Invalid chunk specification (ISA BAD-TYPE) passed to sdm |#
NIL
E> (sdm isa type1 value 3)
#|Warning: Invalid slot-name VALUE in call to define-chunk-spec. |#
#|Warning: Invalid chunk specification (ISA TYPE1 VALUE 3) passed to sdm |#
E> (sdm)
#|Warning: get-module called with no current model. |#
#|Warning: No declarative memory module found |#
```

print-dm-finsts

Syntax:

print-dm-finsts -> ((chunk-name time-stamp)*)

Remote command name:

print-dm-finsts

Arguments and Values:

```
chunk-name ::= the name of a chunk in DM
```

time-stamp ::= a number indicating the time the first was applied to the chunk chunk-name in seconds

Description:

Print-dm-finsts can be used to see which chunks in the DM of the current model have declarative finst markers. It takes no parameters and will print out a table of the chunks with finsts on them showing the time at which the finst was set in seconds. It returns a list of two element lists where each sublist has the name of a chunk with a finst on it as the first element and the creation time of its finst in seconds as the second element.

If there is no current model then a warning is printed and **nil** is returned.

Examples:

This example assumes that the count model from tutorial unit 1 has been loaded.

```
1> (print-dm-finsts)
Chunk name Time Stamp
------
NIL
> (run 10)
                                SET-BUFFER-CHUNK GOAL FIRST-GOAL NIL
    0.000
           GOAL
    0.300
                                Stopped because no events left to process
           -----
0.3
50
NIL
3> (print-dm-finsts)
Chunk name
          Time Stamp
-----
Ε
               0.300
D
               0.200
               0.100
((E 0.3) (D 0.2) (C 0.1))
E> (print-dm-finsts)
#|Warning: get-module called with no current model. |#
```

sdp

Syntax:

Remote command name:

Arguments and Values:

```
chunk-name ::= the name of a chunk in declarative memory
param-name ::= a keyword which names a declarative parameter
param-value-pair ::= param-name new-param-value
new-param-value ::= a value to which the preceding param-name is to be set
param-values ::= [(param-value*) | (chunk-name*) | :error]
param-value ::= the current value of a requested declarative parameter or :error.
```

Description:

Sdp is used to set or get the declarative parameters of the chunks in the current model. It is similar to the <u>sgp command</u> which is used to set and get module parameters.

Each chunk has several declarative parameters associated with it, and most of those are related to the computation of the activation equation. The declarative parameters are only relevant when the <u>:esc parameter</u> is enabled, and even then, some of the parameters are only available when specific options of the declarative module are also enabled.

The declarative parameters available through sdp are listed below. An important thing to note is that while these declarative parameters are maintained using general chunk parameters not all of the general chunk parameters are available through sdp. Only the chunk parameters which are relevant to the declarative module are accessible through the sdp command, and the mapping of declarative parameters onto chunk parameters may not be one-to-one. Thus, the declarative parameters should only be accessed through the sdp command and not be read or changed through the general chunk parameter accessors since their internal representations are not part of the declarative module's API.

- name := the name of the chunk. Cannot be changed.
- activation := the chunk's current activation value. Cannot be changed through sdp.
- permanent-noise := the permanent noise is a value which is added to the activation of the chunk each time it is computed. It defaults to 0.0. If :pas is set to a number, then when a chunk is initially added to DM a random noise value generated using the :pas value as the s parameter to act-r-noise will be generated and set as the chunk's permanent noise. It can be set by the modeler to any number, which will override the default and automatically generated values.
- base-level := the chunk's current base-level value. Cannot be changed directly through sdp when base-level learning is enabled because in that case it is controlled by the chunk's creation-time, reference-count, and/or reference-list. If base-level learning is disabled then it can be set to a number which will be the β_i value for the chunk.
- creation-time := the time (in seconds) when the chunk was first added to DM. Used by the base-level equations to determine the t_j values and the chunk's life time. Can be set to any time (including negative values) which is less than or equal to the current time. This is only applicable when :bll is set to a non-nil value.
- reference-count := the number of references which the chunk has received. Can be set to any positive value. It is applicable when :bll is non-**nil** and :ol is either **t** or a number. It is the n

value used in the optimized base-level equations. If the reference-count is set by the user then the reference-list for the chunk will be adjusted to contain an appropriate number of references as follows. If the reference-list is as long as the reference-count specified or :ol is **t** then the reference-list will be unchanged. If the reference-list is currently longer than the specified reference-count it will be truncated to that many of the most recent entries. If the reference-list is shorter than the specified reference-count but has as many items as the current setting of :ol it will be unchanged. Otherwise, the reference-list will be set to an evenly distributed set of references as would be done by the <u>set-base-levels command</u>.

- reference-list := the list of times at which the chunk's references have occurred (most recent first). Can be set to a list of times. It is applicable when :bll is non-nil and :ol is either nil or a number. If :ol is nil, then the list will contain all of the reference times of the chunk. If :ol is set to a number then it will only hold that many references (the most recent). If more references are provided than are needed, the list is truncated to the necessary length. When the reference-list is set by the user the reference-count may be adjusted automatically. If :ol is nil, then the reference-count will be updated to the length of the reference-list (even though the reference-count is not actually used when :ol is nil). If :ol is a number and the reference-count is less than the length of the (possibly truncated) reference-list it will be set to the length of the reference-list. Otherwise, the reference-count will be unchanged.
- references := This parameter is deprecated and should not be used, but is still available for compatibility with older models. This parameter will not be shown for a chunk and modelers should use reference-count and reference-list instead to get/set the relevant values.
- source := the chunk's current activation spread from the current buffer contents. Cannot be changed directly through sdp. Only applicable when the :mas parameter is set to a number.
- sjis := this reports the S_{ji} value for chunks j to the chunk i (where i is the chunk for which the value is being reported). The reported value is a list of two element lists where the first element is the name of a chunk j and the second is the S_{ji} between that chunk j and the chunk i. Only chunks j which have a connection with i are reported all other S_{ji} values to chunk i will be 0.0 (unless a provided :sji-hook overrides that). This parameter is only relevant when the :mas parameter is set to a number. It is possible to set this parameter using a list of two element lists. Each value specified is effectively added to the set of S_{ji} values for the chunk as if the <u>add-sji command</u> was called (possibly replacing a value which was previously set or overriding a default value). The add-sji command is the recommended way to set S_{ji} values instead of using this parameter through sdp.

- similarities := this reports the similarities (the M_{ki} values) between other chunks k and this chunk, i. The reported value is a list of two element lists where the first element of the list is the name of the chunk k and the second element is the similarity value M_{ki}. Only chunks k for which a similarity value has been set and the similarity of the chunk with itself are reported. All other M_{ki} values will be the maximum difference (the :md parameter setting). This parameter is only relevant when the :mp parameter is set to a number. It is possible to set this parameter using a list of two element lists. Each value specified is effectively added to the similarity values for the chunk (possibly replacing a value which was previously set or overriding a default value). The <u>set-similarities command</u> is the recommended means of setting similarities, but if one wants asymmetric similarities between chunks they must be set explicitly with sdp per chunk (set-similarities always sets the values symmetrically).
- last-retrieval-activation := the activation that the chunk had the last time that it was attempted to be retrieved. This value is computed during the start-retrieval event and will be updated for all chunks which match the retrieval request. Cannot be changed through sdp.
- last-retrieval-time := the time at which the last attempt to retrieve this chunk occurred i.e. the time at which the last-retrieval-activation value was set. Cannot be changed through sdp.

Note: because parameter settings are applied in the order provided and there are dependences between the creation-time, reference-count, and reference-list the order in which they are given may affect the resulting values. The ordering to achieve what is typically wanted would be to set creation-time, then reference-count, and then reference-list. That ensures that the creation-time has been updated before any automatic references are generated and that the specified reference-list is not overwritten by one automatically created by the reference-count. It is not required that they be provided in that order however, and one may use other orderings to achieve different resultant values as desired.

If no parameters are provided to sdp, then all of the current model's DM chunks' parameters are printed and a list of all the chunk names is returned.

If a chunk or list of chunks is specified as the first parameter to sdp then the following parameters are set or retrieved from only those chunks. If no chunk names are provided then the settings are applied to or retrieved from all chunks in DM at the time of the call to sdp.

If chunk names are specified but no specific parameters are specified then the parameters for those chunks are printed and the list of those chunk names is returned.

When sdp prints the parameters for a chunk its name is printed followed by the parameters which are currently appropriate based on the declarative module's parameter settings to the command output stream.

If any of the chunk names provided are invalid a warning will be printed and the corresponding element of the return list will be **:error**.

If all of the parameters passed to sdp (after any chunk names) are keywords, then it is a request for the current values of the parameters named. Those parameters are printed for the chunks specified and a list containing a list for each chunk specified is returned. Each sub-list contains the values of the parameters requested in the order requested and the sub-lists are in the order of the chunks which were requested. If an invalid parameter is requested, then a warning is printed and the value returned in that position will be the keyword **:error**.

If there are any non-keyword parameters in the call to sdp and the number of parameters (not counting the chunk names) is even, then they are assumed to be pairs of a parameter name and a parameter value. For all of the specified chunks (or all chunks in DM if none are specified) those parameters will be set to the provided values. The return value will be a list containing a list for each chunk specified. Each sub-list contains the values of the parameters set in the order they were set and the sub-lists are in the order of the chunks which were specified. If a particular parameter value was not of the appropriate type, then a warning is printed and the value returned in that position will be the keyword **:error**.

It is also possible to pass lists of a chunk name and parameter settings to sdp. Essentially, each list provided could be formatted as something that could be passed to sdp and they will each be processed as appropriate.

If there is no current model at the time of the call, then a warning is displayed and **nil** is returned.

There is one small issue worth noting about using sdp. If the :activation or :base-level value is returned (either because it is explicitly specified or because no parameters were specified and thus it gets returned automatically) that will cause the chunk's activation to be recomputed at the current time if it is not currently at the time of the chunk's last retrieval attempt (the value of the :last-retrieval-time parameter). That activation computation will include the activation noise if there is any. There are two consequences of that. First, multiple calls to sdp will likely return different :activation values for a given chunk, even if those calls occur at the same model time. The other

consequence is that if there is noise in the activations then if sdp has to recomputed the chunk activations it will affect the random sequence which will likely change how a model with a set <u>seed</u> <u>parameter</u> runs from that point on relative to how it would have run had sdp not been called.

Examples:

The examples assume that this model has been defined:

```
(define-model test
  (sgp :esc t :bll .5 :mas 2 :mp 1)
  (chunk-type test slot1 slot2)
  (add-dm (a isa test)
         (b isa test slot1 a slot2 c)
          (c isa test slot1 a slot2 c)
          (d isa test slot2 b)))
1> (sdp)
Declarative parameters for chunk D:
 :Activation 2.191
 :Permanent-Noise 0.000
 :Base-Level 2.191
 :Creation-Time 0.000
 :Reference-Count 1
 :Source-Spread 0.000
 :Sjis ((D 2.0) (B 1.3068528))
 :Similarities ((D 0.0))
Declarative parameters for chunk C:
 :Activation 2.191
 :Permanent-Noise 0.000
 :Base-Level 2.191
 :Creation-Time 0.000
 :Reference-Count 1
 :Source-Spread 0.000
 :Sjis ((A 0.9013877) (C 1.5945349))
 :Similarities ((C 0.0))
Declarative parameters for chunk B:
 :Activation 2.191
 :Permanent-Noise 0.000
 :Base-Level 2.191
 :Creation-Time 0.000
 :Reference-Count 1
 :Source-Spread 0.000
 :Sjis ((B 1.3068528) (A 0.9013877) (C 0.9013877))
 :Similarities ((B 0.0))
Declarative parameters for chunk A:
 :Activation 2.191
 :Permanent-Noise 0.000
 :Base-Level 2.191
 :Creation-Time 0.000
 :Reference-Count 1
 :Source-Spread 0.000
 :Sjis ((A 0.9013877))
 :Similarities ((A 0.0))
(DCBA)
2> (sdp a :permanent-noise)
Declarative parameters for chunk A:
 :PERMANENT-NOISE 0.000
((0.0))
3> (sdp a :permanent-noise .3)
((0.3))
```

```
4> (sdp a)
Declarative parameters for chunk A:
 :Activation 2.491
 :Permanent-Noise 0.300
 :Base-Level 2.191
 :Creation-Time 0.000
 :Reference-Count 1
 :Source-Spread 0.000
 :Sjis ((A 0.9013877))
:Similarities ((A 0.0))
(A)
5> (sdp (a b) :name :activation)
Declarative parameters for chunk A:
 :NAME A
 :ACTIVATION 2.491
Declarative parameters for chunk B:
 :NAME B
 :ACTIVATION 2.191
((A 2.4910133) (B 2.1910133))
6> (sdp-fct '(c))
Declarative parameters for chunk C:
 :Activation 2.191
 :Permanent-Noise 0.000
 :Base-Level 2.191
 :Creation-Time 0.000
 :Reference-Count 1
 :Source-Spread 0.000
 :Sjis ((A 0.9013877) (C 1.5945349))
 :Similarities ((C 0.0))
(C)
7> (sdp-fct '((d b) :sjis))
Declarative parameters for chunk D:
:SJIS ((D 2.0) (B 1.3068528))
Declarative parameters for chunk B:
:SJIS ((B 1.3068528) (A 0.9013877) (C 0.9013877))
((((D 2.0) (B 1.3068528))) (((B 1.3068528) (A 0.9013877) (C 0.9013877))))
8> (sdp (a :base-level) (b :creation-time -1.0))
Declarative parameters for chunk A:
 :BASE-LEVEL 2.191
((2.1910133)(-1.0))
9> (sdp b)
Declarative parameters for chunk B:
 :Activation 0.693
 :Permanent-Noise 0.000
 :Base-Level 0.693
 :Creation-Time -1.000
 :Reference-Count 1
 :Source-Spread 0.000
 :Sjis ((B 1.3068528) (A 0.9013877) (C 0.9013877))
 :Similarities ((B 0.0))
(B)
10> (sdp-fct '(:reference-count 3))
((3)(3)(3)(3))
11> (sdp-fct '((a b)))
Declarative parameters for chunk A:
 :Activation 3.590
 :Permanent-Noise 0.300
 :Base-Level 3.290
 :Creation-Time 0.000
```

```
:Reference-Count 3
 :Source-Spread 0.000
 :Sjis ((A 0.9013877))
 :Similarities ((A 0.0))
Declarative parameters for chunk B:
 :Activation 1.792
 :Permanent-Noise 0.000
 :Base-Level 1.792
 :Creation-Time -1.000
 :Reference-Count 3
 :Source-Spread 0.000
 :Sjis ((B 1.3068528) (A 0.9013877) (C 0.9013877))
 :Similarities ((B 0.0))
(A B)
E> (sdp bad-chunk)
#|Warning: BAD-CHUNK does not name a chunk in DM. |#
(:ERROR)
E> (sdp a :bad-parameter)
Declarative parameters for chunk A:
#|Warning: BAD-PARAMETER is not a declarative parameter for chunks. |#
((:ERROR))
E> (sdp)
#|Warning: get-module called with no current model. |#
#|Warning: No declarative memory module found |#
```

sji/add-sji

Syntax:

```
sji chunk-name-j chunk-name-i -> [ sji | nil ]
sji-fct chunk-name-j chunk-name-i -> [ sji | nil ]
add-sji (chunk-name-j chunk-name-i sji)* -> ([sji | :error]*)
add-sji-fct ((chunk-name-j chunk-name-i sji)*) -> ([sji | :error]*)
```

Remote command name:

```
sji
sji-fct
add-sji
add-sji-fct
```

Arguments and Values:

```
chunk-name-j ::= the name of a chunk chunk-name-i ::= the name of a chunk sji ::= a number which is the associative strength (S_{ji} value) from chunk-name-j to chunk-name-i
```

Description:

The sji command is used to get the S_{ji} value between two chunks in the current model. It takes two parameters which are the names of the chunk j and the chunk i respectively, and it returns the S_{ji} value between them. The S_{ji} value will be either the value determined by the <u>standard equation</u>, the

explicit value which has been set using the add-sji command, or the result returned by the $\underline{sji\text{-hook}}$ if it is specified. The sji-hook function overrides an explicit setting and the default calculation, and an explicitly set value will override the default calculation. If either of the chunk names is invalid then a warning is printed and an S_{ji} of 0.0 is returned. If there is no current model then a warning is printed and nil is returned.

The add-sji command is used to specify explicit S_{ji} values between chunks. It can be used to set any number of S_{ji} values at a time. Each parameter to add-sji (or element of the list passed to add-sji-fct) should be a list of three items. Those items are the chunk j, the chunk i, and the S_{ji} value between them respectively. It applies the S_{ji} values in order left to right. Thus, if any pair of items is specified more than once it will be the right most setting for the pair that will be their S_{ji} . It returns a list of the S_{ji} values set in the order they were specified. If any of the lists are not three elements long, have bad chunk names, or an invalid S_{ji} value then that item is ignored for purposes of setting an S_{ji} , a warning is printed, and the corresponding element of the return list will be **:error**.

Examples:

The example assumes this initial model is defined.

```
(define-model sji-demo
   (sgp :esc t :mas 2)
   (chunk-type item slot)
   (add-dm (a isa item slot nil)
           (b isa item slot a)
           (c isa item slot d)
           (d isa item slot c)
           (e isa item slot c)
           (f isa item slot f)
           (g isa item slot f)))
> (sji a b)
1.3068528
> (sji b a)
0.0
> (sji c d)
0.9013877
> (sji d c)
1.3068528
> (sji-fct 'a 'a)
1.3068528
> (sji-fct 'f 'f)
1.5945349
E> (sji-fct 'bad-name 'a)
#|Warning: BAD-NAME does not name a chunk in the current model. |#
E> (sji a a)
```

```
#|Warning: get-module called with no current model. |#
#|Warning: No declarative memory module found |#
NIL
1> (add-sji (a b 2.5) (b a 10))
(2.5 10)
2> (sji a b)
2.5
3> (sji b a)
4> (add-sji-fct '((f f 1) (d c 0)))
(1 \ 0)
5> (sji f f)
6> (sji d c)
7> (add-sji (c d 1.0) (c d 2.0))
(1.0 2.0)
8> (sji c d)
2.0
E> (add-sji a b 1.0)
#|Warning: Bad Sji setting in A |#
#|Warning: Bad Sji setting in B |#
#|Warning: Bad Sji setting in 1.0 |#
(:ERROR :ERROR)
E> (add-sji (a bad 1.0))
#|Warning: Bad Sji setting in (A BAD 1.0) |#
(:ERROR)
E> (add-sji-fct '(a b 2))
#|Warning: Bad Sji setting in A |#
#|Warning: Bad Sji setting in B |#
#|Warning: Bad Sji setting in 2 |#
(:ERROR :ERROR)
E> (add-sji (a a 1))
#|Warning: get-chunk called with no current model. |#
#|Warning: Bad Sji setting in (A A 1) |#
(:ERROR)
```

similarity/set-similarities

Syntax:

```
similarity item1 item2 -> [ sim | nil ]
similarity-fct item1 item2-> [ sim | nil ]
set-similarities (chunk-name-k chunk-name-i sim)* -> ([sim | :error]*)
set-similarities-fct ((chunk-name-k chunk-name-i sim)*) -> ([sim | :error]*)
```

Remote command name:

similarity ' item1 item2 '

```
similarity-fct ' item1 item2 '
set-similarities ' (chunk-name-k chunk-name-i sim)* '
set-similarities-fct ' ((chunk-name-k chunk-name-i sim)*) '
```

Arguments and Values:

item1 ::= any value
item2 ::= any value

chunk-name-k ::= the name of a chunk chunk-name-i ::= the name of a chunk

sim ::= a number which is the similarity between the specified items

Description:

The similarity command is used to get the similarity value between two items in the current model (the items do not have to be chunks). It takes two parameters which are the items, and it returns the similarity value between them (the M_{ki} from the partial matching equation). The value will be determined either by the <u>default calculation</u>, explicit user settings, or <u>the hook function</u>. The simhook function overrides an explicit setting and the default calculation, and an explicitly set value will override the default calculation. If there is no current model then a warning is printed and **nil** is returned.

The set-similarities command is used to specify explicit similarity values between chunks (to use values other than the defaults between non-chunk items one must use the hook function). It can be used to set any number of similarity values at a time. Each parameter to set-similarities (or element of the list passed to set-similarities-fct) should be a list of three items. Those items are the chunk k, the chunk i, and the similarity value between them respectively. It applies the similarity values in order left to right. Thus, if any pair of items is specified more than once it will be the right most setting for the pair that will be their similarity. Note that similarities are set reciprocally with this command, and thus setting the similarity for k,i also sets the same similarity for i,k. It returns a list of the similarity values set in the order they were specified. If any of the lists are not three elements long, have bad chunk names, or an invalid similarity value then that item is ignored for purposes of setting a similarity, a warning is printed, and the corresponding element of the return list will be :error. If there is no current model then a warning will be printed and all elements in the list will be :error.

Examples:

This example assumes that this initial model is defined.

```
(define-model sim-demo
   (sgp :esc t :mp 1)
```

```
(add-dm (a isa chunk)
           (b isa chunk)
           (c isa chunk)))
1> (sgp :ms :md)
:MS 0.0 (default 0.0) : Maximum Similarity
:MD -1.0 (default -1.0) : Maximum Difference
(0.0 - 1.0)
2> (similarity a b)
-1.0
3> (similarity a a)
4> (similarity-fct 'a 'c)
-1.0
5> (similarity-fct "STRING" "string")
6> (similarity-fct "STRING" 'string)
-1.0
7> (similarity-fct 1.5 1.5)
0.0
E> (similarity a b)
#|Warning: get-module called with no current model. |#
#|Warning: No declarative memory module found |#
NIL
1> (set-similarities (a b -.5) (b c -2))
(-0.5 - 2)
2> (similarity a b)
-0.5
3> (similarity b a)
-0.5
4> (similarity b c)
5 > (set-similarities-fct '((a a .5) (a c -1) (a c -2)))
(0.5 - 1 - 2)
6> (similarity a c)
7> (similarity a a)
0.5
E> (set-similarities a b .5)
#|Warning: Bad similarity setting in A |#
#|Warning: Bad similarity setting in B |#
#|Warning: Bad similarity setting in 0.5 |#
(:ERROR :ERROR)
E> (set-similarities (d e .5))
#|Warning: Bad similarity setting in (D E 0.5) |#
(:ERROR)
E> (set-similarities (a b 1) (a d 1) (b c 1))
#|Warning: Bad similarity setting in (A D 1) |#
(1 :ERROR 1)
```

```
E> (set-similarities (a a 1))
#|Warning: get-chunk called with no current model. |#
#|Warning: Bad similarity setting in (A A 1) |#
(:ERROR)
```

get-base-level/set-base-levels/set-all-base-levels

Syntax:

```
get-base-level {chunk-name*} -> ([base-level | :error ]*) get-base-level-fct (chunk-name*) -> ([base-level | :error ]*) set-base-levels (chunk-name level {creation-time})* -> ([base-level | :error ]*) set-base-levels-fct ((chunk-name level {creation-time})*) -> ([base-level | :error ]*) set-all-base-levels level {creation-time} -> [t | nil]
```

Remote command name:

get-base-level get-base-level-fct set-base-levels set-base-levels-fct set-all-base-levels

Arguments and Values:

```
chunk-name ::= the name of a chunk
base-level ::= a number representing the base-level activation of a chunk
level ::= a number which is the setting for the base-level of chunk-name or all chunks in DM
creation-time ::= a number which represents the time at which chunk-name was added to DM
```

Description:

Get-base-level will return a list of the current base-level activations in the current model for the chunks provided in the same order as they are given. This will result in the base-level being recomputed for those chunks. If a chunk-name given does not name a chunk which is in DM of the current model then the corresponding base-level value will be **:error**. If there is no current model then a warning is printed and **nil** is returned.

Set-base-levels is used to set the base-level activation for chunks in DM of the current model. For each chunk specified, its base-level is set as described below and if a new creation time is specified that is also set for the chunk. The list of current base-level activations is returned for the chunks specified in the same order as they were given. If a chunk-name is invalid, the level is not a number, or the creation time is specified and is not a number then a warning is printed, no change is made to the chunk's parameters and the corresponding base-level returned will be **:error**.

The setting of the chunk's base-level depends on the settings of the <u>:bll</u> and <u>:ol</u> parameters. If :bll is **nil** then the level provided is used directly as the chunk's base-level. If :bll is non-**nil** then the setting of the :ol parameter determines how the level is used. If :ol is **t** then the level is the number of references for the chunk (n in the <u>optimized learning equation</u>). If :ol is **nil** then the level specifies how many references the chunk has and a history of the chunk is generated which evenly spaces those references between the current time and the chunk's creation time (which will be the new value if provided). If :ol is a number, then the level specifies the number of references for the chunk (the n in the hybrid optimized equation) and a history list is generated which evenly spaces either the value of :ol or level (whichever is lesser) references between the current time and the chunk's creation-time.

The set-all-base-levels command works like the set-base-levels command except that it applies the level and creation-time (if provided) to all chunks in DM of the current model at the time it is called. If it was successful it returns **t**. If there was a problem then a warning is printed and **nil** is returned.

Examples:

```
1> (define-model test-base-levels
       (sgp :esc t :bll nil)
       (add-dm (a isa chunk)
               (b isa chunk)
               (c isa chunk)))
TEST-BASE-LEVELS
2> (get-base-level a b)
(0.0\ 0.0)
3> (set-all-base-levels 1.5)
4> (set-base-levels (c -1))
(-1)
5> (get-base-level a b c)
(1.5 \ 1.5 \ -1)
1> (define-model test-base-levels-2
      (sgp : esc t : bll .5 : ol t)
      (add-dm (a isa chunk)
              (b isa chunk)
              (c isa chunk)))
TEST-BASE-LEVELS-2
2> (get-base-level-fct '(a b c))
(2.1910133 2.1910133 2.1910133)
3> (set-all-base-levels 4 -1)
4> (sdp)
Declarative parameters for chunk C:
 :Activation 2.079
```

```
:Permanent-Noise 0.000
 :Base-Level 2.079
 :Reference-Count 4.000
 :Creation-Time -1.000
Declarative parameters for chunk B:
 :Activation 2.079
 :Permanent-Noise 0.000
 :Base-Level 2.079
 :Reference-Count 4.000
 :Creation-Time -1.000
Declarative parameters for chunk A:
 :Activation 2.079
 :Permanent-Noise 0.000
 :Base-Level 2.079
 :Reference-Count 4.000
 :Creation-Time -1.000
(C B A)
5> (set-base-levels-fct '((a 2 -10)))
(0.2350018)
6>(get-base-level-fct '(a b))
(0.2350018 2.0794415)
E> (get-base-level bad-name)
(:ERROR)
E> (set-all-base-levels :not-a-number)
#|Warning: Invalid level :NOT-A-NUMBER |#
E> (set-all-base-levels 1.5 :not-a-number)
#|Warning: Invalid creation-time :NOT-A-NUMBER |#
E> (set-base-levels (a))
#|Warning: Invalid level in setting (A) |#
(:ERROR)
E> (set-base-levels (a 1.5) (:not-a-chunk 1.5))
#|Warning: :NOT-A-CHUNK does not name a chunk in DM. |#
(1.5 : ERROR)
E> (get-base-level a)
#|Warning: get-module called with no current model. |#
#|Warning: No declarative memory module found |#
NIL
E> (set-base-levels (b 3))
#|Warning: get-module called with no current model. |#
#|Warning: No declarative memory module found |#
NIL
E> (set-all-base-levels 10)
#|Warning: get-module called with no current model. |#
#|Warning: No declarative memory module found |#
NIL
clear-dm
```

Syntax:

```
clear-dm -> [ t | nil ]
```

Remote command name:

clear-dm

Arguments and Values:

Description:

The clear-dm command can be used to remove all chunks from the declarative memory of the current model. It is not recommended for general use, but there may be rare situations where it would be needed. The command returns **t** if the current model's DM was cleared and **nil** if there was no current model or some other problem was encountered. It will always print a warning that states either that all chunks were cleared or that a problem occurred.

Examples:

```
> (clear-dm)
#|Warning: All the chunks cleared from DM. |#
T

E> (clear-dm)
#|Warning: get-module called with no current model. |#
#|Warning: No declarative memory module found |#
NIL
```

reset-declarative-finsts

Syntax:

reset-declarative-finsts -> nil

Remote command name:

reset-declarative-finsts

Arguments and Values:

Description:

The reset-declarative-finsts command can be used to remove all of the finst markers from the declarative module of the current model. It takes no parameters and always returns **nil**. If there is no current model then it will print a warning.

This command is not recommended for typical modeling use because the ":recently-retrieved reset" request parameter setting can be used in a request to accomplish the same thing in a more model-

driven manner. However, sometimes it may be necessary or more convenient to do that through the code accompanying the model.

Examples:

```
> (reset-declarative-finsts)
NIL
E> (reset-declarative-finsts)
#|Warning: get-module called with no current model. |#
#|Warning: No declarative module found - cannot reset the finsts. |#
NTI
```

merge-dm

Arguments and Values:

```
merge-dm [chunk-description* | chunk-name*] -> (chunk*)
merge-dm-fct (chunk-description* | chunk-name*) -> (chunk*)
```

Remote command name:

```
merge-dm ' [chunk-description* | chunk-name*] '
merge-dm-fct ' (chunk-description* | chunk-name*) '
```

Arguments and Values:

```
chunk-description ::= ({chunk-name}{[doc-string isa chunk-type | isa chunk-type]} {slot value}*)
chunk-name ::= the name of the chunk to create
doc-string ::= a string that will be the documentation for the chunk
chunk-type ::= a name of a chunk-type in the model
slot ::= a name of a slot for the chunk
value ::= a value which will be the contents of the correspondingly named slot for this chunk
chunk ::= the name of a chunk that was created
```

Description:

The merge-dm command functions exactly like the <u>add-dm command</u> to create new chunks for the model. However, unlike add-dm merge-dm will merge those chunks into the current model's declarative memory in the same way they would be merged if they had been cleared from a buffer. Thus, if any of the chunks created by merge-dm are equal using the <u>chunk-equal</u> test with a chunk already in declarative memory that existing declarative memory chunk is strengthened with a new reference at the current time and those two chunks are merged. If a chunk created by merge-dm is not equal to an existing chunk in the current model's declarative memory then that new chunk is added to declarative memory as if it had been created using add-dm.

If there are dependencies among the chunks created with merge-dm then those chunks will be merged into declarative memory in an order that allows for proper merging of all chunks if such an order exists. If there are dependencies and no safe order exists a warning will be displayed to indicate that and the chunks will be merged into declarative memory in the order that they are provided. Merge-dm returns a list of the names of the chunks that were created in the order in which they were merged into declarative memory (first chunk returned was the first merged).

If the syntax is incorrect or any of the components are an invalid list describing a chunk then a warning is displayed and no chunk is created for that chunk description, but all valid chunks defined will still be created.

If there is no current model or no chunks are created and **nil** is returned.

Examples:

These examples assume that base-level learning is enabled so that there is a strengthening of activations when additional references to a chunk occur.

```
1> (chunk-type node slot1 slot2)
NODE
2> (add-dm (a slot1 b slot2 c)
           (b slot1 10)
           (c slot2 20))
(A B C)
3> (sdp)
Declarative parameters for chunk C:
 :Activation 2.191
 :Permanent-Noise 0.000
 :Base-Level 2.191
 :Reference-Count 1.000
 :Creation-Time 0.000
Declarative parameters for chunk B:
 :Activation 2.191
 :Permanent-Noise 0.000
 :Base-Level 2.191
 :Reference-Count 1.000
 :Creation-Time 0.000
Declarative parameters for chunk A:
 :Activation 2.191
 :Permanent-Noise 0.000
 :Base-Level 2.191
 :Reference-Count 1.000
 :Creation-Time 0.000
(C B A)
4> (merge-dm (d slot1 e slot2 f)
             (e slot1 10)
             (f slot2 20)
             (x slot1 30))
(E F D X)
5> (sdp)
Declarative parameters for chunk C:
```

```
:Activation 2.884
 :Permanent-Noise 0.000
 :Base-Level 2.884
 :Reference-Count 2.000
 :Creation-Time 0.000
Declarative parameters for chunk X:
 :Activation 2.191
 :Permanent-Noise 0.000
 :Base-Level 2.191
 :Reference-Count 1.000
 :Creation-Time 0.000
Declarative parameters for chunk B:
 :Activation 2.884
 :Permanent-Noise 0.000
 :Base-Level 2.884
 :Reference-Count 2.000
 :Creation-Time 0.000
Declarative parameters for chunk A:
 :Activation 2.884
 :Permanent-Noise 0.000
 :Base-Level 2.884
 :Reference-Count 2.000
 :Creation-Time 0.000
(C X B A)
6> (merge-dm-fct '((y)))
(Y)
7E> (merge-dm (g slot1 h)
                        (h slot2 g))
#|Warning: Chunks in call to merge-dm have circular references. |#
#|Warning: Because of that there is no safe order for merging and they will be merged in
the order provided. |#
(G H)
E> (merge-dm (isa bad-type-name))
#|Warning: Invalid chunk definition: (ISA BAD-TYPE-NAME) chunk-type specified does not
exist. |#
NIL
E> (merge-dm (a))
#|Warning: get-module called with no current model. |#
#|Warning: Could not create chunks because no declarative module was found |#
NIL
```

print-activation-trace

Syntax:

print-activation-trace time {time-in-ms} -> nil

Remote command name:

print-activation-trace

Arguments and Values:

time ::= a number which is the time of a start-retrieval event time-in-ms ::= a generalized boolean indicating the units for time

Description:

The print-activation-trace command works in conjunction with the <u>retrieval-history</u> to allow one to print the activation trace information for retrieval requests that occurred during a model run after the model has stopped. If the retrieval-history stream is being recorded, then this command will print out the activation trace for the retrieval request which started at the time provided, measured in milliseconds if the time-in-ms parameter is true or not provided or seconds if the time-in-ms parameter is specified as **nil**, from the current model as it would have appeared in the model trace if the <u>:act_parameter</u> had been set, except that this trace information will be printed to the command trace instead of the model trace. If the history is not being recorded, the time provided does not correspond to the time of a start-retrieval event, or there is no current model then a warning will be printed instead of an activation trace.

Examples:

These examples assume that the fan experiment and model from unit 5 of the ACT-R tutorial have been loaded.

```
1> (record-history "retrieval-history")
2> (fan-sentence "hippie" "park" t 'person)
                                    Stopped because no events left to process
(1.354 T)
3> (print-activation-trace 485)
Chunk PARK matches
Chunk IN does not match
Chunk STORE does not match
Chunk LAWYER does not match
Chunk FIREMAN does not match
Chunk BANK does not match
Chunk DEBUTANTE does not match
Chunk CAVE does not match
Chunk CAPTAIN does not match
Chunk CHURCH does not match
Chunk HIPPIE does not match
Chunk GIANT does not match
Chunk FOREST does not match
Chunk EARL does not match
Chunk DUNGEON does not match
Chunk CASTLE does not match
Chunk BEACH does not match
Chunk GUARD does not match
Computing activation for chunk PARK
Computing base-level
User provided chunk base-level: 10.0
Total base-level: 10.0
Computing activation spreading from buffers
 Spreading 1.0 from buffer IMAGINAL chunk CHUNKO-0
    sources of activation are: (HIPPIE)
```

```
Spreading activation 0.0 from source HIPPIE level 1.0 times Sji 0.0
Total spreading activation: 0.0
Adding transient noise 0.0
Adding permanent noise 0.0
Chunk PARK has an activation of: 10.0
Chunk PARK with activation 10.0 is the best
4> (print-activation-trace 0.235 nil)
Chunk HIPPIE matches
Chunk IN does not match
Chunk STORE does not match
Chunk LAWYER does not match
Chunk FIREMAN does not match
Chunk BANK does not match
Chunk DEBUTANTE does not match
Chunk CAVE does not match
Chunk CAPTAIN does not match
Chunk CHURCH does not match
Chunk PARK does not match
Chunk GIANT does not match
Chunk FOREST does not match
Chunk EARL does not match
Chunk DUNGEON does not match
Chunk CASTLE does not match
Chunk BEACH does not match
Chunk GUARD does not match
Computing activation for chunk HIPPIE
Computing base-level
User provided chunk base-level: 10.0
Total base-level: 10.0
Computing activation spreading from buffers
Total spreading activation: 0.0
Adding transient noise 0.0
Adding permanent noise 0.0
Chunk HIPPIE has an activation of: 10.0
Chunk HIPPIE with activation 10.0 is the best
NIL
5E> (print-activation-trace 0.050)
#|Warning: No activation trace information available for time 0.05 |#
NİL
E> (print-activation-trace 0.0)
#|Warning: get-module called with no current model. |#
#|Warning: No declarative module available for reporting activation trace. |#
NIL
```

print-chunk-activation-trace

Syntax:

Remote command name:

print-chunk-activation-trace

Arguments and Values:

chunk-name ::= the name of a chunk in the model's declarative memory

time ::= a number which is the time of a start-retrieval event

time-in-ms ::= a generalized boolean indicating the units for time

total ::= a number which is the total activation the chunk had for the retrieval

 $\verb|base-leve| ::= a number which is the total value of the base-level component of the chunk's activation$

spreading ::= a number which is the total spreading activation component of the chunk's activation or **nil** if spreading activation is not enabled

similarity ::= a number which is the total partial matching component of the chunk's activation or **nil** if partial matching is not enabled

noise ::= a number which is the total amount of noise added to the chunk's activation

Description:

The print-chunk-activation-trace command works in conjunction with the <u>:sact parameter</u> to allow one to print the activation trace information for the retrieval requests that occurred during a model run after the model has stopped. If the :sact parameter is non-nil, then this command will print out the activation trace for the specified chunk at the time provided, measured in milliseconds if the time-in-ms parameter is true or seconds if it is nil or not specified, from the current model in the current meta-process similar to how it would have appeared in the model trace if the <u>:act parameter</u> had been set, except that this trace information will be printed to the command output instead of the model output. If the :sact parameter is nil, the time provided does not correspond to the time of a start-retrieval event, or there is no current model or meta-process then a warning will be printed instead of an activation trace. If the provided chunk-name doesn't name a chunk or wasn't an element in declarative memory then the output will indicate it doesn't have any activation information to display.

If there was chunk activation information displayed then this command will return five values. The first value will be the total activation for the chunk. The remaining four values are the primary components of that activation value: base-level activation, spreading activation, partial matching penalty, and noise. The spreading activation and partial matching penalty values will be **nil** if the corresponding mechanism is not enabled for the model. If there is no chunk activation information displayed then the return value of the command is **nil**.

Examples:

These examples assume that the fan experiment and model from unit 5 of the ACT-R tutorial has been loaded.

```
1> (record-history "retrieval-history")
2> (fan-sentence "hippie" "park" t 'person)
    1.444
             -----
                                    Stopped because no events left to process
(1.354 T)
3> (print-chunk-activation-trace park 485)
Computing activation for chunk PARK
Computing base-level
User provided chunk base-level: 10.0
Total base-level: 10.0
Computing activation spreading from buffers
  Spreading 1.0 from buffer IMAGINAL chunk CHUNKO-0
    sources of activation are: (HIPPIE)
    Spreading activation 0.0 from source HIPPIE level 1.0 times Sji 0.0
Total spreading activation: 0.0
Adding transient noise 0.0
Adding permanent noise 0.0
Chunk PARK has an activation of: 10.0
10
0.0
NTI
0.0
4> (print-chunk-activation-trace-fct 'p1 .585 nil)
Computing activation for chunk P1
Computing base-level
Starting with blc: 0.0
Total base-level: 0.0
Computing activation spreading from buffers
 Spreading 1.0 from buffer IMAGINAL chunk CHUNKO-0
    sources of activation are: (PARK HIPPIE)
    Spreading activation 0.10685283 from source PARK level 0.5 times Sji 0.21370566
    Spreading activation 0.10685283 from source HIPPIE level 0.5 times Sji 0.21370566
Total spreading activation: 0.21370566
Adding transient noise 0.0
Adding permanent noise 0.0
Chunk P1 has an activation of: 0.21370566
0.21370566
0.0
0.21370566
NIL
0.0
5> (print-chunk-activation-trace-fct 'p5 0.585 nil)
Chunk P5 did not match the request.
NIL
6> (print-chunk-activation-trace-fct 'park 0.585 nil)
Chunk PARK was not considered.
NIL
7E> (print-chunk-activation-trace park 0.0)
#|Warning: No activation trace information available for time 0.0 |#
NIL
E> (print-chunk-activation-trace chunk 0.0)
#|Warning: get-module called with no current model. |#
#|Warning: No declarative module available for reporting activation trace. |#
NIL
```

saved-activation-history

Syntax:

saved-activation-history -> (activation-history*)

Remote command name:

saved-activation-history

Arguments and Values:

```
activation-history ::= (time chunk-name*)
time ::= a number which is the time of a retrieval request for which a history has been saved
chunk-name ::= the name of a chunk for which activation information was stored at time
```

Description:

The saved-activation-history command returns a list which indicates what retrieval information has been saved in the retrieval-history stream from the current model. The same information is available from the retrieval-times processor for the retrieval-history and that is recommended over this command, but this command may be more convenient since it does not return the data as a JSON string. This command will return a list of lists where each sub-list consists of a time in milliseconds and the chunks which were attempted to be retrieved at that time for which the activation information has been recorded. There will be a separate sub-list for each time for which activation details are recorded and those lists will be in order based on the times (lowest time first). If there is no retrieval history recorded or no current model then a warning will be printed and the return value will be **nil**.

Examples:

This example assume that the fan experiment and model from unit 5 of the ACT-R tutorial has been loaded.

```
E> (saved-activation-history)
#|Warning: get-module called with no current model. |#
#|Warning: No declarative module available for reporting activation trace. |#
NTI
```

whynot-dm

Syntax:

```
whynot-dm chunk-name* -> (matching-chunk*) whynot-dm-fct (chunk-name*) -> (matching-chunk*)
```

Remote command name:

whynot-dm

Arguments and Values:

```
chunk-name ::= the name of a chunk in the current model matching-chunk ::= the name of a chunk which matched the last retrieval request
```

Description:

The whynot-dm command can be used to determine which chunks in the current model's declarative memory matched the last retrieval request which the declarative module has received and to indicate reasons why a chunk did not get retrieved. If there has been a retrieval request made to the declarative module then the whynot-dm command will display the time at which the most recent request occurred along with the display of the request's specification. Then, for each of the chunk names passed to it (or all chunks in the model's declarative memory if no names are provided) it will print out the chunk, its appropriate parameters if subsymbolic computations are enabled, and then whether the chunk matched that request or not.

It returns a list of all the chunks which did match that request at the time it was made (regardless of whether they were passed into whynot-dm for display). The list is sorted by the chunks' activations at the time of the request (highest activation first), and if there was a chunk retrieved it will be the first element of the list.

If there is no current model then a warning is printed and **nil** is returned. If an invalid chunk-name is provided it will indicate that in the output.

Examples:

This example assumes the count model from unit 1 of the tutorial has been loaded.

```
1> (reset)
DEFAULT
2> (whynot-dm)
No retrieval request has been made.
NIL
3> (run .1)
    0.050
            DECLARATIVE
                                   START-RETRIEVAL
    0.050
           PROCEDURAL
                                   CONFLICT-RESOLUTION
    0.100
           DECLARATIVE
                                   RETRIEVED-CHUNK C
    0.100
                                   Stopped because time limit reached
0.1
20
NIL
4> (whynot-dm)
Retrieval request made at time 0.05:
   FIRST 2
FIRST-GOAL
   START 2
   END 4
Declarative parameters for chunk FIRST-GOAL:
 :Activation 0.000
 :Permanent-Noise 0.000
 :Base-Level 0.000
FIRST-GOAL did not match the request
F
   FIRST 5
   SECOND 6
Declarative parameters for chunk F:
 :Activation 0.000
 :Permanent-Noise 0.000
 :Base-Level 0.000
F did not match the request
   FIRST 4
   SECOND 5
Declarative parameters for chunk E:
 :Activation 0.000
 :Permanent-Noise 0.000
 :Base-Level 0.000
E did not match the request
D
   FIRST 3
   SECOND 4
Declarative parameters for chunk D:
 :Activation 0.000
 :Permanent-Noise 0.000
 :Base-Level 0.000
D did not match the request
```

```
С
   FIRST 2
   SECOND 3
Declarative parameters for chunk C:
 :Activation 0.000
 :Permanent-Noise 0.000
 :Base-Level 0.000
 :Last-Retrieval-Activation 0.000
 :Last-Retrieval-Time 0.050
C matched the request
C was the chunk chosen to be retrieved
   FIRST 1
   SECOND 2
Declarative parameters for chunk B:
 :Activation 0.000
 :Permanent-Noise 0.000
 :Base-Level 0.000
B did not match the request
(C)
5> (whynot-dm b)
Retrieval request made at time 0.05:
    FIRST 2
В
   FIRST 1
   SECOND 2
Declarative parameters for chunk B:
 :Activation 0.000
 :Permanent-Noise 0.000
 :Base-Level 0.000
B did not match the request
(C)
6> (whynot-dm-fct (list 'c))
Retrieval request made at time 0.05:
    FIRST 2
С
   FIRST 2
   SECOND 3
Declarative parameters for chunk C:
 :Activation 0.000
 :Permanent-Noise 0.000
 :Base-Level 0.000
 :Last-Retrieval-Activation 0.000
 :Last-Retrieval-Time 0.050
C matched the request
C was the chunk chosen to be retrieved
(C)
7> (whynot-dm first-goal-0)
Retrieval request made at time 0.05:
Chunk FIRST-GOAL-0 is not in the model's declarative memory.
```

```
(C)
8E> (whynot-dm :bad-name)
Retrieval request made at time 0.05:
    FIRST 2

:BAD-NAME does not name a chunk in the current model.
(C)
E> (whynot-dm)
#|Warning: Whynot-dm called with no current model. |#
NIL
```

simulate-retrieval-request

Syntax:

```
simulate-retrieval-request specification -> (matching-chunk*)
simulate-retrieval-request-fct (specification) -> (matching-chunk*)
simulate-retrieval-request-plus-seed-fct (specification) -> (matching-chunk*) seed
```

Remote command name:

```
simulate-retrieval-request 'specification 'simulate-retrieval-request-fct '(specification) 'simulate-retrieval-request-plus-seed-fct '(specification) '
```

Arguments and Values:

```
specification ::= [ chunk-name | {isa chunk-type }{{modifier} slot value}* ]
chunk-name ::= the name of a chunk in the current model
chunk-type ::= the name of a chunk-type in the current model
modifier ::= [= | - | < | > | <= | >=]
slot ::= [ possible-slot | request-param ]
possible-slot ::= the name of a valid slot in chunk-type or any valid slot if no chunk-type provided
request-param ::= a keyword which is a valid retrieval buffer request parameter
value ::= any value
matching-chunk ::= the name of a chunk in DM which matched specification
seed ::= the value of the :seed parameter in the model after the retrieval process was simulated
```

Description:

The simulate-retrieval-request command can be used to simulate the results of making a request to the retrieval buffer under the current model conditions. If there is a current model then the specification provided is used to create a <u>chunk-spec</u> which is used to simulate a request to the retrieval buffer. That request will perform the matching and activation calculations based on the current buffer contents for spreading activation and report the results of whether chunks match the request or not and show the activation for those which do similar to the low detail activation trace.

The simulated request does not perform many of the side effects which occur with a normal retrieval request. The simulated request does not trigger calls to the functions set with the :retrieval-request-hook, or :retrieval-chunk-hook parameters. The results of the simulated request are not recorded for use with why-not-dm and are not recorded in the retrieval-history stream. The activations computed will include noise, but the model's :seed parameter will be restored to the value it had prior to those computations. It does however set the activation parameter of the chunks that are matched which can be accessed using the command chunk-activation (see extending chunks for information on using chunk parameters).

It returns a list of all the chunks which match the request specified sorted by the chunks' activations (highest activation first) with any chunk which would have been retrieved as the first element of the list. However, just because there is a first element in the list does not mean that it would necessarily be retrieved because it may have an activation below the current retrieval threshold.

The simulate-retrieval-request-plus-seed-fct function returns the value of the <u>:seed parameter</u> after the retrieval process completes as its second value. That is done so that one can use this mechanism to implement a second buffer that accesses the model's declarative memory and update the random state appropriately.

If there is no current model then a warning is printed and **nil** is returned. If an invalid specification is provided it will indicate that in the output and return **nil**.

Examples:

These examples assume the grouped model from unit 5 of the tutorial has been loaded.

```
> (simulate-retrieval-request)
Chunk LIST has the current best activation 0.13675894
Chunk FIRST has activation -0.36428827
Chunk SECOND has activation -0.2693139
Chunk THIRD is now the current best with activation 0.15103722
Chunk FOURTH has activation 0.069821134
Chunk GROUP1 has activation 0.14088637
Chunk GROUP2 has activation 0.05243059
Chunk GROUP3 has activation -0.31867743
Chunk ITEM1 has activation -0.010031511
Chunk ITEM2 has activation 0.11004096
Chunk ITEM3 has activation -0.087834366
Chunk ITEM4 has activation -0.27916592
Chunk ITEM5 is now the current best with activation 0.21117316
Chunk ITEM6 has activation -0.2579252
Chunk ITEM7 has activation 0.18635121
Chunk ITEM8 has activation 0.09208258
Chunk ITEM9 has activation -0.2433808
Chunk GOAL has activation -0.044656888
Chunk ITEM5 with activation 0.21117316 is the best
(ITEM5 ITEM7 THIRD GROUP1 LIST ITEM2 ITEM8 FOURTH GROUP2 ITEM1 ...)
```

```
> (simulate-retrieval-request isa item - name nil)
Chunk ITEM1 has the current best activation -0.36428827
Chunk ITEM2 is now the current best with activation -0.2693139
Chunk ITEM3 is now the current best with activation 0.15103722
Chunk ITEM4 has activation 0.069821134
Chunk ITEM5 has activation 0.14088637
Chunk ITEM6 has activation 0.05243059
Chunk ITEM7 has activation -0.31867743
Chunk ITEM8 has activation -0.010031511
Chunk ITEM9 has activation 0.11004096
Chunk ITEM3 with activation 0.15103722 is the best
(ITEM3 ITEM5 ITEM9 ITEM4 ITEM6 ITEM8 ITEM2 ITEM7 ITEM1)
> (simulate-retrieval-request-fct '(position third))
Chunk GROUP1 has the current best activation -1.3642883
Chunk GROUP2 is now the current best with activation -0.76931393
Chunk GROUP3 is now the current best with activation 0.15103722
Chunk ITEM1 has activation -0.9301789
Chunk ITEM2 has activation -0.35911363
Chunk ITEM3 has activation 0.05243059
Chunk ITEM4 has activation -1.3186774
Chunk ITEM5 has activation -0.5100315
Chunk ITEM6 has activation 0.11004096
Chunk ITEM7 has activation -1.0878344
Chunk ITEM8 has activation -0.7791659
Chunk ITEM9 is now the current best with activation 0.21117316
Chunk ITEM9 with activation 0.21117316 is the best
(ITEM9 GROUP3 ITEM6 ITEM3 ITEM2 ITEM5 GROUP2 ITEM8 ITEM1 ITEM7 ...)
> (simulate-retrieval-request group1)
Chunk GROUP1 has the current best activation -0.36428827
Chunk GROUP2 has activation -1.7693139
Chunk GROUP3 has activation -1.8489628
Chunk GROUP1 with activation -0.36428827 is the best
(GROUP1 GROUP2 GROUP3)
> (simulate-retrieval-request-plus-seed-fct '(name "1"))
Chunk ITEM1 has the current best activation 0.13675894
Chunk ITEM2 has activation -1.3642883
Chunk ITEM3 has activation -1.2693139
Chunk ITEM4 has activation -0.8489628
Chunk ITEM5 has activation -0.9301789
Chunk ITEM6 has activation -0.85911363
Chunk ITEM7 has activation -0.94756943
Chunk ITEM8 has activation -1.3186774
Chunk ITEM9 has activation -1.0100315
Chunk ITEM1 with activation 0.13675894 is the best
(ITEM1 ITEM4 ITEM6 ITEM5 ITEM7 ITEM9 ITEM3 ITEM8 ITEM2)
(77093543977 39822)
E> (simulate-retrieval-request-fct '(isa list))
#|Warning: Element after isa in define-chunk-spec isn't a chunk-type. (ISA LIST) |#
#|Warning: Invalid request specification passed to simulate-retrieval-request. |#
NIL
E> (simulate-retrieval-request)
#|Warning: get-module called with no current model. |#
#|Warning: No declarative memory module available. Simulate-retrieval-request cannot
perform the request. |#
NTI
```

add-dm-chunks

Syntax:

```
add-dm-chunks existing-chunk-name* -> (existing-chunk-name*)
add-dm-chunks-fct (existing-chunk-name*) -> (existing-chunk-name*)
```

Remote command name:

add-dm-chunks add-dm-chunks-fct

Arguments and Values:

existing-chunk-name ::= the name of a chunk that already exists

Description:

The add-dm-chunks command can be used to add a chunk which already exists to the current model's declarative memory. For each of the names provided, if it names an existing chunk and that chunk is not already in the model's declarative memory it is added to declarative memory in the same way that add-dm adds chunks which it creates.

It returns a list of the chunks which were added to the model's declarative memory. If there is no current model then a warning is displayed and **nil** is returned.

Examples:

```
1> (add-dm a b)
(A B)

2> (define-chunks c d)
(C D)

3> (dm)
B

A
(B A)

4> (add-dm-chunks a c)
(C)

5> (add-dm-chunks-fct '(b d))
(D)

6> (dm)
D

C
```

```
A

(D C B A)

E> (add-dm-chunks a b)
#|Warning: get-module called with no current model. |#
#|Warning: Could not add chunks to DM because no declarative module was found |#
```

merge-dm-chunks

Syntax:

```
merge-dm-chunks existing-chunk-name* -> (existing-chunk-name*) merge-dm-chunks-fct (existing-chunk-name*) -> (existing-chunk-name*)
```

Remote command name:

```
merge-dm-chunks merge-dm-chunks-fct
```

Arguments and Values:

existing-chunk-name ::= the name of a chunk that already exists

Description:

The merge-dm-chunks command can be used to merge a chunk which already exists into the current model's declarative memory. For each of the names provided, if it names an existing chunk that is not already in declarative memory then it is merged into declarative memory in the same way that merge-dm merges chunks which it creates.

It returns a list of the chunks which were merged into the model's declarative memory. If there is no current model then a warning is displayed and **nil** is returned.

It would seem like this should allow a chunk to be merged repeatedly into declarative memory to strengthen that chunk, but since the <u>merge-chunks</u> command will not merge a chunk with itself that is not allowed. Instead, one would have to use merge-dm with the description of the chunk which could be created with <u>chunk-spec-to-chunk-def</u> and <u>chunk-name-to-chunk-spec</u>:

```
(merge-dm-fct (list (chunk-spec-to-chunk-def (chunk-name-to-chunk-spec 'd))))
Examples:
1> (add-dm (a value 1) (b value 2))
(A B)
2> (define-chunks (c value 1) (d value 3))
```

```
(C D)
3> (merge-dm-chunks b c)
(C)
4> (sdp)
Declarative parameters for chunk B:
 :Activation 2.191
 :Permanent-Noise 0.000
 :Base-Level 2.191
 :Creation-Time 0.000
 :Reference-Count 1
Declarative parameters for chunk A:
 :Activation 2.884
 :Permanent-Noise 0.000
 :Base-Level 2.884
 :Creation-Time 0.000
:Reference-Count 2
(B A)
5> (merge-dm-chunks-fct '(a d))
(D)
6> (sdp)
Declarative parameters for chunk D:
 :Activation 2.191
:Permanent-Noise 0.000
 :Base-Level 2.191
 :Creation-Time 0.000
 :Reference-Count 1
Declarative parameters for chunk B:
 :Activation 2.191
 :Permanent-Noise 0.000
 :Base-Level 2.191
 :Creation-Time 0.000
 :Reference-Count 1
Declarative parameters for chunk A:
 :Activation 2.884
 :Permanent-Noise 0.000
 :Base-Level 2.884
 :Creation-Time 0.000
:Reference-Count 2
(D B A)
E> (merge-dm-chunks a)
#|Warning: get-module called with no current model. |#
#|Warning: Could not merge chunks to DM because no declarative module was found |#
NIL
```

Perceptual & Motor modules

The perceptual and motor modules provide a model with a way to interact with a world. The provided perceptual modules allow the model to attend to visual and aural stimuli and the given motor modules provide the model with hands and a voice. The perceptual and motor modules provided with ACT-R are essentially updated versions of the modules which comprised those same components in the ACT-R/PM system. ACT-R/PM was developed by Mike Byrne as a combination of ACT-R, the Visual Interface for ACT-R created by Mike Matessa, and the EPIC cognitive architecture created by David Kieras and David Meyer. Providing a model access to an external world was an important development in the advancement of ACT-R modeling, and that integration lead to many of the changes that came about with the introduction of ACT-R 5 (which eventually replaced ACT-R/PM).

Unlike the cognitive modules, the perceptual and motor modules each primarily work with chunks that are created using the slots of specific chunk-types that the module defines, and the requests which they respond to are more rigidly specified descriptions of actions. The chunk-types a module defines and any initial chunks which it creates will be listed with each module's description.

These modules also have more complicated internal states than the basic state free and state busy which can be queried for all modules. Each of these modules has three separate internal systems: preparation, processor, and execution. Each of those systems can be queried individually for being busy or free. Different requests to these modules may require the use of different internal systems and thus may not require that all internal states be free before being allowed to progress. This is particularly useful in the motor module to request an action before the previous has completed. How the modules respond to the queries and how that affects the requests which can be made to them vary from module to module.

Before describing the perceptual and motor modules themselves, first some information about how those modules interact with the world will be described.

Devices

In previous versions of ACT-R the perceptual and motor modules interacted with the world through a single interface called a device. A model could only be associated with a single device at any time and that device had to provide a set of specific methods for interacting with the perceptual and motor modules. That approach however does not extend well to the distributed system design of this version of ACT-R, and thus the entire notion of a device has been overhauled.

Now, instead of a single device providing a specific set of methods for the perceptual and motor modules, the modules themselves have been redesigned to provide more user access without the need for a device. There is however still the ability to create devices, but now a device does not require any particular methods nor does it have to be associated with all of the perceptual and motor modules simultaneously. In fact, any module may provde an 'interface' to which a device (or possibly multiple devices) can be connected and different modules may have different devices installed at the same time. Effectively, now a device is just a general mechanism for extending the operation of the system.

The basic representation for the device in the older ACT-R software was one where the model was sitting in front of a computer monitor, with its hands on a keyboard or mouse, and speaking into a microphone. A similar set of capabilities are included with the current version, but those are now represented as separate devices, and those devices will be described with the appropriate modules.

There was also a set of tools provided with the older software which allowed one to create simple GUI tasks for a model based on the device mechanism (called the AGI – ACT-R GUI Interface). The AGI is still available, but now is not tied directly to any specific Lisp GUI libraries. It only provides a virtual system by default, but includes an API for connecting that virtual system to a real UI. The ACT-R Environment uses that API to create a visible UI which can be interacted with by a person or model, as was done through a custom device for the previous versions of ACT-R. Details on the AGI and the ACT-R Environment are available in their own manuals.

Information on creating devices and interfaces for modules are covered later in the manual. Here we will describe the software device module which provides the commands for working with devices as well as some parameters for controling the details for the basic model interface of interacting with a computer.

Device Module

The device module is a software module which provides the commands for installing and uninstalling devices, for finding out which modules provide interfaces for devices, and which devices are currently installed. It also maintains parameters that control the details of the devices which provide a basic computer interface for a model.

Parameters

:cursor-fitts-coeff

This parameter is the b coefficient in the Fitts's Law equation for aimed movements which is used when the model moves the mouse or other cursor devices. The default value is .1 and it can be set to any positive value.

:default-target-width

This is the width of targets with undefined widths when computing the Fitts's law computation for ply and move-cursor actions, when a zero or negative width is provided for any Fitts's law computation, and when an approach width for a visual feature cannot be computed. No units are assumed and this value is used explicitly. Therefore, it is in the same units as the distance provided for Fitts's law computations. The default value is 1.0.

:key-closure-time

This parameter specifies the amount of time in seconds that passes between when a key starts to be depressed and when the switch closes and signals the key is down. It is a representation of the physical devices with which the model interacts. The default value is .01.

:needs-mouse

This parameter controls whether or not the model will be using a mouse device. If it is set to a nonnil value then when using the AGI tools to create an interface for the model a mouse device will be installed automatically. If it is set to **nil** then no mouse device will be installed by default, and that is the default value. It can be set to **t**, any string, or any symbol. A string or symbol value is used to indicate a color for the AGI to use when displaying a mouse cursor so that the cursors for different models can be distinguished if being displayed through the visible AGI API. :pixels-per-inch

This is the number of pixels/inch used for computations of the size of items in terms of degrees of

visual angle. The default value is 72 and it can be set to any positive number.

:process-cursor

This parameter controls whether the mouse cursor should be included as a feature for the vision

module when using the AGI interface. If it is set to t, then a feature for the mouse will be generated

automatically. The default value is nil.

:stable-loc-names

When using the AGI interface, this parameter determines whether the device sorts the items found in

the window before generating the visual features. Setting the parameter to t, which is the default

value, will force the items to be sorted which means that the same AGI display will result in the same

feature names each time it is run on all systems – it will be deterministic. If it is set to **nil** then the

items in the interface will not be sorted and the names could vary among runs or across systems.

Setting it to **nil** should not affect the model's performance and may improve the time it takes to run

the simulation at the potential cost of debugging time needed to compare different model runs.

:viewing-distance

This is the assumed distance between the model's eyes and the display in inches. It is used in

determining the size of items in terms of degrees of visual angle. The default is 15 and it can be set

to any positive number.

Commands

install-device

Syntax:

install-device device-list -> [device-list | nil]

Remote command name:

install-device

Arguments and Values:

device-list ::= (interface device {details})

339

```
interface ::= a string which names the interface to which the device is being installed device ::= a string which names the device being installed details ::= any value which will be passed to the device when installed
```

Description:

The install-device command takes one parameter which should be a list of two or three items. If the first item in the list names an interface and the second item names a device, then that device is attempted to be installed into that interface for the current model. If a third parameter is provided then it is passed to the device during the istallation. If the device is successfully installed into the interface then the device-list is returned. If any of the parameters are invalid, the given device is already installed for that interface, the device is not successfully installed, or there is no current model then a warning is printed and **nil** is returned.

Examples:

```
> (install-device '("motor" "cursor" "mouse"))
("motor" "cursor" "mouse")
1> (install-device '("motor" "keyboard"))
("motor" "keyboard")
2E> (install-device '("motor" "keyboard"))
#|Warning: The device ("motor" "keyboard") is already installed. No device installed. |#
NIL
E> (install-device '("vision" "keyboard"))
#|Warning: Keyboard does not yet support any features for the vision interface. |#
NIL
E> (install-device '("speech" "keyboard"))
#|Warning: Keyboard device does not provide actions for the "speech" interface. |#
#|Warning: Keyboard does not yet support being used with the speech interface. |#
E> (install-device '("bad" "keyboard"))
#|Warning: Invalid interface "bad" in call to install-device with ("bad" "keyboard"). No
device installed. |#
NIL
E> (install-device '("motor" "bad"))
#|Warning: Invalid device "bad" in call to install-device with ("motor" "bad"). No device
installed. |#
E> (install-device '("motor" "keyboard"))
#|Warning: install-device called with no current model. |#
NIL
```

remove-device

Syntax:

remove-device device-list -> [t | nil]

Remote command name:

remove-device

Arguments and Values:

```
device-list ::= (interface device {details})
interface ::= a string which names the interface to which device was installed
device ::= a string which names the device that was installed
details ::= any value which was passed to the device when installed
```

Description:

The remove-device command takes one parameter which should be a list of two or three items. If that list of items has been installed as a device in the current model then that device is removed from those which are installed and **t** is returned. If the list is not one which has been installed or there is not current model then a warning is printed and **nil** is returned.

Examples:

```
1> (install-device '("motor" "keyboard"))
("motor" "keyboard")

2> (remove-device '("motor" "keyboard"))
T

3E> (remove-device '("motor" "keyboard"))
#|Warning: Device ("motor" "keyboard") is not currently installed and cannot be removed. |
# NIL

E> (remove-device '("bad"))
#|Warning: Device ("bad") is not currently installed and cannot be removed. |#
NIL

E> (remove-device '("motor" "keyboard"))
#|Warning: remove-device called with no current model. |#
NII
```

current-devices

```
current-devices interface -> [ (device-list*) | nil ]
```

Remote command name:

current-devices

Arguments and Values:

interface ::= a string which names an interface

```
device-list ::= (interface device {details})
device ::= a string which names a device that was installed
details ::= a value which was passed to the device when installed
```

Description:

The current-device command takes one parameter which is the name of an interface. It returns a list of device-lists for all the devices that are installed for that interface in the current model. If there is no current model or the given value does not name an interface then a warning is printed and **nil** is returned.

Examples:

```
1> (install-device '("motor" "cursor" "mouse"))
("motor" "cursor" "mouse")

2> (current-devices "motor")
(("motor" "cursor" "mouse"))

> (current-devices "vision")
NIL

E> (current-devices "bad")
#|Warning: "bad" does not name a valid interface in call to current-devices. |#
NIL

E> (current-devices "motor")
#|Warning: current-devices called with no current model. |#
NIL
```

defined-devices

defined-devices -> device*

Remote command name:

defined-devices

Arguments and Values:

device ::= a string which names a device

Description:

The defined-devices command takes no parameters and returns a list with the names of all the devices which are currently defined.

Examples:

```
> (defined-devices)
("cursor" "exp-window" "keyboard" "microphone")
```

defined-interfaces

defined-interfaces -> interface*

Remote command name:

defined-interfaces

Arguments and Values:

interface ::= a string which names an interface

Description:

The defined-interfaces command takes no parameters and returns a list with the names of all the interfaces which are currently defined.

Examples:

```
> (defined-interfaces)
("motor" "speech" "vision")
```

notify-device

Syntax:

notify-device device-list feature -> [result | nil]

Remote command name:

notify-device

Arguments and Values:

```
device-list ::= a list representing an installed device feature ::= any value which will be passed to the device's notification command result ::= any value which is returned by the device's notification command
```

Description:

The notify-device command takes two parameters. The first should be a list of two or three items which represents an installed device for the current model. The second can be any value. If the current model has the indicated device installed, then the feature value provided will be passed to the notification command for that device (if it has one) and the value returned by that command will be returned. If the device is not installed, there is no current model, or the device does not have a notification command then **nil** will be returned.

What a notification command does with the feature is up to the device and there are no constraints on how that can be used. Some examples of how it can be used are the experiment window device of the AGI uses it to allow the user to pass new display details to visible window handlers and the default keyboard device uses it for the motor module to pass finger movements to the keyboard which may then result in key presses.

Examples:

```
E> (notify-device nil nil)
#|Warning: notify-device called with no current model. |#
NIL

E> (notify-device nil nil)
#|Warning: Device NIL is not installed when trying to notify with features NIL. |#
NIL
```

Vision module

The vision module provides a model with a visual attention system. That attention system is an abstraction which does not attempt to model what is happening with the eyes₁, and it consists of two subsystems: a "where" system and a "what" system. Those two subsystems work together, but each has its own buffer and accepts specific requests.

The model's visual world

The vision module "sees" objects that are provided to it directly by the modeler and/or through devices — it does not do any image processing or attempt to create visual features on its own (although people have built extensions which do that to create the objects for the module). Those objects each have a set of features, and all of the features of the objects available to the model are referred to collectively as the visicon (visual icon). The features in the visicon are available to the where system to find the location of an object which creates a chunk containing some of the information about the object, like its general categorization, location, and color (the specific details on the information that is available are up to the modeler/device but must include some representation of a location). With that location information the what system can attend to the object and get a chunk containing a more detailed representation of its information (again the details on the information that is available are up to the modeler/device).

Details on how to create visual features for a model are described in the <u>visicon features</u> section of the manual.

The Where System

The where system takes requests through the visual-location buffer. A request to the visual-location buffer specifies a set of feature constraints, and the where system searches the visicon to find an object which matches those constraints and creates a chunk representing the corresponding item's location if one is found. This is often referred to as "finding a location". The constraints are specified as slot-value pairs in a request and should represent visual properties of the object, the spatial location of the object, coarse temporal information such as whether it recently became visible, and tests of whether the model has previously attended to that location. This is akin to so-called "pre-attentive"

_

¹ There has been work done by Dario Salvucci to create a more detailed vision module which takes into account eye movements which is instantiated in a system called EMMA (eye movements and movements of attention) which can be used as an extension of the vision module in ACT-R. That module is included in the extras directory of ACT-R, and is not part of the default system and will not be described here.

visual processing (Triesman & Gelade, 1980) and supports visual pop-out effects. For example, if the display consists of one green object in a field of blue objects, the time to determine the location of the green object is constant regardless of the number of blue objects. It is also possible to specify the specific information about the object e.g. find the letter X, which is not information that would be considered pre-attentive. The reason for allowing that is to provide ACT-R modelers with enough flexibility to use the system as they want, and, as with many pieces of the software, it is up to the modeler to decide what is reasonable/justifiable when building a model.

When a visual-location request is made, if there is an object in the visicon whose features meet the constraints, then a chunk representing the location of that object is placed in the visual-location buffer. If multiple objects meet the constraints, then the newest one (the one with the most recent onset time) will be the one that is chosen. If multiple objects meet the constraints and they have the same onset time, then one of those objects will be picked randomly. If there are no objects which meet the constraints, then the buffer will be left empty and an error will be indicated.

Finsts

As noted above, one property of the objects in the vision which can be tested is whether the item has been previously attended by the model. The vision module is able to keep track of a small number of locations to which it has attended. It does so using a set of markers called finsts (fingers of instantiation) which are limited both in number and in duration. When an object is attended by the model a finst is placed upon it. The finst will remain until the its duration expires, at which time the object will revert to unattended, or until an attention shift requires a finst and there are none available. If all finsts are in use and a new one is needed then the oldest one which was assigned will be removed (thus forcing that object to revert to unattended) and reused for the newly attended object. The visual finsts work the same as those described for the <u>declarative module</u>, but the two systems are separate with each module having its own set of finsts.

The What System

The what system takes requests through the visual buffer. Its primary use is to attended to objects which have been found using the where system. To do that, a request to the what system is made providing a chunk representing an object's location. That will cause the what system to shift visual attention to that location, process the object located there, and place a chunk representing the object into the visual buffer. If there is more than one object at the location specified when the attention shift completes, only one of them will be encoded and placed into the buffer. The vision module

chooses among the objects by using the constraints which led to the where system finding that visual location. Thus, if the location to be attended to was found based on a constraint of having the color red, and there are three objects at that location, one of which is red, then the red one will be encoded.

The what system has a rudimentary tolerance for movement. That is, if the location chunk provided to be attended specifies a location, but the object which created that feature has moved slightly such that it is no longer at that specific location the vision module will still attend that item if the movement is small. Just how far an object can move and still be encoded is configurable with a parameter, and the default tolerance is 0.5 degrees of visual angle. That means the object can move up to 0.5 degrees of visual angle from the location which was found by the where system and still be processed by the what system.

The basic assumption behind the vision module is that the chunks placed into the visual buffer as a result of an attention operation are episodic representations of the objects in the visual scene. Thus, a chunk with the value "3" represents a memory of the character "3" available via the eyes, not the semantic THREE used in arithmetic—a declarative retrieval would be necessary to make that mapping. Note also that there is no "top-down" influence on the creation of these chunks; top-down effects are assumed to be a result of the system's processing of these basic visual chunks, not anything that's done by the vision module. (See Pylyshyn, 1999 for a clear argument about why it should work this way.)

Re-encoding

Once a location has been attended to the model continues to attend to that location until stopped, and if the visual scene changes the module will automatically update the chunk in the visual buffer to reflect any changes which occurred at that location. The where system will be busy while it reencodes the new object (or lack of one) at the currently attended location. This behavior is sometimes undesirable because visual attention cannot be shifted to a new location while it is busy re-encoding a change at the current location which may make a response to new stimuli slower than desired. If this is a problem, it is possible for the model to stop attending to a location after it has processed the visual chunk. A <u>clear request</u> to the visual buffer can be used to make the vision module stop attending to the visual scene, and then it will no longer re-encode items until a new attention shift is performed.

Scene change

The vision module is sensitive to every change to the visual scene with respect to re-encoding as described above. It is also possible for the model to detect when there has been a change as well, and the modeler can specify how much change is required before the model will "notice" the difference. When there is a change to the visicon the module computes the proportion of the items which have changed. If that value is greater-than or equal to a threshold set with the <u>:scene-change-threshold parameter</u> then the module will indicate that there has been a scene change. That signal will only last for a short time (controlled with the <u>:visual-onset-span parameter</u>), and is made available to the model through the <u>scene-change query</u> of the visual buffer.

This is the calculation which computes the proportion of items which have changed:

$$Change = \frac{d+n}{o+n}$$

o: The number of features in the scene prior to the update

d: The number of features which have been deleted or modified from the original scene

n: The number of features which are newly added to the scene by the update

If both o and n are 0 then the change value is also reported as 0 (which could happen if there are no old items and all the new items are added and removed within a single update).

Tracking

The vision module has a rudimentary ability to track moving objects. The basic pattern is to attend the object, then issue a request to start tracking it. While the module is tracking an object the chunks representing that item in the visual-location and visual buffers will be updated as the object moves, and the where system will remain busy. Tracking will continue until a new request is made of the what system, which could be a clear request to stop attending everything.

Interface & Devices

The vision module provides an interface called "vision" which can be used to install devices. That interface has no functionality associated with it other than to generate an <u>installing-vision-device signal</u> which can be monitored to know when a visual device is installed. Any number of devices can be connected to it. The assumption is that any device connected will provide features to the vision module using the same mechanisms available to the modeler.

The "exp-window" device provided by the AGI can be installed for the vision interface to provide the model with visual features for some simple GUI items (text, buttons, lines, and images) which are described in detail in the AGI manual.

A "cursor" device can be installed for the vision interface to provide the model with an object that represents the cursor it is controlling (which presumably is also installed for the motor module so that the model can control it). That object will be updated as the cursor moves. The location chunk for a cursor object will look like this (where the value represents the type of cursor installed):

```
VISUAL-LOCATIONO
KIND CURSOR
VALUE MOUSE
DISTANCE 1080
SCREEN-X 0
SCREEN-Y 0
SIZE 1.0
```

The object chunk will look like this:

```
CURSOR0-0
SCREEN-POS VISUAL-LOCATION0
VALUE MOUSE
CURSOR T
```

History Stream

visicon-history

The vision module provides one data history stream called visicon-history. When it is enabled it will record the information from the visicon every time it is updated. The data will be recorded based on the time of the update, and the value recorded will be a string with the text as would be output from print-visicon at that time.

Parameters

:auto-attend

This parameter controls whether or not a visual-location request results in an automatically generated request to the visual buffer to also move attention to the location which is found. This is designed as a modeling shortcut to allow one to skip productions which make attention shift requests when they will always follow a visual-location request in the model. It does not affect the timing of the model

because there is a 50ms delay before the visual request is sent to compensate for the skipped production's firing time. It is off by default (**nil**) but setting it to **t** will enable that functionality.

:delete-visicon-chunks

This parameter controls what happens to chunks which the vision module creates internally for the visicon when they are no longer needed. The default value is **t** which means that those chunks are deleted and the names uninterned through the <u>purge-chunk command</u>. Setting this parameter to **nil** will prevent those chunks from being deleted. Most models should leave this parameter at the default value, but if one is working to extend or modify the operation of the vision module itself it may be necessary to disable this functionality.

:optimize-visual

This parameter is not currently used by the system. In previous versions of ACT-R it allowed the modeler to control how text is processed by the AGI devices, and it could be set to have each letter that was displayed parsed into multiple sub-letter features from different possible feature sets like those from Gibson's (1968) set and Briggs & Hochevar's (1975) set. This capability will be available again in the future, but might not be associated with this specific parameter because it will likely be part of a more general "processing level" mechanism.

:overstuff-visual-location

This parameter controls whether the module can "stuff" a new chunk into the buffer when there is already a previously stuffed chunk in the buffer. The default value is **nil** which means that it will not overwrite a previously stuffed chunk, but if it is set to **t** then it will overwrite a chunk which was stuffed into the visual-location buffer with a new one.

:scene-change-threshold

This parameter controls the smallest proportion of change in the visicon which will result in signaling that the scene has changed. It must be set to a number in the range [0.0 - 1.0] and defaults to .25.

:tracking-clear

This parameter controls how the module reacts when an object being tracked is no longer found in the visicon. If it is set to \mathbf{t} (which is the default value) then the module will clear the currently attended location when it stops tracking which will leave the visual buffer empty if it was holding the tracked

object chunk. If it is set to **nil** then the currently attended location will be the last tracked location of the object and the <u>re-encoding process</u> will take place if the visual buffer is empty.

:unstuff-visaul-location

This parameter lets the modeler specify whether the vision module removes the chunks which it "stuffs" into the visual-location buffer. The default value is **t** which means that if a stuffed chunk is still in the visual-location buffer and has not be modified after the <u>:visual-onset-span</u> time has passed that chunk will be <u>erased</u> from the buffer by the vision module. If it is set to a number then it works similar to the setting of **t** except that the value of this parameter specifies the time in seconds after which the erasing occurs instead of the :visual-onset-span parameter. If it is set to **nil** then the module will not automatically remove a chunk which has been stuffed into the visual-location.

:visual-attention-latency

This parameter specifies how long a visual attention shift will take in seconds. The default value is . 085.

:visual-finst-span

This parameter controls how long a finst marker will remain on a feature. It is measured in seconds and defaults to 3.0.

:visual-movement-tolerance

This parameter controls how far an object can move and still being considered the same object by the vision module without being explicitly tracked. It is measured in degrees of visual angle and defaults to 0.5.

:visual-num-finsts

This parameter controls how many finsts are available to the vision module. It can be set to any positive number and defaults to 4.

:visual-onset-span

This parameter specifies how long an item recently added to the visicon will be marked as new and also for how long a scene change notice will be available. It is measured in seconds, and the default value is 0.5.

:visual-encoding-hook

This parameter can be set to a command which can adjust the time that it takes for a move-attention

request or automatic re-encoding to finish with the encoding-complete action. If a command is set

for this parameter it will be called during each move-attention request and automatic re-encoding

with four parameters: a list of the coordinates which are currently being attended at the time of the

request or **nil** if there is no currently attended location, a list of the coordinates of the new location to

attend, the name of the chunk which was used to specify the new location, and the scale value for the

attention request. If the hook command returns **nil** then the normal encoding time will apply. If the

command returns a number then that is used as a time in seconds for the length of the encoding

process (which will be randomized if the :randomize-time parameter is enabled). Any other return

value suppresses the competion of the encoding-complete action and the schedule-encoding-complete

command must be called to finish the attention shift. Only one command can be set on the hook at a

time, and it will print a warning if a command is replaced with a different one.

Visual-location buffer

The visual-location buffer is used to access the where system of the vision module as described

above. In addition to taking requests to find locations, the vision module will also place chunks into

the visual-location buffer automatically without a model request (a process referred to as "buffer

stuffing"). Whenever there is an update to the visual scene, if the visual-location buffer is empty or

the <u>:overstuff-visual-location</u> parameter is set to **t** and a previously "stuffed" chunk is in the visual-

location buffer, a location chunk of some visual feature may be placed into the visual-location buffer.

The feature which gets "stuffed" into the buffer is chosen based on preferences which can be set

either by the modeler using the <u>set-visloc-default command</u> or directly by the model with a <u>set-visloc-</u>

default request. The default preference is for the left-most unattended item. If the :unstuff-visual-

<u>location</u> parameter is not **nil** then the module will also automatically remove a stuffed chunk from the

buffer if it is there past the indicated delay time.

Activation spread parameter: :visual-location-activation

Default value: 0.0

Queries

'State busy' will always be nil.

352

'State free' will always be t.

'State error' will be ${f t}$ if the last visual-location request failed to find a matching location and it will be ${f nil}$ in all other situations. Once it becomes ${f t}$ it will remain ${f t}$ until a new visual-location request is

made or a clear request is made of the *visual* buffer.

The visual-location buffer has an additional query that allows one to check the attended status of the

location represented by the chunk currently in the visual-location buffer.

'Attended t' will be t if there is a chunk in the visual-location buffer and that location currently has a

finst on it. Otherwise it will be nil.

'Attended nil' will be t if there is a chunk in the visual-location buffer and that location does not

currently have a finst on it. Otherwise it will be nil.

'Attended new' will be t if there is a chunk in the visual-location buffer, that location does not

currently have a finst, and that feature was added to the model's visicon within the <u>:visual-onset-span</u>.

Otherwise it will be nil.

Requests

Find location

A find-location request to the visual-location buffer is an attempt to find an item in the visicon. All of the items in the visicon are compared against the specification provided in the request and if there is an item which matches that specification a chunk describing that item is placed into the visual-location buffer. The specification given describes the properties which the item must have in order to match. If a property is not specified then its value is not considered for the matching.

Any of the slots may be specified using any of the modifiers (-, <, >, <=, or >=) in much the same way one specifies a <u>retrieval request</u>. Each of the slots may be specified any number of times. In addition, there are some special tests which one can use that will be described below. All of the constraints specified will be used to find a location in the visicon to be placed into the visual-location buffer. If there is no location in the visicon which satisfies all of the constraints then the visual-location buffer will indicate an error state and set the visual-location buffer's failure flag.

When the slot being tested holds a number it is also possible to use the slot modifiers <, <=, >, and >= along with specifying the value. If the value being tested or the value specified is not a number, then those tests will result in warnings and are not considered in the matching.

You can use the values **lowest** and **highest** in the specification of any slot which has a numeric value. Of the features which match the other constraints the one with the numerically lowest or highest value for that slot will then be the one found. There is one note about using **lowest** and **highest** when more than one slot is specified in that way. First, all of the non-relative values are used to determine the set of items to be tested for relative values. Then the relative tests are performed one at a time in the order provided to reduce the matching set.

It is also possible to use the special value **current** in a slot of the request. That means the value of the slot must be the same as the value for the location of the currently attended object (the one attention was last shifted to with a move-attention request to the visual buffer). If the model does not have a currently attended object (it has not yet attended to anything or has cleared its attention) then the tests with a value of **current** are ignored.

An additional component of the find location requests is the ability to use variables to compare the particular values within a feature to each other in the same way that the LHS tests of a production use variables to match chunks. If a value for a slot in a find location request starts with the character & then it is considered to be a variable in the request. The request variables can be combined with the modifiers and any of the other values allowed to be used in the requests.

The :nearest request parameter can be used to find the items closest to the currently attended location in some dimension or closest to some other location. If there are constraints other than :nearest specified then they are all tested first. The nearest of the locations that matches all of the other constraints is the one that will be placed into the buffer. There are several options available for using the :nearest request parameter. To find the location of the object nearest to the currently attended location (computed as the straight line distance based on the screen-x, screen-y, and distance values of the feature by default) we can again use the value **current**. Alternatively, one can specify any location chunk for the nearest test, and the location of the object nearest to that location will be the one returned. It is also possible to find the locations of objects nearest to the current object along a particular axis by specifying current-x, current-y, or current-distance. Finally, one can request locations which are nearest in angular distance relative to an arbitrary center point using either **clockwise** or **counterclockwise** as the nearest specification. The center point used for the calculation is the location specified using the :center request parameter (or the location of the object if a visual object is provided as the :center). If no :center is specified in the request then the most recent center specified by the <u>set-visual-center-point command</u> is used, or the default center point of 0,0 is used if set-visual-center-point has not been called.

If the :attended request parameter is specified, that is used as a test of the finsts: :attended **t** means that the item is currently marked with a finst, :attended **nil** means that it is not, and :attended **new** means that it is not currently marked and it has recently been added to the visicon (within the time specified by the :visual-onset-span parameter).

If there is more than one item which is found as a match, then the one which has been added to the visicon most recently will be the one chosen, and if there is more than one with the same recent onset time, then a random one of those will be chosen.

This request takes no time to return the resulting chunk and will show up with the following events when successful:

0.050 VISION Find-location 0.050 VISION SET-BUFFER-CHUNK VISUAL-LOCATION LOC1

When no location in the visicon matches the request a failure will be indicated in the trace with a find-loc-failure event:

0.755 VISION FIND-LOC-FAILURE

When the :auto-attend parameter is set to **t** a move attention request will follow all successful find location requests. The move-attention event will occur 50ms after the find-location event and the vision module will be busy during the entire time from the find-location request until the attention shift is completed (the automatically attending event will only show in the high detail trace level):

```
0.050 VISION Find-location
0.050 VISION SET-BUFFER-CHUNK VISUAL-LOCATION VISUAL-LOCATION1-0
0.050 VISION automatically attending VISUAL-LOCATION1-0
...
0.100 VISION Move-attention VISUAL-LOCATION1-0
0.185 VISION Encoding-complete VISUAL-LOCATION1-0 NIL
```

Set-visloc-default

```
{isa set-visloc-default-type}
   set-visloc-default t
   {{modifier} valid-slot [value | variable]}*
   {:nearest nearest-spec}
   {:attended [t | nil | new]}
   {:center [vis-loc | vis-obj]}
set-visloc-default-type ::= the name of a chunk-type
modifier ::= [ = | - | > | < | >= | <= ]
valid-slot ::= the name of a slot which is valid for the set-visloc-default-type if provided or any chunk
             otherwise
value ::= any value, but the symbols lowest, highest and current have special meanings.
variable ::= a name which starts with the character &
nearest-spec ::= [vis-loc | current | current-x | current-y | current-distance | clockwise |
                 counterclockwise ]
vis-loc ::= a chunk which has represents a visual location
vis-obj ::= a chunk which represents a visual object
```

A set-visloc-default request allows the model to change the constraints that are used when determining which (if any) chunk from the visicon will be stuffed into the visual-location buffer when the screen is updated. It works the same as the <u>set-visloc-default command</u> described below.

The slot values provided can be specified in the same way that they can for a find location request. The only difference is that this request requires the slot set-visloc-default be specified with a value of **t** to distinguish it from a normal find location request.

This request does not directly place a chunk into the visual-location buffer. It works essentially as a delayed request – at each future visicon update this specification will be used to determine if a chunk should be placed into the visual-location buffer. However, it does initiate an immediate check of the

visicon using the new specification which could result in a chunk being placed into the buffer at the

time of the request.

It will generate an event in the trace which looks like this:

0.850 **VISION** Set-visloc-default

If a chunk is stuffed into the buffer either immediately due to this request or upon a future screen

change the trace showing that setting of the chunk in the buffer will indicate that it was unrequested:

0.850 **VISION** SET-BUFFER-CHUNK VISUAL-LOCATION VISUAL-LOCATIONO-0 NIL

Visual buffer

The visual buffer is used to access the what system of the vision module as described above. It takes

requests to attend to locations, track features, or to stop attending to items, and it will hold a chunk

representing a visual object in response to requests.

Activation spread parameter: :visual-activation

Default value: 0.0

Queries

'State busy' will be **t** between the time any visual request is started and the time it completes. It will

also be **t** between when an unrequested re-encoding starts and it completes. It will be **nil** otherwise.

'State free' will be **nil** between the time any visual request is started and the time it completes. It will

also be **nil** between when an unrequested re-encoding starts and it completes. It will be **t** otherwise.

'State error' will be **t** if the last visual request failed or **nil** otherwise. It will not change from **t** to **nil**

until a successful request is completed -- any of the available visual requests will reset the error state

to **nil** if completed.

'Scene-change t' will be t if there has been a detected scene change which has not been explicitly

cleared within the past :visual-onset-span seconds. Otherwise it will be **nil**.

'Scene-change nil' will be t if there has not been a detected scene change within the past :visual-

onset-span seconds or such a scene change has been explicitly cleared. Otherwise it will be **nil**.

357

'Scene-change-value *value*' will be **t** if *value* is a number and the last scene change had a proportion

of change which is greater than or equal to value. Otherwise it will be nil. This query is intended

primarily as a debugging aid so that a modeler can see the last change value via the buffer-status

command, but there may be circumstances where it would be useful to test that directly within a

model.

The visual buffer can be used to query the internal states of the vision module, but this is generally

not needed since there is no benefit to doing so since the requests cannot be "pipelined" by checking

for particular subsystems being free.

'Preparation busy' will be **t** during the execution of a clear request and it will be **nil** otherwise.

'Preparation free' will be **nil** during the execution of a clear request and it will be **t** otherwise.

'Processor busy' will be t between the time a move-attention request is started and the time it

completes and it will be **nil** otherwise.

'Processor free' will be **nil** between the time a move-attention request is started and the time it

completes and it will be t otherwise.

'Execution busy' will be t between the time of a move-attention or start-tracking request and its

completion as well as during an unrequested re-encoding. It will be **nil** otherwise.

'Execution free' will be **nil** between the time of a move-attention or start-tracking request and its

completion as well as during an unrequisted re-encoding. It will be **t** otherwise.

'Last-command *command*' The query will be **t** if *command* is a symbol which is the name of the last

request received by the vision module (through either the visual-location or visual buffer) or the

symbol **none**, otherwise it will be **nil**. The visual-location requests are named find-location and set-

visloc-default, and the visual requests are named move-attention, start-tracking, clear-scene-change,

and assign-finst. If there has not been a request, or a clear request has occurred then the last

command will be recorded as the symbol **none**.

Requests

move-attention

cmd move-attention **screen-pos** *location*

358

{scale level}

The move-attention request moves the vision module's attention to the item at the location given, which must be a chunk specifying a visual location (it must have the x and y position slots which are screen-x and screen-y by default). If there is an item within the <u>movement tolerance</u> of that location, then a chunk which represents that item is placed into the visual buffer after the <u>attention shift time</u> passes (unless the <u>:visual-encoding-hook</u> parameter is set in which case the time to finish the encoding may be generated by an external source). If there is no item there, then the buffer is left empty and the error state of the visual buffer is set and a buffer failure is indicated.

The scale value is currently unused. In older versions of ACT-R it was possible for the vision module to attempt to coalesce separate text items provided by the AGI device into words or phrases, but that capability is not currently provided. A more general use of scale is being developed which will provide more flexibility to the modeler in creating the visicon, but that is not yet available.

A move-attention request results in the following events being displayed in the trace showing the move-attention event with the location to which attention was shifted and the scale used (shown as NIL here because no scale was specified in that request), the encoding-complete occurring after the wisual-attention-latency time passes (in this case the default .085 seconds) also showing the location and scale from the request, and then the buffer being set to the chunk that encodes the visual information:

0.100	VISION	Move-attention LOC1-0 NIL
0.185 0.185	VISION VISION	Encoding-complete LOC1-0 NIL SET-BUFFER-CHUNK VISUAL TEXT1

If no item is found, then the same first two events will be shown, but there will be no setting of a chunk in the buffer and instead an event will show that no object was found:

```
0.185 VISION No visual-object found
```

and the state error query will report **t** and the visual buffer's failure flag will be set.

There may also be maintenance events generated which have no trace output that have an action of unlock-device when the move-attention request comes from a production because the vision module delays processing any visual updates that occur while the production is firing to avoid any inconsistencies in the information – no visicon updates are processed between the selection of a production and its firing if that production has a request to the visual buffer.

If a move-attention request is received while the module is currently handling another request, then a warning is printed and the current request is ignored:

```
#|Warning: Attention shift requested at 0.8 while one was already in progress. |#
```

The timing of the encoding-complete event for this request uses the <u>randomize-time command</u>. Therefore, if the <u>:randomize-time parameter</u> is set to a non-**nil** value the timing on that event will be randomized accordingly.

start-tracking

cmd start-tracking

The start-tracking request will make the vision module continue to "track" an item in the vision as it moves and/or changes over time until the tracking is terminated. If there is an item currently attended by the vision module, then the start-tracking request will keep the vision module's attention focused on that item. Both the visual-location and visual buffers will be updated with changes to that item and if the buffers are empty new chunks will be placed into them representing any changes. The execution state will be busy while the model is tracking. This will show up in the trace as a start-tracking event and there will be subsequent set-buffer-chunk and mod-buffer chunk events to update the visual-location and visual buffers as necessary (note that the setting is marked as requested **nil** because the chunks are not a direct result of the request):

0.185	VISION	Start-tracking
0.185 0.185	VISION VISION	SET-BUFFER-CHUNK VISUAL-LOCATION LOC3 NIL SET-BUFFER-CHUNK VISUAL TEXT1 NIL
0.700 0.700	VISION VISION	MOD-BUFFER-CHUNK VISUAL-LOCATION MOD-BUFFER-CHUNK VISUAL
1.000 1.000	VISION VISION	SET-BUFFER-CHUNK VISUAL-LOCATION LOC11 NIL SET-BUFFER-CHUNK VISUAL TEXT5 NIL

If a request to start-tracking is made when there is no currently attended item a warning will be displayed and the module will not become busy:

```
#|Warning: Request to track object but nothing is currently being attended. |#
```

There is one minor issue which may be important in the model when using tracking. For the visual-location buffer to be updated it must either be empty when the start-tracking request is made, it must contain the visual-location chunk which was used when the object was first attended, or it must contain the chunk which matches the screen-pos slot of the chunk in the visual buffer. However,

buffer stuffing may place a different chunk into that buffer between the attention shift and the starting of tracking. Thus, if one wants to make sure that both buffers will be updated with tracking information there should also be a -visual-location> action in the production which makes the start-tracking request to clear the buffer or an =visual-location> action to keep the current chunk (assuming the current chunk matches the object to be tracked).

If the tracked object no longer appears in the visicon then the module will stop updating the buffers. If the tracking-clear parameter is set to t then the module will not attempt to re-encode a new visual object, but if tracking-clear is set to nil then the re-encoding will occur at the last location of the object being tracked.

clear

[cmd clear | clear t]

A clear request can be used to make the vision module stop attending to any currently attended object which will stop the re-encoding from occurring until a new item is attended. A clear request will also stop the tracking of an item, clear the error flags if set for either of the vision module's buffers, and clear the change scene notice if one is set. A clear request will make the preparation state busy for 50ms.

Here are the events which will show for a clear request.

```
1.455 VISION CLEAR
...

1.505 VISION CHANGE-STATE LAST NONE PREP FREE
```

Note, that after the clear request is done the last-command recorded by the module will be none and not clear – the clear effectively clears the history of its own request as well.

It will also generate a <u>visual-clear signal</u> which can be monitored.

clear-scene-change

cmd clear-scene-change

A clear-scene-change request can be used to clear any pending scene change notice from the module. It will not affect any other operation of the module. A clear-scene-change request will take no time and does not make any of the module's stages busy.

Here is the event which will show in the trace for a clear-scene-change request.

0.485 VISION

CLEAR-SCENE-CHANGE

assign-finst

```
cmd assign-finst
[object obj | location loc]
```

The assign-finst request can be used to explicitly tag a visual item as having been attended with a finst. The item can be specified using one of the chunks previously returned by the vision module through either buffer. If it is an object chunk returned through the visual buffer then it must be specified using the object slot, and if it is a location chunk from the visual-location buffer it must be specified using the location slot. It takes no time to process the request and the module will not be marked as busy. An event like one of these will be shown in the trace indicating which slot was used to assign the finst:

0.100 VISION assign-finst LOCATION VISUAL-LOCATION0-0-00.235 VISION assign-finst OBJECT TEXTO-0

If the chunk provided represents an item in the current visicon then that item will have a finst placed on it in the same way as if it had been explicitly attended. If the item does not represent a feature in the visicon then a warning is printed and no action is performed:

#|Warning: X does not name an object or feature in the current visicon. No finst created.|#
This request does not affect the status of any of the module's queries other than last-command.

clear-all-finsts

cmd clear-all-finsts

A clear-all-finsts request can be used to clear all of the finsts from the vision module. It will take no time and does not make any of the module's stages busy.

Here is the event which will show in the trace for a clear-all-finsts request.

0.485 VISION CLEAR-ALL-FINSTS

Chunks & Chunk-types

The vision module creates two general chunk types which may be used as the basis for visual features and objects:

```
(chunk-type visual-location screen-x screen-y distance kind color value height width size) (chunk-type visual-object screen-pos value status color height width)
```

Those chunk-types are used to create the following chunk-types which represent the objects available from the AGI (some of which are created outside of the vision module, but which are listed here for reference):

```
(chunk-type (text (:include visual-object)) (text t))
(chunk-type (oval (:include visual-object)) (oval t))
(chunk-type (line (:include visual-object)) (line t) end1-x end1-y end2-x end2-y)
(chunk-type (image (:include visual-object)) (image t))
(chunk-type (cursor (:include visual-object)) (cursor t))
```

It also creates these types for the requests which it accepts:

```
(chunk-type (set-visloc-default (:include visual-location)) (set-visloc-default t) type)
(chunk-type vision-command cmd)
(chunk-type (move-attention (:include vision-command)) (cmd move-attention) screen-pos scale)
(chunk-type (start-tracking (:include vision-command)) (cmd start-tracking))
(chunk-type (assign-finst (:include vision-command)) (cmd assign-finst) object location)
(chunk-type (clear-scene-change (:include vision-command)) (cmd clear-scene-change))
(chunk-type (clear-all-finsts (:include vision-command)) (cmd clear-all-finsts))
```

It creates many chunks which are used in the specification of requests, in the creation of visual objects, and for the names of the requests if they are not already chunks. All of these chunks are marked as immutable if created by the vision module:

```
(define-chunks
 (lowest name lowest)
 (highest name highest)
 (current name current)
 (current-x name current-x)
 (current-distance name current-distance)
 (current-y name current-y)
 (clockwise name clockwise)
 (counterclockwise name counterclockwise)
 (external name external)
 (internal name internal)
 (text name text)
 (box name box)
 (line name line)
 (oval name oval)
 (char-primitive name char-primitive)
 (new name new)
 (find-location name find-location)
 (move-attention isa move-attention)
 (assign-finst isa assign-finst)
 (start-tracking isa start-tracking)
 (clear-scene-change isa clear-scene-change)
 (set-visloc-default isa set-visloc-default)
 (clear-all-finsts isa clear-all-finsts)
 (cursor)(mouse)(joystick1)(joystick2))
```

The module also defines a chunk-type and a set of chunks to name colors if chunks with those names do not exist, and it marks the chunks it creates as immutable:

```
(chunk-type color color)
(define-chunks
 (black color black)
 (red color red)
 (blue color blue)
 (green color green)
 (white color white)
 (magenta color magenta)
 (yellow color yellow)
 (cyan color cyan)
 (dark-green color dark-green)
 (dark-red color dark-red)
 (dark-cyan color dark-cyan)
 (dark-blue color dark-blue)
 (dark-magenta color dark-magenta)
 (dark-yellow color dark-yellow)
 (light-gray color light-gray)
 (dark-gray color dark-gray)
 (gray color gray)
(pink color pink)
 (light-blue color light-blue)
 (purple color purple)
 (brown color brown))
```

Commands & Signals

visicon-update

Signal:

visicon-update

Description:

The visicon-update signal is generated after every update to the visicon.

visual-clear

Signal:

visual-clear

Description:

The visual-clear signal is generated whenever a clear request is processed by the vision module.

installing-vision-device

Signal:

installing-vision-device device

Arguments and Values:

device ::= the device list of the device that is installed.

Description:

The installing-vision-device signal is generated whenever a new device is installed for the "vision" interface. It will have one parameter which is the device list of that device.

print-visicon

Syntax:

print-visicon -> nil

Remote command name:

print-visicon

Description:

The print-visicon command will print out a description of the features which are currently in the visicon of the current model to the command trace. Each feature will be printed on a separate line showing all of the values which may be specified in a visual-location request to find the item. All features will show the Name which represents the name of the chunk which will be copied into the visual-location buffer when the feature is found or stuffed, Att (attended) indicating whether or not it currently has a finst, Loc which represents the x, y, and z position of the item (in the screen-x, screen-y, and distance slots by default), and Size which represents the approximate area covered by the item in degrees of visual angle squared. Any other attributes which were specified for the feature will be displayed in other columns, and it is not necessary for every feature to have all of the attribues. It will always return **nil**. If there is no current model it will print out a warning instead of the visicon.

Examples:

This example represents the result after running the extras/vision-module/multi-window example task.

> (print-visicon)

```
Kind
                                                           Text Color Width Height Cursor
                Att Loc
                                          Value Size
Name
                    ( 0 0 1080)
                                   CURSOR
                                          MOUSE
VISUAL-LOCATION2 NEW
                                                1.0
                                                                                     Т
                                          "a"
VISUAL-LOCATIONO NEW (15 16 1080)
                                   TEXT
                                                0.19999999 T
                                                                       7
                                                                             10
VISUAL-LOCATION1 NEW (215 216 1080)
                                                0.19999999 T
                                                                 BLUE
                                   TEXT
                                                                             10
NIL
E> (print-visicon)
#|Warning: get-module called with no current model. |#
```

printed-visicon

Syntax:

printed-visicon -> visicon-string

Remote command name:

printed-visicon

Arguments and Values:

visicon-string ::= a string which contains the visicon information

Description:

The printed-visicon command is exactly like the print-visicon command above, except that instead of printing the visicon to the command trace it returns a string containing the output. If there is no current model a warning will be output and the string will contain a warning instead of the visicon.

Examples:

This example represents the result after running the extras/vision-module/multi-window example task.

```
> (printed-visicon)
                                                            Text Color Width Height Cursor
"Name
                                   Kind
                                           Value Size
                Att Loc
VISUAL-LOCATION2 NEW ( 0 0 1080) CURSOR MOUSE 1.0
                                                                                    Т
                                          "a"
VISUAL-LOCATIONO NEW ( 15 16 1080) TEXT
                                                0.19999999 T
                                                                RED
                                                                      7
                                                                             10
                                          "a"
VISUAL-LOCATION1 NEW (215 216 1080)
                                  TEXT
                                               0.19999999 T
                                                                BLUE
                                                                             10
E> (printed-visicon)
#|Warning: get-module called with no current model. |#
"#|Warning: No vision module found. |#"
```

remove-visual-finsts

Syntax:

remove-visual-finsts {set-new {restuff}} -> nil

Remote command name:

remove-visual-finsts

Arguments and Values:

set-new ::= a generalized boolean which specifies whether to set all visual features to the new state restuff ::= a generalized boolean which specifies whether to check for stuffing of the visual-location buffer after removing the finsts

Description:

The remove-visual-finsts command is used to have the vision module of the current model remove all of the finsts from the visual features in the visicon. If the set-new parameter is non-nil then the features will all be marked as attended new and have their onset times changed to the current time. If the set-new parameter is nil (the default value if not provided) then the features will be either attended new or attended nil based on their original onset relative to the current time. Those which have not been on the display longer than the module's visual-onset-span time will be marked as attended new and the others will be marked as attended nil. If the restuff parameter is non-nil, then it will trigger the where system to possibly stuff the visual-location buffer after resetting the finsts. If the restuff parameter is nil (the default value if not provided) then it will not attempt to stuff the visual-location buffer. The command always returns nil. If there is no current model a warning is printed.

This command is not recommended as a plausible mechanism of the vision module, but may be useful in creating some experimental situations which would require reprocessing the whole display otherwise.

Examples:

This example was generated after running the task in examples/vision-module/dynamic-object-creation and the first step of advancing the clock is done to make sure the items are not attended new by default.

```
1> (run-full-time 1)
    1.370 ----- Stopped because time limit reached
1.0
1
NIL

2> (print-visicon)
Name Att Loc Size
```

```
CHUNKO T
           ( 10 20 1080) 1.0
CHUNK1 T
           (100 20 1080) 1.0
NIL
3> (remove-visual-finsts)
4> (print-visicon)
Name Att Loc
                           Size
       - - -
                           ----
CHUNKO NIL ( 10 20 1080) 1.0
CHUNK1 NIL (100 20 1080) 1.0
NIL
5> (remove-visual-finsts t)
NIL
6> (print-visicon)
Name Att Loc
                           Size
CHUNKO NEW (10 20 1080) 1.0
CHUNK1 NEW (100 20 1080) 1.0
NIL
7> (buffer-chunk visual-location)
VISUAL-LOCATION: NIL
8> (remove-visual-finsts nil t)
NIL
9> (run .01)
    1.370
            VISION
                                   SET-BUFFER-CHUNK VISUAL-LOCATION CHUNKO NIL
     1.370
            PROCEDURAL
                                   CONFLICT-RESOLUTION
     1.380
            -----
                                   Stopped because time limit reached
0.01
7
NIL
10> (print-visicon)
Name Att Loc
                         Size
-----
       --- --------
CHUNKO NEW ( 10 20 1080) 1.0
CHUNK1 NEW (100 20 1080) 1.0
NIL
E> (remove-visual-finsts)
#|Warning: get-module called with no current model. |#
#|Warning: No vision module found. Cannot remove the visual finsts. |#
NIL
```

set-visloc-default

Syntax:

Remote command name:

set-visloc-default

Arguments and Values:

Description:

Set-visloc-default is used to set the conditions which are tested in the visicon to determine if a chunk should be stuffed into the visual-location buffer for the current model. The specification is the same as for a <u>find location request</u> to the visual-location buffer. That specification is used to create a <u>chunk-spec</u> which is used with <u>find-matching-chunks</u> to test the visicon chunks at each screen update using "&" as the variable-char and then filtering the results based on any of the request parameters and/or relative slot tests (lowest or highest) which are included in the specification.

The default specification is given by:

```
(set-visloc-default screen-x lowest :attended new)
```

The command returns **t** if a new specification is set. If the specification is not valid then no change is made and **nil** is returned. If there is no current model then it prints a warning and returns **nil**.

Examples:

```
> (set-visloc-default isa visual-location screen-x lowest :attended new)
T
> (set-visloc-default-fct '(isa visual-location color blue :nearest current))
T
E> (set-visloc-default isa bad-type)
#|Warning: Element after isa in define-chunk-spec isn't a chunk-type. (ISA BAD-TYPE) |#
#|Warning: Invalid chunk specification. Default not changed. |#
NIL
E> (set-visloc-default)
#|Warning: No current model. Cannot set visloc defaults. |#
```

add-word-characters

Syntax:

add-word-characters char* -> [word-char-list | nil]

Remote command name:

add-word-characters

Arguments and Values:

char ::= a character to be added to those used in the construction of words can be a Lisp character, Lisp symbol, or a single element string

word-char-list ::= a list of all the characters which have been specified with add-word-characters. In Lisp the elements will be characters but for the remote command it will be single element strings.

Description:

The add-word-characters command can be used to adjust how the text items are divided into word based features by the default text processing mechanisms of the AGI for the current model. By default, text items are broken into separate word features as collections of sequential characters which are either all alphanumericp or all not alphanumericp. Thus, this text string "one--word" would be broken into three separate visual items "one", "--", and "word". This command allows one to specify additional characters to group with the alphanumerics. Thus, if #\- were added using this command that string would instead be processed as a single word for the visual representation.

Add-word-characters takes any number of characters to add to those grouped with the alphanumerics. If there is a current model it returns a list of all the additional characters which have been added using this command for that model. If there is no current model a warning is printed and **nil** is returned.

This command does not cause the AGI to reprocess its features. Only those items created after adding new word characters will be processed with those new characters included. Any characters added with this command are removed when the model is reset. Thus, this command should probably be included in the model's definition.

Examples:

```
1> (install-device (open-exp-window "" nil))
("vision" "exp-window" "")
2> (add-text-to-exp-window nil "splits.on*all_non-alpha+characters")
```

```
("" "TEXT-VDI-623")
3> (run .1)
    0.000
             VISION
                                    SET-BUFFER-CHUNK VISUAL-LOCATION VISUAL-LOCATIONO NIL
    0.000
             VISION
                                    visicon-update
                                    CONFLICT-RESOLUTION
    0.000
             PROCEDURAL
     0.100
                                    Stopped because time limit reached
0.1
6
NIL
4> (print-visicon)
Name
                   Att Loc
                                        Text Kind Color Width Value
                                                                                 Height Size
                                                                   "splits"
VISUAL-LOCATIONO
                   NEW
                       (322 306 1080)
                                        Τ
                                               TEXT
                                                    BLACK
                                                            42
                                                                                 10
                                                                                          1.18
                                                                   ıı jir
                       (347 306 1080)
VISUAL-LOCATION1
                   NEW
                                        Τ
                                               TEXT BLACK
                                                            7
                                                                                 10
                                                                                         0.19999999
                                                                   "on"
                        (357 306 1080)
VISUAL-LOCATION2
                   NEW
                                        Τ
                                              TEXT BLACK
                                                            14
                                                                                 10
                                                                                         0.39
                                                                   II * II
                   NEW
                        (368 306 1080)
                                              TEXT BLACK
                                                                                 10
VISUAL-LOCATION3
                                        Т
                                                            7
                                                                                         0.19999999
                        (381 306 1080)
                                                                   "all"
VISUAL-LOCATION4
                   NEW
                                              TEXT
                                                    BLACK
                                                                                 10
                                        Т
                                                            21
                                                                                         0.59
                                                                   11 11
VISUAL-LOCATION5
                   NEW
                        (396 306 1080)
                                        Т
                                               TEXT
                                                    BLACK
                                                            7
                                                                                 10
                                                                                         0.19999999
VISUAL-LOCATION6
                        (409 306 1080)
                                        Т
                                                    BLACK
                                                                   "non"
                   NEW
                                               TEXT
                                                            21
                                                                                 10
                                                                                         0.59
                                                                   11 _ 11
VISUAL-LOCATION7
                   NEW
                        (424 306 1080)
                                        Т
                                               TEXT
                                                    BLACK
                                                            7
                                                                                 10
                                                                                         0.19999999
                                                                   "alpha"
VISUAL-LOCATION8
                   NEW
                        (445 306 1080)
                                        Т
                                               TEXT
                                                    BLACK
                                                            35
                                                                                 10
                                                                                         0.97999996
                                                                   ^{11}+^{11}
VISUAL-LOCATION9
                   NEW
                        (466 306 1080)
                                        Т
                                               TEXT
                                                    BLACK
                                                            7
                                                                                 10
                                                                                         0.19999999
                        (504 306 1080)
                                                                   "characters"
VISUAL-LOCATION10
                   NEW
                                        Т
                                               TEXT BLACK
                                                            70
                                                                                 10
                                                                                         1.9699999
NIL
5> (reset)
6> (add-word-characters "." #\_ '-)
(#\- #\_ #\.)
7> (install-device (open-exp-window "" nil))
("vision" "exp-window" "")
8> (add-text-to-exp-window nil "splits.on*all_non-alpha+characters")
("" TEXT-VDI-624")
9> (run .1)
    0.000
             VISION
                                    SET-BUFFER-CHUNK VISUAL-LOCATION VISUAL-LOCATIONO NIL
     0.000
             VISION
                                    visicon-update
     0.000
             PROCEDURAL
                                    CONFLICT-RESOLUTION
     0.100
             _ _ _ _ _ _
                                    Stopped because time limit reached
0.1
6
NIL
10> (print-visicon)
                  Att
                       Loc
                                       Text
                                             Kind Color Width
                                                                  Value
                                                                                   Height
                                                                                           Size
                                                                                   -----
                  ---
                       -----
                                       ----
                                             ----
                                                    ----
                                                           ____
                                                                  -----
                                                                                            -----
                                       Τ
                                              TEXT
                                                                  "splits.on"
VISUAL-LOCATIONO NEW
                       (333 306 1080)
                                                    BLACK
                                                           63
                                                                                   10
                                                                                            1.77
                       (368 306 1080)
                                                           7
VISUAL-LOCATION1
                  NEW
                                       Т
                                              TEXT
                                                    BLACK
                                                                                   10
                                                                                           0.19999
                                                                  "all_non-alpha"
                       (417 306 1080)
                                              TEXT
                                       Τ
                                                    BLACK
VISUAL-LOCATION2
                  NEW
                                                          91
                                                                                   10
                                                                                           2.56
                                             TEXT
                                                                  "+"
                       (466 306 1080) T
                                                    BLACK 7
VISUAL-LOCATION3 NEW
                                                                                   10
                                                                                           0.19999
VISUAL-LOCATION4 NEW
                       (504 306 1080) T
                                             TEXT BLACK 70
                                                                  "characters"
                                                                                   10
                                                                                           1.96999
NIL
E> (add-word-characters)
#|Warning: get-module called with no current model. |#
#|Warning: No vision module available could not add new word characters. |#
NIL
```

set-visual-center-point

Syntax:

set-visual-center-point $x y \rightarrow [\log | \text{nil}]$

Remote command name:

set-visual-center-point

Arguments and Values:

```
x := a number indicating the x coordinate of the reference point y := a number indicating the y coordinate of the reference point loc := (x \ y)
```

Description:

The set-visual-center-point command is used to specify the center point used for the current model when determining the nearest location for a request that specifies :nearest as **clockwise** or **counterclockwise** and which does not also specify a center with the :center request parameter. The x and y values provided must be numbers and they specify the coordinates of the center to use. The default center point is 0,0 if this command is not used. If x and y are both numbers then that point is used as the center and a list of those values is returned. If either x or y is not a number or if there is no current model then a warning is printed and **nil** is returned.

Examples:

```
> (set-visual-center-point 100 75)
(100 75)

E> (set-visual-center-point 10 :not-a-number)
#|Warning: X and Y values must be numbers for set-visual-center-point. |#
NIL

E> (set-visual-center-point 10 40)
#|Warning: get-module called with no current model. |#
#|Warning: No vision module available so cannot set center point. |#
NIL
```

attend-visual-coordinates

Syntax:

attend-visual-coordinates $x y \{z\} \rightarrow [t \mid nil]$

Remote command name:

attend-visual-coordinates

Arguments and Values:

```
x ::= a number indicating the current x position of visual attentiony ::= a number indicating the current y position of visual attentionz ::= a number indicating the current z position of visual attention
```

Description:

The attend-visual-coordinates command is used to set the current model's location of visual attention. If the two or three values provided are all numbers then the model's visual attention point will be set to those coordinates and **t** will be returned. If no z position is provided the current <u>:viewing-distance</u> value will be used.

If there is no current model, or a non-numeric position is provided then this command will print a warning and return **nil**.

Note, this is not performed as a request by the module and is intended for setting the initial position of visual attention. It should not be used while the model is running or if the model has stopped running but any visual action is still in progress.

Examples:

Only examples of the warning messages are shown here. For actual examples of using the command see the examples/vision-module directory of the distribution.

```
E> (attend-visual-coordinates 50 50)
#|Warning: get-module called with no current model. |#
#|Warning: No vision module found. Cannot set visual coordinates. |#
NIL

E> (attend-visual-coordinates "x" 50)
#|Warning: Invalid position value in call to attend-visual-coordinates: "x" 50 NIL |#
NIL
```

schedule-encoding-complete

Syntax:

schedule-encoding-complete delay -> nil

Remote command name:

schedule-encoding-complete

Arguments and Values:

delay ::= a number indicating the time in seconds after which to execute the encoding-complete action

Description:

The schedule-encoding-complete command can be used when the <u>:visual-encoding-hook</u> parameter is set to a command and that command returns a value which suspended the normal scheduling of the encoding-complete event after a <u>move-attention request</u>. It will schedule that event to occur for the vision module of the current model based on the parameters of the last move-attention request after the provided number of seconds have passed. It always returns **nil**. If there is no current model or there has not been a suspended move-attention request for the current model then a warning is printed and no event is scheduled. If the delay provided is not a non-negative number then a warning is printed and the event will be scheduled with a delay of 0.

Examples:

```
> (schedule-encoding-complete .1)
NIL

E> (schedule-encoding-complete -1)
#|Warning: get-module called with no current model. |#
NIL

E> (schedule-encoding-complete -1)
#|Warning: Invalid delay time passed to schedule-encoding-complete -1. Using 0 instead. |#
NIL

E> (schedule-encoding-complete .1)
#|Warning: Schedule-encoding-complete called but there are no attention parameters available. |#
NIL
```

chunk-to-visual-position

Syntax:

chunk-to-visual-position chunk -> [(x,y,z), nil]

Remote command name:

chunk-to-visual-position

Arguments and Values:

```
chunk ::= the name of a chunk representing a visual location or visual object x ::= a number indicating the x position of the chunk
```

```
y ::= a number indicating the y position of the chunkz ::= a number indicating the z position of the chunk
```

Description:

The chunk-to-visual-position command can be used to get the position information from a chunk which represents a visual location or a visual object. If the value provided names a chunk in the current model and that chunk contains visual location slots the values of those slots are returned in a list ordered x, y, z. If the value provided names a chunk in the current model, that chunk has a slot named screen-pos, and that slot's value is a chunk with visual location slots then the values of those slots are returned in a list ordered x, y, z. For any other situation it will return **nil**.

Examples:

This example assumes the examples/vision-module/new-visicon-features-position-slots example task has been run which results in these visual chunks having been created:

```
CHUNK2-0
  VALUE T
  SIZE 1.0
  POS-1 50
  POS-2 15
  POS-3 1080
CHUNK4-0
   SCREEN-POS CHUNK2-0
   VALUE T
CHUNK1-0
  SIZE 1.0
  X 10
     15
   Z 1080
VISUAL-OBJECT0-0
   SCREEN-POS CHUNK1-0
> (chunk-to-visual-position 'chunk2-0)
(50 15 1080)
> (chunk-to-visual-position 'chunk4-0)
(50 15 1080)
> (chunk-to-visual-position 'chunk1-0)
(10 15 1080)
> (chunk-to-visual-position 'visual-object0-0)
(10 15 1080)
> (chunk-to-visual-position 'free)
E> (chunk-to-visual-position 'chunk1-0)
#|Warning: chunk-to-visual-position requires a current model. |#
```

Audio module

The audio module provides a model with rudimentary audio perception abilities and is very similar to the <u>vision module</u>. It has both a what and where system and two buffers which accept requests. It has a store of audio events called the *audicon*, and those are transformed into chunks which the model can use by requesting an attention shift to a particular event.

Auditory world

The sounds which the model hears are simulated using the commands described later, and there are no devices associated with the audio module. There are commands for generating pure tones, spoken digits, spoken words, and a general command which allows one to specify all of the components of the sound directly. In addition, the model will also hear its own speech which it generates using the speech module.

Sound events occur over time and are not immediately available for processing in the audicon. There are several attributes to a sound event which describe it and control the timing of the model's access to the sound.

- Onset: The time at which the sound began.
- Duration: The amount of time that the sound is present.
- Content delay: The amount of time between a sound's onset and when the content of the sound is accessible to the auditory system. No information can be extracted before this time has passed.
- Recode time: The amount of time (after the content is available) that it takes for the auditory system to construct a representation of the sound.
- Content: The value which will be made available to the model once the sound is attended.
- Kind: The basic description of the type of sound. The given commands create kinds of tone,
 digit, word, and speech.
- Location: An indication of where the sound originated. The built-in options are **external** for sounds generated by the simulated sound commands, **self** for words the model speaks, and **internal** for words the model subvocalizes. Other values may be provided when creating custom sounds with the commands described below.

The sound events are only available in the audicon for a short time before they decay. After a sound event ends and the <u>decay time</u> elapses, the sound event is removed from the audicon.

The Where System

The where system takes requests through the aural-location buffer. A request to the aural-location buffer specifies a set of constraints to test against the detectable events in the audicon. If there is a sound event in the audicon that meets those constraints, then a chunk representing that sound event is placed in the aural-location buffer. If multiple objects meet the constraints, then one will be picked randomly. If there are no sound events which meet the constraints, then the buffer will be left empty and the state error query to the aural-location buffer will be true and the buffer's failure flag will be set.

Like the vision and declarative modules, the audio module maintains a set of finsts which mark items that have been attended, and the attended status of an audio event can be a constraint in a request to the aural-location buffer. However, unlike those other modules, because the audicon is already time limited (audio events decay on their own) there is no limit on the number or duration of the auditory finsts.

The What System

The what system takes requests through the aural buffer. Its primary use is to attend to audio events which have been found using the where system. A request to the what system requires a chunk representing an audio event. In response to the request, the what system will shift aural attention to that audio event, process the sound, and place a chunk representing that sound into the aural buffer.

Like the vision module, the assumption behind the aural module is that the sound chunks placed into the aural buffer as a result of an attention operation are episodic representations of the sounds. Thus, a sound chunk with content "3" represents a memory of hearing the number "3" being spoken, not the semantic THREE used in arithmetic—a declarative retrieval would be necessary to make that mapping.

History Stream

audicon-history

The audio module provides one data history stream called audicon-history. When it is enabled it will record the information from the audicon every time it is updated. The data will be recorded based on

the time of the update, and the value recorded will be a string with the text as would be output from <u>print-audicon</u> at that time.

Parameters

:aural-encoding-hook

This parameter can be set to a command which can adjust the time that it takes for an attend-sound request to the aural buffer to finish. If a command is set for this parameter it will be called during each attend-sound request with two parameters: the name of the chunk provided as the event in the request and a boolean which indicates whether the request found a matching sound to attend (t) or not (nil). If the hook command returns nil then the normal encoding time will apply. If the command returns a number then that is used as a time in seconds for the length of the encoding process (which will be randomized if the :randomize-time parameter is enabled). Any other return value suppresses the competion of the action and the schedule-audio-encoding-complete command must be called to finish the aural attention shift. Only one command can be set on the hook at a time, and it will print a warning if a command is replaced with a different one.

:aural-loc-hook

This parameter can be used to adjust the aural-location request and aural-location buffer stuffing actions. It can be used to add a delay to the timing of the action, to force a particular matching chunk to be chosen (when there are multiple matching chunks), or to force a failure to find a chunk. It can be set to a function or valid ACT-R command. Only one hook command can be set at a time, and if a different command is set it will print a warning indicating the change. When it is set, that command will be passed three values: the list of audio-event chunks which match the request, the chunk-spec-id of the request, and a generalized boolean indicating whether this is for the stuffing of the buffer (t) or a request to the module (nil). If the command returns a number, that number will be used as the delay time (in seconds) before the buffer is set with the result. If the command returns a list of two items, the first of which is a number and the second of which is either an item from the list of matching chunks or nil then that will use the number as the delay time (in seconds) and the specified chunk will be the one placed into the buffer or a find-sound-failure will be generated if the value is nil. All other return values will result in the default operation and print a warning to indicate an invalid return value. Therefore, if a command is set and one still wants to get default behavior the command must return 0 (no delay on the action).

:digit-detect-delay

This parameter controls the content delay time given to digit sounds created with the <u>new-digit-sound</u> command. It is measured in seconds. It can be set to any non-negative value and the default is 0.3.

:digit-duration

This parameter controls the duration given to digit sounds created with the <u>new-digit-sound</u> command in seconds. It can be set to any non-negative number and the default is 0.6.

:digit-recode-delay

This parameter controls the recode time given to digit sounds created with the <u>new-digit-sound</u> command in seconds. It is also the time that it takes for a failure to encode to occur when an audio event is no longer available. It can be set to any non-negative number and the default is 0.5.

:overstuff-aural-location

This parameter controls whether the module can "stuff" a new chunk into the buffer when there is already a previously stuffed chunk in the buffer. The default value is **nil** which means that it will not overwrite a previously stuffed chunk when new information becomes available, but if it is set to **t** then it may overwrite a chunk which was stuffed into the aural-location buffer when new auditory information is available.

:sound-decay-time

This parameter controls how long sound events will stay in the audicon measured in seconds. It can be set to any non-negative number and the default is 3.0.

:tone-detect-delay

This parameter controls the content delay time given to tone sounds created with the <u>new-tone-sound</u> command in seconds. It can be set to any non-negative number and the default is 0.05.

:tone-recode-delay

This parameter controls the recode time given to tone sounds created with the <u>new-tone-sound</u> command in seconds. It can be set to any non-negative number and the default is 0.285.

:unstuff-aural-location

This parameter lets the modeler specify whether the audio module removes the chunks which it

"stuffs" into the aural-location buffer. The default value is **nil** which means that the module will not

automatically remove a chunk which has been stuffed into the aural-location buffer. If it is set to t

then if a stuffed chunk is still in the aural-location buffer and has not be modified after the :sound-

<u>decay-time</u> time has passed that chunk will be <u>erased</u> from the buffer by the audio module. If it is set

to a number then it works similar to the setting of t except that the value of this parameter specifies

the time in seconds after which the erasing occurs instead of the :sound-decay-time parameter.

Aural-location buffer

The aural-location buffer is used to access the where system of the audio module as described above.

In addition to taking requests to find sounds, the audio module will also place chunks into the aural-

location buffer automatically without a model request (a process referred to as "buffer stuffing").

Whenever there is a new sound available to the model, if the aural-location buffer is empty or the

:overstuff-aural-location parameter is t and there is a previously stuffed chunk in the aural-location

buffer, an audio-event chunk of a feature from the audicon may be placed into the aural-location

buffer. The feature which gets "stuffed" into the buffer is chosen based on preferences which can be

set by the modeler using the set-audloc-default command or by the model with a set-audloc-default request. The default preference is for any unattended item in the audicon to be stuffed into the buffer.

If the :unstuff-aural-location parameter is not **nil** then the module will also automatically remove a

stuffed chunk from the buffer if it is there past the indicated delay time.

Activation spread parameter: :aural-location-activation

Default value: 0.0

Queries

'State busy' will always be **nil.**

'State free' will always be t.

'State error' will be t if the last aural-location request failed to find a matching audio-event and it will

be **nil** in all other situations. Once it becomes **t** it will remain **t** until a new aural-location request is

made or the explicit clear request is made of the aural buffer.

381

The aural-location buffer has two additional queries that allows one to check the attended and finished status of the audio-event represented by the chunk in the aural-location buffer.

'Attended t' will be **t** if there is a chunk in the aural-location buffer and that audio-event currently has a finst on it. Otherwise it will be **nil**.

'Attended nil' will be **t** if there is a chunk in the aural-location buffer and that location does not currently have a finst on it. Otherwise it will be **nil**.

'Finished t' will be **t** if there is a chunk in the aural-location buffer and that audio-event has finished playing (its offset time has been reached or passed). Otherwise it will be **nil**.

'Finished nil' will be **t** if there is a chunk in the aural-location buffer and that audio-event has not finished playing (its offset time has not been reached yet). Otherwise it will be **nil**.

Requests

find-sound

```
{isa audio-event-chunk-type}
{{modifier} valid-slot [value | variable]}*
{:attended [t | nil]}
{:finished [t | nil]}
```

audio-event-chunk-type ::= a symbol which names a chunk-type used for audio event features modifier ::= [= | - | > | < | > =]

valid-slot ::= the name of a slot which is valid for the audio-event-chunk-type if provided or any chunk otherwise

value ::= any value, but the symbols **lowest** and **highest** have special meanings variable ::= a name which starts with the character &

A find-sound request is an attempt to find an audio event in the audicon. All of the items in the audicon are compared against the values provided in the request and if there is an item which is detectable and matches that specification an audio-event chunk describing that item is placed into the aural-location buffer. The specification given describes the properties which the item must have in order to match. If a property is not specified then its value is not considered for the matching

Any of the slots may be specified using any of the modifiers (-, <, >, <=, or >=) in much the same way one specifies a <u>retrieval request</u>. Each of the slots may be specified any number of times. In addition, there are some special tests which one can use that will be described below. All of the

constraints specified will be used to find an audio event in the audicon to be placed into the aural-location buffer. If there is no audio event in the audicon which satisfies all of the constraints then the aural-location buffer will indicate an error state and its failure flag will be set.

When the slot being tested holds a number it is also possible to use the slot modifiers <, <=, >, and >= along with specifying the value. If the value being tested or the value specified is not a number, then those tests will result in warnings and are not considered in the matching.

You can use the values **lowest** and **highest** in the specification of any slot which has a numeric value. Of the features which match the other constraints the one with the numerically lowest or highest value for that slot will then be the one found. There is one note about using **lowest** and **highest** when more than one slot is specified in that way. First, all of the non-relative values are used to determine the set of items to be tested for relative values. Then the relative tests are performed one at a time in the order provided to reduce the matching set.

An additional component of the find-sound requests is the ability to use variables to compare the particular values within a feature to each other in the same way that the LHS tests of a production use variables to match chunks. If a value for a slot in a find-sound request starts with the character & then it is considered to be a variable in the request. The request variables can be combined with the modifiers and any of the other values allowed to be used in the requests.

If the attended value is specified, that is used as a test with the auditory finsts where :attended t means that the item is currently marked with a finst (has been attended) and :attended nil means that it is not marked (has not been attended).

The finished value can be used to test whether or not the sound is still 'playing' or not. That is determined by the offset time of the sound. If the current time is greater-than or equal to the offset time of the sound then it is considered to be finished, but if the current time is less-than the offset time of the sound it is not finished.

If there is more than one item which is found as a match then a random one of those will be chosen. This request takes no time to return the resulting chunk and will show up with the following events when successful:

0.100 AUDIO FIND-SOUND

0.100 AUDIO SET-BUFFER-CHUNK AURAL-LOCATION AUDIO-EVENTO

If no sound event which matches the request is found then the buffer will be left empty and the state error query of the buffer will be true. That will result in a find-sound-failure event showing up in the trace:

```
0.050 AUDIO find-sound-failure
```

The aural-location buffer may be set to a chunk even without a request being made. If the aural-location buffer is empty and a new sound event becomes detectable an audio-event chunk which represents it may be stuffed into the aural-location buffer. This is the event which will be generated in the trace indicating a chunk being set without being requested:

```
0.060 AUDIO SET-BUFFER-CHUNK AURAL-LOCATION AUDIO-EVENTO NIL
```

If a sound event which is not yet finished is placed into the aural-location buffer it will not have values for its offset or duration slots since the sound is still playing. If that audio event is attended with a request to the aural buffer and remains in the aural-location buffer until the sound is completed then those slots will be updated to contain the appropriate values with an event that will look like this in the trace:

```
0.500 AUDIO AUDIO-EVENT-ENDED AUDIO-EVENTO
```

set-audloc-default

```
{isa audio-default-chunk-type}
set-audloc-default t
{{modifier} valid-slot [value | variable]}*
{:attended [t | nil]}
{:finished [t | nil]}
```

audio-default-chunk-type ::= a symbol which names a chunk-type used for audio event features modifier ::= [= | - | > | < | >=]

valid-slot ::= the name of a slot which is valid for the audio-default-chunk-type if provided or any chunk otherwise

value ::= any value, but the symbols **lowest** and **highest** have special meanings variable ::= a name which starts with the character &

A set-audloc-default request allows the model to change the constraints that are used when determining which (if any) chunk from the audicon will be stuffed into the aural-location buffer when an audio event becomes detectable. It works the same as the <u>set-audloc-default command</u>.

The slot values provided can be specified in the same way that they can for a find-sound request with

the only difference bein that this request requires the slot set-audloc-default be specified with a value

of **t** which is what distinguishes it from a normal find-sound request.

This request does not directly place a chunk into the aural-location buffer. It works essentially as a

delayed request – each time a new audio event becomes detectable this specification will be used to

determine if a chunk should be placed into the aural-location buffer.

It will generate an event in the trace which looks like this:

0.050 **AUDIO** SET-AUDLOC-DEFAULT

Aural buffer

The aural buffer is used to access the what system of the audio module as described above. It takes

requests to attend to audio events. It attends to the event and creates a chunk to encode it which is

placed into the aural buffer.

Activation spread parameter: :aural-activation

Default value: 0.0

Queries

'State busy' will be **t** between the time any aural request is started and the time it completes. It will be

nil otherwise.

'State free' will be **nil** between the time any aural request is started and the time it completes. It will

be t otherwise.

'State error' will be t if the last aural request failed or nil otherwise. It will not change from t to nil

until a successful request is completed – either an attend sound or a clear request will reset it.

The aural buffer can be used to query the internal states of the audio module, but this is generally not

needed since there is no benefit to doing so since the requests cannot be "pipelined" by checking for

particular subsystems being free.

385

'Preparation busy' will be **t** during the time of a clear request and its completion and during an attend sound request if the sound is not yet available (the detect time has not passed since its entry into the

audicon) and it will be **nil** otherwise.

'Preparation free' will be nil during the time of a clear request and its completion and during an

attend sound request if the sound is not yet available (the detect time has not passed since its entry

into the audicon) and it will be t otherwise.

'Processor busy' will always be nil.

'Processor free' will always be t.

'Execution busy' will be t between the start and end of an attend sound request. It will be nil

otherwise.

'Execution free' will be nil between the start and end of an attend sound request. It will be t

otherwise.

'Last-command' command should be a symbol which corresponds to one of the audio

module's requests for either buffer, or the symbol none. The query will be **t** if that is the name of the

last request received by the audio module otherwise it will be nil. Note that it is requests to the

module in general which are tested, not just requests to the aural buffer. The possible command

value are find-sound, set-audloc-default, sound, or none (representing that there has been no requests

made since the module was last cleared).

Requests

clear

[cmd clear | clear t]

A clear request can be sent to clear the error flags of both of the audio module's buffers. A clear

request will make the preparation state busy for 50ms. These events will show in the trace for a clear

request to the aural buffer:

0.485 AUDIO

CLEAR

0.535

AUDIO

CHANGE-STATE LAST NONE PREP FREE

386

Note, that after the clear request completes the last-command recorded by the module will be none and not clear – a clear request effectively clears the history of its own request as well.

attend sound

event audio-event

audio-event ::= a chunk which represents an audio event usually provided by the aural-location buffer

An attend sound request moves the audio module's attention to the sound event provided. If that sound event is still available in the audicon then it will be marked as attended and a chunk which represents that sound will be placed into the aural buffer after the sound event's recode time has passed. The resulting chunk will be constructed from the features of the audio event and any additional features specified when it was created. Its kind slot will have the same value as the audio-event that was used to attend to it. Its content slot will be set with the details of the sound. Its event slot will be the name of the original sound event chunk from the audicon, and any additional slots specified when creating the sound action will also be set.

This results in the following events being displayed in the trace showing the attention shift event with the audio-event listed, the audio-encoding-complete occurring after the sound event's recode time passes (in this case the default .285 seconds for a tone sound), and then the buffer being set to the sound chunk that encodes the visual information:

0.150	AUDIO	ATTEND-SOUND AUDIO-EVENTO
0.435	AUDIO	AUDIO-ENCODING-COMPLETE AUDIO-EVENTO
0.435	AUDIO	SET-BUFFER-CHUNK AURAL TONEO

If there is no corresponding sound available in the audicon, then the buffer is left empty, the error state is set to **t**, and the buffer's failure flag is set. This event will show that no object was found after taking the <u>amount of time required to recode a digit</u> (the time to fail is always the same regardless of the type of sound the event represents):

0.585	AUD10	ATTEND-SOUND AUDIO-EVENTO-1
1.085	AUDIO	attend-sound-failure
1.000	AUDIO	accenu-sounu-ratture

If a sound request is received while the module is currently handling another sound request, then a warning is printed and the newer request is ignored:

#|Warning: Auditory attention shift requested at 0.6 while one was already in progress. |#

The timing of the audio-encoding-complete and attend-sound-failure events for this request use the <u>randomize-time command</u>. Thus, if the <u>:randomize-time parameter</u> is set to non-nil the timing on those events will be randomized accordingly.

Chunks & Chunk-types

The audio module creates chunk-types which are used for creating and requesting audio event and attended sound chunks, and also a type for making a set-audloc-default request:

```
(chunk-type audio-event onset offset duration pitch kind location id)
(chunk-type (set-audloc-default (:include audio-event)) (set-audloc-default t))
(chunk-type sound kind content event)
```

It creates several chunks which are used in the specification of requests, in the creation of audio events, the creation of sound chunks, and for the names of the requests if they are not already chunks. All of these chunks are marked as immutable if created by the audio module:

```
(define-chunks
  (digit isa chunk)
  (speech isa chunk)
  (tone isa chunk)
  (word isa chunk)
  (highest isa chunk)
  (lowest isa chunk)
  (sound isa chunk)
  (find-sound isa chunk)
  (set-audloc-default isa chunk)
  (internal isa chunk)
  (external isa chunk)
  (self isa chunk)
  (high isa chunk)
  (middle isa chunk)
  (low isa chunk))
```

Commands & Signals

new-sound

Signal:

new-sound

Description:

The new-sound signal is generated at the onset time of every sound which is generated by one of the sound creation commands below.

new-digit-sound/new-tone-sound/new-other-sound/new-word-sound

Syntax:

```
new-digit-sound digit {onset {time-in-ms]} -> [t | nil ]
new-tone-sound freq duration {onset {time-in-ms}} -> [t | nil ]
new-word-sound word {onset {location {time-in-ms}}} -> [t | nil ]
new-other-sound content duration delay recode {onset {location {kind {time-in-ms {feature*]}}}}} -> [t | nil ]
```

Remote command names:

```
new-digit-sound
new-tone-sound
new-word-sound word {onset {'location' {time-in-ms}}
new-other-sound 'content' duration delay recode {onset {'location' {'kind' {time-in-ms {'feature'*|}}}}}
```

Arguments and Values:

```
digit ::= a number representing the digit to be heard
onset ::= a number which is the time at which the sound will begin in seconds or milliseconds
time-in-ms ::= a generalized boolean which indicates the units used for the onset
freq ::= a number representing the frequency of the tone to be heard
duration ::= a number which is the amount of time between the onset and when the sound stops in
seconds
word ::= a string which is the word (or words) which will be heard
location ::= any value which will be the audio event's location slot value
content ::= any value which is the content for the attended sound chunk
delay ::= a number which is the content delay for the sound in seconds
recode ::= a number which is the recode time for the sound in seconds
kind ::= a value which will be used as the value for the kind slot of both chunks
feature ::= ([:evt | :sound | :both ] slot value)
slot ::= a symbol which will be used as a slot name in the chunk indicated by the feature
value::= a value which will be used as the value for the corresponding slot
```

Description:

The new-*-sound commands are used to create new sound events for the audicon of the current model. A newly created audio event will be placed into the audicon at the onset time of the sound event with the other properties of that audio event being set based on which command was used to create it. If the time-in-ms parameter is specified as non-nil then a provided onset time is measured in milliseconds, and if it is not provided or nil the provided onset time will be measured in seconds. Here is how those values are set based on the command:

new-digit-sound

Onset: as provided or the current time if not provided

Duration: set using <u>randomize-time</u> on the value of <u>:digit-duration</u>

Content delay: set using <u>randomize-time</u> on the value of <u>:digit-detect-delay</u>

Recode time: the value of :digit-recode-delay

Content: the provided digit

Kind: digit

Location: external

new-tone-sound

Onset: as provided or the current time if not provided

Duration: as provided

Content delay: set set using <u>randomize-time</u> on the value of <u>:tone-detect-delay</u>

Recode time: the value of :tone-recode-delay

Content: the provided frequency

Kind: tone

Location: external

new-word-sound

Onset: as provided or the current time if not provided

Duration: computed using the get-articulation-time command of the speech module

Content delay: set using <u>randomize-time</u> on the value of <u>:digit-detect-delay</u>

Recode time: the maximum between the duration/2 and the duration - .15 seconds

Content: the provided string

Kind: word

Location: as provided, or external if not provided

new-other-sound

Onset: as provided or the current time if not provided

Duration: as provided Content delay: as provided Recode time: as provided Content: as provided

Kind: as provided, or **speech** if not provided Location: as provided, or **external** if not provided

Other slots: the event and/or sound chunk will have additional slots set as provided

Each new sound will generate a maintenance event which will not be shown in the trace. It will have an action of stuff-sound-buffer and no parameters. It will occur at the time the sound event becomes detectable, and this is where the testing is done to determine whether or not a new sound should be stuffed into the aural-location buffer.

Each new sound will also generate a new-sound signal at its onset time.

If a sound is successfully created and added to the audicon of the model then **t** is returned. If there is no current model or an invalid parameter is provided a warning will be displayed and **nil** will be returned.

Examples:

```
> (new-tone-sound 400 .75)
T
> (new-tone-sound 400 .5 1000 t)
T
> (new-digit-sound 6 1.0)
T
> (new-word-sound "Hello" .25 'left)
T
> (new-other-sound 'new-content .5 .2 .15 (mp-time) 'external 'other nil '(:both value t) '(:evt volume large))
T

E> (new-tone-sound 100 .5 'not-a-time)
#|Warning: Onset must be a number. No new tone sound created. |#
NIL
E> (new-tone-sound 'high .2)
#|Warning: Freq must be a number. No new tone sound created. |#
NIL
E> (new-digit-sound 3)
#|Warning: No current model found. Cannot create a new sound. |#
NII
```

print-audicon

Syntax:

print-audicon -> nil

Remote command names:

print-audicon

Description:

The print-audicon command will print out a description of the features which are currently in the audicon of the current model to the command trace. Each feature will be printed on a separate line showing several of the default characteristics of the sound event. It will always return **nil**. If there is no current model then it will print out a warning instead.

Examples:

```
1> (new-tone-sound 400 .5)
2> (new-word-sound "Hi" 1.0 'external)
3> (print-audicon)
Sound event Att Detectable Kind
                                              location
                                   Content
                                                       onset
                                                                offset Sound ID
AUDIO-EVENTO NIL NIL
                            TONE
                                   400
                                              EXTERNAL 0
                                                                 500 TONEO
NIL
4> (run-full-time 1.0)
1.0
NIL
5> (print-audicon)
Sound event Att Detectable Kind
                                   Content
                                                                 offset Sound ID
                                              location
                                                        onset
                                   -----
                            -----
                                                        ----
                                                                -----
                                                         0
AUDIO-EVENTO NIL T
                            TONE
                                   400
                                              EXTERNAL
                                                                   500 TONEO
                                   "Hi"
AUDIO-EVENT1 NIL NIL
                            WORD
                                                        1000
                                                                  1100 WORD0
                                              EXTERNAL
NIL
E> (print-audicon)
#|Warning: get-module called with no current model. |#
#|Warning: No audio module found |#
NIL
```

printed-audicon

Syntax:

printed-audicon -> audicon-string

Remote command name:

printed-audicon

Arguments and Values:

audicon-string ::= a string which contains the audicon information

Description:

The printed-audicon command is exactly like the print-audicon command above, except that instead of printing the audicon to the command trace it returns a string containing the output. If there is no current model a warning will be output and the string will contain a warning instead of the audicon.

Examples:

```
1> (new-tone-sound 100 .5)
2> (run-full-time 1)
1.0
22
NIL
3> (printed-audicon)
"Sound event Att Detectable Kind Content
                                              location
                                                         onset
                                                                 offset Sound ID
            --- ------
                                                         ----
AUDIO-EVENTO T
               Т
                          TONE 100
                                              EXTERNAL
                                                                    500 TONEO
4> (printed-audicon)
#|Warning: get-module called with no current model. |#
"#|Warning: No audio module found|#"
```

set-audloc-default

Syntax:

Remote command name:

```
set-audloc-default ' {isa chunk-type} {{modifier} slot [value | variable]}* {:attended [t | nil]} '
```

Arguments and Values:

```
chunk-type ::= the name of a chunk-type modifier ::= [=|-|>|<|>=|<=] slot ::= the name of a slot which must be valid for chunk-type if it is specified value ::= any value variable ::= a name which starts with the character &
```

Description:

The set-audloc-default command is used to set the specification used when testing the items in the audicon to determine if an audio event chunk should be stuffed into the aural-location buffer for the current model. The parameters provided are used to create a <u>chunk-spec</u> that will be tested against the set of chunks in the audicon using <u>find-matching-chunks</u> after it has been filtered for attended and/or finished items. The default specification is set with:

```
(set-audloc-default :attended nil)
```

The command returns **t** if a new specification is set. If there is no current model then it prints a warning and returns **nil**. If the parameters provided do not properly represent a valid chunk-spec then no changes are made to the current default spec and **nil** is returned.

Examples:

```
> (set-audloc-default isa audio-event onset lowest kind tone)
T
> (set-audloc-default-fct (list '- 'location 'self))
T

E> (set-audloc-default isa sound slot)
#|Warning: Chunks extended with slot SLOT during a chunk-spec definition. |#
#|Warning: Invalid specs in call to define-chunk-spec - not enough arguments |#
#|Warning: Invalid chunk specification. Default audloc not changed. |#
NIL

E> (set-audloc-default :attended t :attended nil)
#|Warning: The :attended and :finished specification for set-audloc-default can only be specified at most once. |#
#|Warning: Audloc defaults not changed. |#
NIL

E> (set-audloc-default)
#|Warning: No current model. Cannot set audloc defaults. |#
NIL
```

schedule-audio-encoding-complete

Syntax:

schedule-audio-encoding-complete delay -> nil

Remote command name:

schedule-audio-encoding-complete

Arguments and Values:

delay ::= a number indicating the time in seconds before finishing the current aural attention shift

Description:

The schedule-audio-encoding-complete command can be used when the <u>:aural-encoding-hook</u> parameter is set to a command and that command returns a value which suspended the normal scheduling of the completion of the attention shift in response to an <u>attend sound request</u>. It will schedule the completion event (either audio-encoding-complete if successful or attend-sound-failure if not) to occur for the audio module of the current model based on the last attend sound request after

the provided number of seconds have passed. It always returns **nil**. If there is no current model or there has not been a suspended attend sound request for the current model then a warning is printed and no event is scheduled. If the delay provided is not a non-negative number then a warning is printed and the event will be scheduled with a delay of 0.

Examples:

```
> (schedule-audio-encoding-complete .1)
NIL

E> (schedule-audio-encoding-complete .1)
#|Warning: Schedule-audio-encoding-complete called but there is no pending attend-sound action. |#
NIL

E> (schedule-audio-encoding-complete .1)
#|Warning: get-module called with no current model. |#
NIL

E> (schedule-encoding-complete -1)
#|Warning: Invalid delay time passed to schedule-encoding-complete -1. Using 0 instead. |#
NIL
```

Motor module

The motor module functions as a model's hands. It is conceptually based on EPIC's Manual Motor Processor (Kieras & Meyer, 1996) and is quite similar in many respects. It provides a model with the ability to operate virtual keyboard and mouse devices by default, but it is possible to extend the actions and devices with which the model can interact. It has one buffer through which it accepts requests and it does not generate any chunks in response. There is currently no learning mechanism built into the motor module.

Physical world

The model's hands are represented as existing in a horizontal plane in front of the model (like a desktop) on which devices can be placed, and at any time each hand will be associated with at most one device. Because a keyboard was the first device created for a model to use, that plane is represented as a grid of square cells 3/4" (~19mm) on a side (the standard key spacing for full size computer keyboards) with the origin located where the upper left key of a keyboard (typically the Esc key) would be located for normal use. Each of the model's fingers will be located in a cell of that space, and the position of the model's hands are considered to be the same as the position of the corresponding index finger. The default positions for the hands are the left hand fingers in cells 1,4 through 4,4 with the thumb at 5,6 and the right hand fingers in cells 7,4 through 10,4 with the thumb at 6,6 (which corresponds to the home row positions for touch typing if the provided keyboard device is installed).

Operation

In general, movement requests require specification of a movement type, called a style (which is specified by the cmd slot of the request) and one or more parameters, such as the hand or finger that is to make the movement. The motor module includes several movement styles based on EPIC's Motor Processor. They are:

- Punch. This is a simple downstroke followed by an upstroke of a finger (pressing a key or button located directly beneath the finger).
- Peck. This is a directed movement of a finger to a location followed by a keystroke, all as one continuous movement.
- Peck-recoil. Same as "peck" above, but the finger moves back to the location at which it started its movement.
- Ply. Moving a device to a given location in space or to control the position of an associated object e.g. the cursor on the screen by using the mouse.
- Hand-ply. Moves a hand to a new location in space e.g. from the keyboard to the mouse.

Those movement styles can be executed directly through requests, but typically one will use higher level actions provided by a device that are built upon those low level styles.

The motor module does not place any chunks into its buffer in response to requests. The buffer should always be empty, and it is the state of the module that is important to the model. <u>As described above for all the perceptual and motor modules</u>, the motor module has three internal states: preparation, processor, and execution. When a request is received by the motor module, it goes through three phases: preparation, initiation, and execution each of which depends upon a different combination of those internal states being available.

In the preparation phase, it builds a list of "features" which guide the actual movement, and it requires the use of the preparation and processor states of the module. The amount of time that preparation takes depends on the number of features that need to be prepared - the more that need to be prepared, the longer it takes. The number of features that need to be prepared depends upon two things: the complexity of the movement to be made and the difference between that movement and the previous movement (the motor module maintains a history of the last set of features that it prepared). On one end of the scale, the motor module is simply repeating the previous movement, then all the relevant features will already be prepared and do not require preparation. On the other end, a request could specify a movement that requires five features (the most for any of the included styles) which do not overlap with the features in the motor module's history, in which case all five features would need to be prepared. The movement features are organized into a hierarchy, such that a change to a feature higher in the hierarchy requires preparing all features below it again regardless of whether they match a previously prepared feature. The movement style is at the top of the hierarchy, and therefore if the movement style changes all of the features required for the movement must be prepared. The hand feature is below the style, and all actions will involve a style and hand. Below the hand is the finger feature (if needed), and then any other features for an action are considered equal and at the bottom of the hierarchy.

When feature preparation is complete, the motor module makes the specified movement. The first 50ms (by default) of the movement is the initiation. During this interval, the processor and execution states are required. Once the initiation phase begins it is not possible for the model to stop the action from completing, but until that happens it is possible for the model to terminate the action (either while it is still being prepared or while it is waiting for a prior exectuion to finish).

The execution phase requires only the execution state of the module. The amount of time that the movement takes to execute depends on the style and features of the action. Simple styles, like punch,

have a fixed execution time, but the more complex styles will have a longer execution time based on the movement necessary which is determined by Fitts's Law.

Fitts's Law

```
T = b * \log_2(D/W + 0.5)
```

T := the time of the movement in seconds

b := a scale parameter dependent on the type of action

D := the distance to the target W := the width of the target

Each state of the module may only be engaged for a single action at a time. If a request is made that requires a state that is already engaged then the motor module is said to be "jammed." When the module is jammed it will output a warning to indicate when the jamming occurred like this:

```
#|Warning: Module :MOTOR jammed at time 0.68 |#
```

When the module jams it will ignore the request that caused the jam and continue with the action that was already occurring. To avoid jamming, as with all modules, one must query the state of the module before making a request. The standard query for state free will avoid jamming the module because that is only true when all of the internal states of the module are not busy. However, it is possible to issue motor requests faster than that because the preparation and execution of an action use different internal states and the module can be preparing one action while it is executing another, and it will internally delay the execution of the second action if necessary to wait for the execution state to become free. Therefore one can have the model perform actions closer together by testing for the appropriate internal state being free, and a query for preparation free instead of state free can often be used instead to start preparing the second action as soon as possible. However, there are two situations in which one may need to be careful when attempting to chain actions together like that. The first situation occurs because the processor state is used by both preparation and execution of an action. Therefore, technically one should query that both preparation and processor are free before starting the next action, but because the default initiation time is the same as the default production firing time the preparation free test in a production is sufficient since the processor will be free by the time the production fires if the preparation free query is successful. If however one has enabled the noise for the timing of production firings and/or motor actions or changed the timing for either such that a production can take less time than the initiation phase of an action, then both preparation free and processor free queries would be required because it would not be guaranteed that the processor

would become free while the production is firing. The other situation occurs when the preparation of the features for the second action depend upon the execution of the first action. That happens if the actions are both movements of the same hand/finger since the features to prepare for the movement depend upon the current position of the item, and if it has not yet completed its move to a new position then the features for the second move will be determined from the wrong starting point. Thus, when two sequential movements are being performed it is best to check that the previous execution has completed and the state free test should be used (since that includes both execution and preparation being free).

Another option for quickly performing actions is to have the module prepare features without executing them. If all of the features for an action are prepared in advance then an execute request can be made to perform that action. Alternatively, one can prepare just a subset of the features needed so that when the action is performed it has a lower preparation cost (which could be useful in the case of a decision task where the model knows it will be punching a finger on the right hand, but doesn't know which one so it could prepare the style and hand features in advance).


Interface & Devices

The motor module has an interface called "motor" which can be used to install any number of devices. When a hand is using a device that device will be notified with the details of any actions which that hand performs, which could be the default action styles or extended actions which have been created.

There are two devices included for use with the motor module: a keyboard device called "keyboard" and a device for moving the virtual mouse cursor using a few different input devices (mouse, first order joystick, and second order joystick) which is called "cursor". None of those devices are installed by default, but if the "exp-window" device of the AGI is installed for the vision interface it will automatically install keyboard and mouse cursor devices for the motor interface if they are not already installed.

Keyboard

This is the layout of the keyboard device for the model:



The device extends the actions which the model can perform to include those for moving the hands to the keyboard, moving the hands on the keyboard, and a command for touch typing keys by name. The requests for those actions and associated modeler commands will be described with the default motor module requests and commands.

There are no details necessary when installing a keyboard device, and only one keyboard device should be installed for the motor interface at a time (technically one could install more than one by providing different details which will be ignored, but that is not recommended).

When the keyboard is notified that a motor action has occurred which will press a key it will generate an output-key signal with two parameters. The first parameter is the name of the model which performed the action and the second is the name of the key which was pressed. That signal can be monitored to detect and record models keyboard responses.

Cursor

The cursor device controls a virtual cursor and multiple virtual cursors (each of which is independent of the others) may be installed. There are three provided types of cursor input devices: a mouse, a first order joystick, and a second order joystick. The particular input device is specified as the details of the cursor device being installed and the values for those are "mouse", "joystick1", and "joystick2" respectively. All three input devices are located to the right of the default keyboard position at fixed coordinates: 28,2, 28,0, and 28,4 respectively (a simplifying assumption that ignores any movement that is made with the device).

The cursor device extends the actions which the model can perform to include those for moving the virtual cursor to a visual location or visual object, moving the right hand to a cursor device, and

clicking the primary mouse cursor button with the index finger. The requests for those actions and associated modeler commands will be described with the default motor module requests and commands.

When a cursor is notified that a model's motor action has occurred which affects the cursor it will generate a signal. There are three signals that are generated for the model actions with a cursor. The first is "move-cursor" which includes three parameters which are the name of the model, the details of the cursor device i.e. the name of which cursor it is, and a list of three values which are the x, y, and z coordinates to which the virtual cursor has been moved. The other two relate to the pressing of buttons on the cursor. All of the cursors assume that there is a button below each finger that activates when the finger strikes it, and that will generate a signal. For the mouse cursor a "click-mouse" signal is generated which is passed three parameters: the name of the model, a list of three values which indicate the x, y, and z coordinates of the virtual cursor at the time of the click, and the name of the finger which performed the click. For all other cursors, a "click-cursor" signal is generated which is passed four parameters: the name of the model, the name of the cursor, a list with the x, y, and z coordinates of the cursor when the click occurred, and the name of the finger which performed the click. The cursor also generates the "move-cursor" signal when the cursor is moved explicitly using the command set-cursor-position, and it will generate a signal called "delete-cursor" whenever a cursor device is uninstalled which will be passed two parameters: the name of the model and the details of the device being uninstalled.

Parameters

:cursor-noise

If this is set to **nil** (which is the default) then the cursor movements made by the model will be to the exact location requested. If it is set to **t** then there will be noise added to the location to which the cursor is moved.

:incremental-mouse-moves

When set to **t**, this will update the cursor location approximately every 50 ms when it is in motion. When set to **nil** (which is the default value) it will update the cursor location only at the end of each cursor movement. If it is set to a number then that is considered as a time in seconds between the updates and replaces the time of .05 used when it is set to **t**. The incremental positions are calculated along the line between the old and new points using a minimum jerk velocity profile.

:min-fitts-time

The minimum movement time in seconds required to perform an aimed movement (one for which the

Fitts's law timing is applied). The default value is 0.1.

:motor-burst-time

This is the minimum time required for the execution of any motor module movement in seconds.

Tthe default is .05.

:motor-feature-prep-time

The time in seconds that it takes to prepare each movement feature. The default is .05.

:motor-initiation-time

This is the length of the initiation time for motor actions in seconds. The default is .05.

:peck-fitts-coeff

The b coefficient in the Fitts's law equation for the timing of peck style movements. The default is .

075.

Manual Buffer

The motor module does not place any chunks into the manual buffer - it is only used for requests.

Almost all of the timing for the requests to the manual buffer (everything except for a clear request)

are randomized using randomize-time.

Activation spread parameter: :manual-activation

Default value: 0.0

Queries:

402

'State busy' will be **t** when any of the internal states of the module (listed below) also report as being busy. Essentially, it will be **t** while there is any request to the manual buffer that has not yet completed. It will be **nil** otherwise.

'State free' will be **t** when all of the internal states of the module (listed below) also report as being free. Essentially, it will be **t** only when all requests to the manual buffer have completed. It will be **nil** otherwise.

'State error' will always be nil.

Unlike the perceptual modules, the internal states of the motor module may be useful to track in a model because it is possible to send new requests while the module is partially busy.

'Preparation busy' will be **t** after a request has been received and until it completes the preparation of the features needed for that request which depends on how many features there are and whether or not they overlap with the last features prepared. It will be **nil** otherwise.

'Preparation free' will be **nil** after a request has been received and until it completes the preparation of the features needed for that request which depends on how many features there are and whether or not they overlap with the last features prepared. It will be **t** otherwise.

'Processor busy' will be **t** while preparation is busy and will continue to be **t** after the features have been prepared until the additional initiation time (set with the <u>:motor-initiation-time parameter</u>) has passed. It will be **nil** otherwise.

'Processor free' will be **nil** while preparation is busy and will continue to be **nil** after the features have been prepared until the additional initiation time (set with the <u>:motor-initiation-time parameter</u>) has passed. It will be **t** otherwise.

'Execution busy' will be **t** once the preparation of a request's features has completed and will remain **t** until the time necessary to complete the action has passed. It will be **nil** otherwise.

'Execution free' will be **nil** once the preparation of a request's features has completed and will remain **nil** until the time necessary to complete the action has passed. It will be **t** otherwise.

'Last-command *command*' *command* should be a symbol which corresponds to one of the manual buffer's requests or the symbol none. The query will be **t** if that is the name of the last request received by the manual buffer otherwise it will be **nil**.

Here is a summary indicating the state transitions for a single movement request assuming that the module is entirely free at the start of the request:

Preparation state	Processor state	Execution state	When
FREE	FREE	FREE	Before event arrives
BUSY	BUSY	FREE	When request is received
FREE	BUSY	BUSY	After preparation of movement
FREE	FREE	BUSY	After initiation of movement
FREE	FREE	FREE	When movement is complete

Requests

clear

[cmd clear | clear t]

A clear request can be sent to clear the history of prepared features. A clear request varies from the other requests in that it will make only make the preparation state busy for 50ms and not the processor or execution states. These events will show in the trace for a clear request to the manual buffer:

0.050	MOTOR	CLEAR	
			_
0.100	MOTOR	CHANGE-STATE LAST NONE PREP FREE	Ξ

Note, that after the clear request completes the last-command recorded by the module will be none and not clear – the clear has effectively cleared the history of its own request as well.

While this request makes the preparation state busy, unlike other requests it does not require that it be free. That makes it possible to use the clear request to terminate an action which has not yet started its execution.

punch

```
cmd punch
hand [ left | right ]
finger [ index | middle | ring | pinkie | thumb ]
```

This request will execute a punch action for the specified finger on the specified hand. This will result in sending a punch notification to the device that hand is using (if there is one). That notification contains a list of features like this indicating which hand and where the finger is located:

```
((model model-name) (style punch) (hand hand) (loc (cell-x cell-y))
```

The time to perform this action is controlled by the initiation and burst times set for the motor module, and the actual execution of the output is controlled by the <u>key closure time</u>. After the initiation time passes the finger starts to move and there is one burst time to complete the downstroke followed by another burst time to complete the upstroke. These are the actions which will be shown in the trace for a punch action indicating the request being received, the preparation of the features completing, the initiation time having passed, the actual striking of a key which is under that finger currently, and the time to finish the execution of the action (returning the finger to a position where it is ready to act again):

```
0.000 MOTOR PUNCH HAND LEFT FINGER INDEX
...
0.150 MOTOR PREPARATION-COMPLETE
...
0.200 MOTOR INITIATION-COMPLETE
...
0.210 MOTOR MOTOR-ACTION-PERFORMED
...
0.300 MOTOR FINISH-MOVEMENT
```

If the hand is interacting with a device, then the motor-action-performed event may not occur and a specific action by that device may be shown instead e.g. this result when a keyboard is installed:

```
0.210 KEYBOARD output-key PRESS-F-MODEL f

peck

cmd peck
```

hand [left | right]
finger [index | middle | ring | pinkie | thumb]
r distance
theta direction

This request will result in the model making a peck style movement with the indicated finger and hand. This will result in sending a peck notification to the device that hand is using (if there is one). That notification contains a list of features like this indicating which hand, and where the finger will be located as a result of the peck:

```
((model model-name) (style peck) (hand hand) (loc (cell-x cell-y))
```

That finger will be moved the specified distance and direction from where it currently is and then interact with the device at that location (pressing the key for a keyboard device). The finger will then remain in that location until moved elsewhere. The distance is measured in cell widths as <u>described above</u>. The direction is an angle measured in radians with 0 being movement along the x axis to the right and increasing with clockwise rotation. The time taken to execute this action is controlled by <u>Fitts's law</u> as described above using the :peck-fitts-coeff parameter (currently the key closure time is not used in the timing of the output action as with a punch). These are the events which one will see for such an action showing the progression through the stages of the motor module and performing the action (which may produce an event specific to the device associated with the hand instead of the motor-action-performed event):

0.050	MOTOR	PECK HAND LEFT FINGER INDEX R 1 THETA 0
0.300	MOTOR	PREPARATION-COMPLETE
0.350	MOTOR	INITIATION-COMPLETE
0.450	MOTOR	MOTOR-ACTION-PERFORMED
0.500	MOTOR	FINISH-MOVEMENT

There are no constraints on how far or in which direction a model's finger can move relative to the other fingers. Thus, at this time, the model may be able to make finger movements which would be impossible for a real person to make and it is up to the modeler to consider such issues.

peck-recoil

```
cmd peck-recoil
hand [ left | right ]
finger [ index | middle | ring | pinkie | thumb ]
r distance
theta direction
```

A peck-recoil is effectively the same as a <u>peck</u>, except that the finger is returned to where it started after the key has been pressed. This will result in sending a peck-recoil notification to the device that hand is using (if there is one). That notification contains a list of features like this indicating which hand, and where the finger will strike as a result of the peck-recoil:

```
((model model-name) (style peck-recoil) (hand hand) (loc (cell-x cell-y))
```

These are the events which one will see for such an action showing the progression through the stages of the motor module and performing the action (which may produce an event specific to the device associated with the hand instead of the motor-action-performed event):

```
0.050 MOTOR PECK-RECOIL HAND LEFT FINGER INDEX R 1 THETA 0
...
0.300 MOTOR PREPARATION-COMPLETE
...
0.350 MOTOR INITIATION-COMPLETE
...
0.450 MOTOR MOTOR MOTOR-ACTION-PERFORMED
...
0.600 MOTOR FINISH-MOVEMENT
```

There are no constraints on how far or in which direction a model's finger can move relative to the other fingers. Thus, at this time, the model may be able to make finger movements which would be impossible for a real person to make and it is up to the modeler to consider such issues.

press-key

cmd press-key key *key*

The press-key request is essentially a programming convenience for modeling typing provided by the keyboard device. It assumes that the model's hands are in the home position or that the right hand is on the keypad and translates the specified key into either a punch or a peck-recoil request as needed to press that key with the appropriate finger from the home position. The key can be specified using either a symbol or string that specifies the name of a key on the keyboard. The names for keys on the <u>default keyboard</u> fall into the following categories:

- Alpha-numeric keys (a-z and 0-9) can be specified with a single character.
- Punctuation keys should be provided in strings or specified with a name (space, backquote, tab, comma, period, semicolon, slash, hyphen, quote, left-bracket, right-bracket, or backslash) to avoid potential syntax problems.
- The function keys are named f1 f15.

- The other keys in the primary key section are named: escape, equal, delete, caps-lock, return (or newline), left-shift (or shift), right-shift, left-control (or control), left-option (or option), left-command (or command), right-command, right-option, and right-control.
- The keys on the keypad area are named: clear, keypad-=, keypad-/, keypad-*, keypad-7, keypad-8, keypad-9, keypad-minus, keypad-4, keypad-5, keypad-6, keypad-plus, keypad-1, keypad-2, keypad-3, keypad-0, keypad-period, and enter.

This request does not represent an ACT-R theory of typing. It only provides a convenience for modeling a moderately skilled touch typist. An ideal theory of typing would be based on a model learning how to type - the model would have to look at the keyboard to determine where each key is, then acquire chunks that encode which keys map to which locations, through practice it would learn specific productions that handle these, and would also involve learning in the motor system itself.

Here are the events which will show in the trace for a press-key request indicating the key that was specified, the progression through the stages of the action, and showing the keyboard response indicating the model name and key:

```
0.050 MOTOR PRESS-KEY KEY F
...
0.200 MOTOR PREPARATION-COMPLETE
...
0.250 MOTOR INITIATION-COMPLETE
...
0.260 KEYBOARD output-key PRESS-KEY-MODEL f
...
0.350 MOTOR FINISH-MOVEMENT
```

If the model's hands are using the keyboard device but are not in the appropriate location for the request (either the home row or the keypad depending on the key), then the model will strike the wrong key since the action is generated based on the key, not the current hand positions.

If an invalid key is specified then a warning is printed and no action is taken:

```
0.050 MOTOR PRESS-KEY BAD-KEY #|Warning: No press-key mapping available for key "BAD-KEY". |#
```

If the keyboard device is not installed for the model or its hands are not interacting with that device then a warning is printed and no action is taken:

```
0.050 MOTOR PRESS-KEY KEY R
#|Warning: No keyboard device installed for motor module. Press-key action ignored. |#

Or
```

 $\#|\mbox{Warning: The RIGHT hand in a press-key action is not on the keyboard. Press-key action ignored. <math display="inline">|\#$

move-cursor

```
cmd move-cursor
[ object object | loc location ]
{hand [ left | right]}
```

This request will result in a ply style movement of the model's hand if it is currently interacting with a cursor device. That ply will move the cursor device associated with the indicated hand (the right hand is the default if not provided) to the specified object (which must be a chunk which represents a visual object) or location (which must be a chunk which represents a visual location) taking time based on <u>Fitts's Law</u>. Note that the actual location of the cursor device itself does not change, only the position of the cursor which it is controlling.

If the <u>:cursor-noise parameter</u> is **nil** then the cursor will be positioned exactly at the coordinates provided by the location or object provided. If :cursor-noise is **t** then a very simplified noise component is added to the target point to determine where the cursor is moved. An offset distance is computed using the effective width of the target – it's width along the vector of approach as used in the Fitts's Law calculation. The offset is computed using the <u>act-r-noise command</u> with an s value that results in it being on the object (along the approach vector) 96% of the time. That offset is applied in a random direction from the target chosen from a uniform distribution.

Here are the events which show for a move-cursor action showing the module progressing through the internal states and a mouse cursor device indicating the final position of the cursor:

```
0.050 MOTOR MOVE-CURSOR LOC X
...
0.250 MOTOR PREPARATION-COMPLETE
...
0.300 MOTOR INITIATION-COMPLETE
...
0.466 MOUSE move-cursor FOO mouse (30 40 1080)
...
0.516 MOTOR FINISH-MOVEMENT
```

If the <u>:incremental-mouse-moves parameter</u> is specified as **t**, then there may be multiple smaller mouse movements leading up to the final position which are spaced approximately 50 ms apart:

0.050	MOTOR	MOVE-CURSOR LOC X
• • •		
0.250	MOTOR	PREPARATION-COMPLETE

```
0.300
        MOTOR
                                INITIATION-COMPLETE
0.300
        MOUSE
                                move-cursor F00 mouse (2 3 1080)
                                move-cursor F00 mouse (13 18 1080)
0.350
        MOUSE
                                move-cursor F00 mouse (25 33 1080)
        MOUSE
0.400
                                move-cursor F00 mouse (30 40 1080)
0.466
        MOUSE
                               FINISH-MOVEMENT
0.516
        MOTOR
```

If the model's hand is not on a cursor device a warning is printed and no action is taken:

```
#|Warning: Hand is not on a cursor device in request to move-cursor. |#
```

The move-cursor action assumes movement in only the x,y plane. If a movement includes a change in the z dimension a warning will be printed to indicate that. It will still move the cursor to the indicated position, but the timing will based on a movement that only occurred in two dimensions i.e. it ignores the z distance traveled and the target width is only measured along the x,y plane:

```
MOVE-CURSOR LOC X
     0.050
             MOTOR
#|Warning: Move-cursor request has different z coordinates for start (0 0 1080) and target
(30 40 10) locations, but motor module assumes a cursor moves in only two dimensions. |#
     0.250
             MOTOR
                                    PREPARATION-COMPLETE
             MOTOR
    0.300
                                    INITIATION-COMPLETE
             MOUSE
                                    move-cursor FOO mouse (30 40 10)
    0.466
     0.516
             MOTOR
                                    FINISH-MOVEMENT
```

If the target position is the same as the current cursor position then a warning is printed and no action is performed:

```
0.050 MOTOR MOVE-CURSOR LOC X #|Warning: Move-cursor action aborted because cursor is at requested target X |#
```

click-mouse

cmd click-mouse

If the model's right hand is located on a virtual mouse cursor, then this request will result in a <u>punch</u> action by the right index finger pressing the primary mouse button. These are the events which one will see for such an action showing the progression through the stages of the motor module and the indication from the mouse cursor that a press occurred which indicates the name of the model, the location of the mouse cursor, and which finger (although there are not separate requests for other

mouse buttons a punch action on any finger while the hand is on the mouse will generate a click-mouse event for that finger):

0.050	MOTOR	CLICK-MOUSE
0.200	MOTOR	PREPARATION-COMPLETE
0.250	MOTOR	INITIATION-COMPLETE
0.260	MOUSE	click-mouse FOO (0 0 1080) INDEX
0.350	MOTOR	FINISH-MOVEMENT

If the model's right hand is not on the virtual mouse then a warning will be printed and no action taken:

```
#|Warning: CLICK-MOUSE requested when hand not at mouse! |#
```

hand-to-mouse

cmd hand-to-mouse

The hand-to-mouse request will move the model's right hand from where ever it is to the default location for the virtual mouse cursor using a hand-ply style movement (the default location for the mouse device is at (28 2) and it has an effective width of 4). These are the events which will show the action progressing through the stages of a motor action along with the final movement indicating the distance and direction the right hand moved:

0.050	MOTOR	HAND-TO-MOUSE
0.250	MOTOR	PREPARATION-COMPLETE
0.300	MOTOR	INITIATION-COMPLETE
0.553	MOTOR	MOVE-A-HAND RIGHT 21.095022 -0.094951704
0.603	MOTOR	FINISH-MOVEMENT

If the model's hand is already on the virtual mouse it will acknowledge the request, but no actions are taken and the module does not become busy. There will only be the one acknowledgement event in the trace:

```
0.050 MOTOR HAND-TO-MOUSE
```

hand-to-joystick1

cmd hand-to-joystick1

The hand-to-joystick1 request will move the model's right hand from where ever it is to the default location for the virtual first order joystick cursor using a hand-ply style movement (the default location for the joystick1 device is at (28 0) and it has an effective width of 4). These are the events which will show the action progressing through the stages of a motor action along with the final movement indicating the distance and direction the right hand moved:

0.050	MOTOR	HAND-TO-JOYSTICK1
0.250	MOTOR	PREPARATION-COMPLETE
0.300	MOTOR	INITIATION-COMPLETE
0.555	MOTOR	MOVE-A-HAND RIGHT 21.377558 -0.1882215
0.605	MOTOR	FINISH-MOVEMENT

If the model's hand is already on the virtual mouse it will acknowledge the request, but no actions are taken and the module does not become busy. There will only be the one acknowledgement event in the trace:

0.050 MOTOR HAND-TO-JOYSTICK1

hand-to-joystick2

cmd hand-to-joystick2

The hand-to-joystick2 request will move the model's right hand from where ever it is to the default location for the virtual second order joystick cursor using a hand-ply style movement (the default location for the joystick1 device is at (28 4) and it has an effective width of 4). These are the events which will show the action progressing through the stages of a motor action along with the final movement indicating the distance and direction the right hand moved:

0.050	MOTOR	HAND-TO-JOYSTICK2
0.250	MOTOR	PREPARATION-COMPLETE
0.300	MOTOR	INITIATION-COMPLETE
0.552	MOTOR	MOVE-A-HAND RIGHT 21.0 0.0
0.602	MOTOR	FINISH-MOVEMENT

If the model's hand is already on the virtual mouse it will acknowledge the request, but no actions are taken and the module does not become busy. There will only be the one acknowledgement event in the trace:

```
0.050 MOTOR HAND-TO-JOYSTICK2
```

hand-to-home

cmd hand-to-home

The hand-to-home request will move the model's right hand from where ever it is to the home position on the virtual keyboard using a hand-ply style movement (the target location for the home position is (7 4) with a width of 4) and position all of the fingers over the appropriate keys. These are the events which will show the action progressing through the stages of a motor action along with the final movement indicating the distance and direction the hand moved:

0.050	MOTOR	HAND-TO-HOME
0.250	MOTOR	PREPARATION-COMPLETE
0.300	MOTOR	INITIATION-COMPLETE
0.553	MOTOR	MOVE-A-HAND RIGHT 21.095022 3.0466409
0.603	MOTOR	FINISH-MOVEMENT

Even if the model's hand is already at the home location it will still progress through all of the stages of the movement to move the hand:

0.000	MOTOR	HAND-TO-HOME
0.200	MOTOR	PREPARATION-COMPLETE
0.250	MOTOR	INITIATION-COMPLETE
0.350	MOTOR	MOVE-A-HAND RIGHT 0.0 0.0
0.400	MOTOR	FINISH-MOVEMENT

hand-to-keypad

cmd hand-to-keypad

The hand-to-keypad request will move the model's right hand from where ever it is to the keypad on the virtual keyboard using a hand-ply style movement (the target location for the keypad position is (19 4)) and position the fingers over the keys 4, 5, 6, and enter with the thumb over 0. These are the

events which will show the action progressing through the stages of a motor action along with the final movement indicating the distance and direction the hand moved:

0.050	MOTOR	HAND-TO-KEYPAD
0.250	MOTOR	PREPARATION-COMPLETE
0.300	MOTOR	INITIATION-COMPLETE
0.481	MOTOR	MOVE-A-HAND RIGHT 12.0 0.0
0.531	MOTOR	FINISH-MOVEMENT

Even if the model's hand is already at the keypad location it will still progress through all of the stages of the movement to move the hand:

```
0.050 MOTOR HAND-TO-KEYPAD
...
0.250 MOTOR PREPARATION-COMPLETE
...
0.300 MOTOR INITIATION-COMPLETE
...
0.400 MOTOR MOVE-A-HAND RIGHT 0.0 0.0
...
0.450 MOTOR FINISH-MOVEMENT
```

point-hand-at-key

```
cmd point-hand-at-key
hand [ left | right ]
to-key key
{offsets [ standard | (finger-offset*)]}
```

```
key ::= either a symbol or string that specifies the key to which the hand should move finger-offset ::= (finger-name x y) finger-name ::= [ index | middle | ring | pinkie | thumb ] x ::= an integer indicating the x coordinate offset for the finger from the position of the hand y ::= an integer indicating the y coordinate offset for the finger from the position of the hand
```

This request will move the hand on the virtual keyboard causing all of the fingers to be repositioned using a hand-ply style movement. The hand will be positioned at the coordinate of the specified key for the installed keyboard device. If the offsets slot is not specified then the fingers will have the same offset from the hand position as they had before it was moved (any previous peck actions will still be reflected in the new positions). If the offsets value is specifed as standard then the index finger of the specified hand will be positioned over the indicated key and the other fingers will be positioned on the keys in the same relative positions as they would be on the home row. If specific finger offsets

are provided then those fingers will be over the keys at the specified offset from the position of the hand and fingers not specified will have the same offset they did before the move.

The key can be specified using either a symbol or string that specifies the name of a key as the target location for the hand in the same way they are named for a <u>press-key request</u>.

Here are the events which will show in the trace for a point-hand-at-key request indicating the hand and key that were specified, the progression through the stages of the action, and indicating the distance and direction the hand was moved:

0.050	MOTOR	POINT-HAND-AT-KEY HAND LEFT TO-KEY t
0.250	MOTOR	PREPARATION-COMPLETE
0.300	MOTOR	INITIATION-COMPLETE
0.400	MOTOR	MOVE-A-HAND LEFT 1.4142135 -0.7853982
0.450	MOTOR	FINISH-MOVEMENT

As with the hand-to-home request, even if the hand is already located over the requested key the module will still progress through the movement stages:

0.450	MOTOR	POINT-HAND-AT-KEY HAND LEFT TO-KEY t
0.500	MOTOR	PREPARATION-COMPLETE
0.550	MOTOR	INITIATION-COMPLETE
0.650	MOTOR	MOVE-A-HAND LEFT 0.0 0.0
0.700	MOTOR	FINISH-MOVEMENT

If an invalid key is specified or no keyboard device is installed then a warning is printed and no action is taken:

```
0.050 MOTOR POINT-HAND-AT-KEY HAND LEFT TO-KEY BAD-KEY #|Warning: No key mapping available for key "BAD-KEY". Point-hand-at-key action ignored. |#

or

#|Warning: No keyboard device installed for motor module. Point-hand-at-key action ignored. |#
```

prepare

```
cmd prepare
style [punch | peck | peck-recoil | ply | hand-ply]
```

```
{hand [ left | right ] }
{finger [ index | middle | ring | pinkie | thumb ] }
{r distance}
{theta direction}
```

The prepare request can be used to have the motor module prepare but not immediately execute a set of features. Those features are stored the same way that the features for a previously executed action are, and thus will decrease the preparation time of a subsequent action which shares those features. Using the <u>execute request</u> it is also possible to perform the action specified by the history of features, so a prepare could be used to set up an action which one may execute later. For instance, if you know the next motor action is going to be a punch of the right index finger, but you're not sure when, you can prepare the movement in advance and then execute it later.

You must specify a style to prepare, and then you may specify any of the parameters that are relevant for that style.

Here is the trace showing a preparation for a ply style action (movement of the left index finger two cells to the right) which shows that only the preparation step occurs for a prepare request:

```
0.050 MOTOR PREPARE PLY HAND LEFT FINGER INDEX R 2 THETA 0 ... 0.300 MOTOR PREPARATION-COMPLETE
```

If that is followed by an execute action there is no preparation step at that time, and the previously prepared action is executed. Here is a continuation of that trace showing an execute request occurring next:

0.350	MOTOR	EXECUTE
0.400	MOTOR	INITIATION-COMPLETE
0.500	MOTOR	MOVE-A-FINGER LEFT INDEX 2 0
0.550	MOTOR	FINISH-MOVEMENT

execute

cmd execute

The execute request causes the model to execute the last movement which was prepared. That will either be a movement which was specified by an explicit <u>prepare request</u> or the last action which was requested. Because all of the features are already prepared there is no preparation step required as

shown in the sequence of events (in this case the last prepared features were for a punch with the left index finger using the keyboard device):

```
0.350 MOTOR EXECUTE
...
0.400 MOTOR INITIATION-COMPLETE
...
0.410 KEYBOARD output-key FOO f
...
0.500 MOTOR FINISH-MOVEMENT
```

If there are no currently prepared features then the execute request prints a warning and no action is taken:

```
0.000 MOTOR EXECUTE #|Warning: Motor Module has no movement to EXECUTE. |#
```

Chunks & Chunk-types

The motor module and the provided devices create chunk-types for each of the requests they make available with the same name as the request and havning a cmd slot with a default value set to a chunk which also has that same name and is defined using that same chunk-type. Here are the chunk-type definitions that are executed by the motor module:

```
(chunk-type motor-command (cmd "motor action"))
(chunk-type (punch (:include motor-command)) (cmd punch) hand finger)
(chunk-type (click-mouse (:include motor-command)) (cmd click-mouse))
(chunk-type (peck (:include motor-command)) (cmd peck) hand finger r theta)
(chunk-type (peck-recoil (:include motor-command)) (cmd peck-recoil) hand finger r theta)
(chunk-type (press-key (:include motor-command)) (cmd press-key) key)
(chunk-type (move-cursor (:include motor-command)) (cmd move-cursor) hand object loc)
(chunk-type (hand-to-mouse (:include motor-command)) (cmd hand-to-mouse))
(chunk-type (hand-to-joystick1 (:include motor-command)) (cmd hand-to-joystick1))
(chunk-type (hand-to-joystick2 (:include motor-command)) (cmd hand-to-joystick2))
(chunk-type (hand-to-home (:include motor-command)) (cmd hand-to-home))
(chunk-type (hand-to-keypad (:include motor-command)) (cmd hand-to-keypad))
(chunk-type (point-hand-at-key (:include motor-command)) (cmd point-hand-at-key)
           hand to-key offsets)
(chunk-type (prepare (:include motor-command)) (cmd prepare) style hand finger r theta)
(chunk-type (execute (:include motor-command)) (cmd execute))
```

These are the chunks which are created if not already defined. These chunks are marked as immutable if defined by the motor module:

```
(define-chunks
  (punch isa punch)
  (click-mouse isa click-mouse)
  (peck isa peck)
  (peck-recoil isa peck-recoil)
  (press-key isa press-key)
  (move-cursor isa move-cursor)
  (hand-to-mouse isa hand-to-mouse)
  (hand-to-joystick1 isa hand-to-joystick1)
```

```
(hand-to-joystick2 isa hand-to-joystick2)
(hand-to-home isa hand-to-home)
(hand-to-keypad isa hand-to-keypad)
(point-hand-at-key isa point-hand-at-key)
(prepare isa prepare)
(execute isa execute)
(left name left)
(right name right)
(index name index)
(middle name middle)
(ring name ring)
(pinkie name pinkie)
(thumb name thumb))
```

Commands

start-hand-at-mouse

Syntax:

start-hand-at-mouse -> [t | nil]

Remote command name:

start-hand-at-mouse

Description:

The start-hand-at-mouse command is used to position the right hand of the current model on the virtual mouse device instead of at the default location. It should be called before running the model, and typically it would be placed into the model definition. It is not intended for moving the model's hand, only specifying its initial location. If the model's hand is successfully placed on the mouse, then **t** is returned. If there is no current model then no change is made, a warning is printed, and **nil** is returned. If there is not a mouse cursor device installed, then one will be installed automatically and a warning will be printed to indicate that and **t** will be returned.

Examples:

```
> (start-hand-at-mouse)
T
E> (start-hand-at-mouse)
#|Warning: No current model. Cannot set hand at mouse. |#
NIL
E> (start-hand-at-mouse)
#|Warning: Installing a default mouse because of start-hand-at-mouse. |#
```

start-hand-at-joystick1

Syntax:

start-hand-at-joystick1 -> [t | nil]

Remote command name:

start-hand-at-joystick1

Description:

The start-hand-at-joystick1 command is used to position the right hand of the current model on the virtual first order joystick cursor device instead of at the default location. It should be called before running the model, and typically it would be placed into the model definition. It is not intended for moving the model's hand, only specifying its initial location. If the model's hand is successfully placed on the joystick cursor, then **t** is returned. If there is no current model then no change is made, a warning is printed, and **nil** is returned. If there is not a joystick1 cursor device installed, then one will be installed automatically and a warning will be printed to indicate that and **t** will be returned.

Examples:

```
> (start-hand-at- joystick1)
T
E> (start-hand-at-joystick1)
#|Warning: No current model. Cannot set hand at joystick1. |#
NIL
E> (start-hand-at-joystick1)
#|Warning: Installing a default joystick1 because of start-hand-at-joystick1. |#
T
```

start-hand-at-joystick2

Syntax:

start-hand-at-joystick2 -> [t | nil]

Remote command name:

start-hand-at-joystick2

Description:

The start-hand-at-joystick2 command is used to position the right hand of the current model on the virtual second order joystick cursor device instead of at the default location. It should be called before running the model, and typically it would be placed into the model definition. It is not intended for moving the model's hand, only specifying its initial location. If the model's hand is successfully placed on the joystick cursor, then **t** is returned. If there is no current model then no

change is made, a warning is printed, and **nil** is returned. If there is not a joystick2 cursor device installed, then one will be installed automatically and a warning will be printed to indicate that and **t** will be returned.

Examples:

```
> (start-hand-at- joystick2)
T
E> (start-hand-at-joystick2)
#|Warning: No current model. Cannot set hand at joystick2. |#
NIL
E> (start-hand-at-joystick2)
#|Warning: Installing a default joystick2 because of start-hand-at-joystick2. |#
T
```

start-hand-at-keypad

Syntax:

start-hand-at-keypad -> [t | nil]

Remote command name:

start-hand-at-keypad

Description:

The start-hand-at-keypad command is used to position the right hand of the current model on the virtual keyboard's keypad with the fingers over the 4, 5, 6, and enter keys and the thumb over 0. It should be called before running the model, and generally it would be placed into the model definition. It is not intended for moving the model's hand, only specifying its initial location. If the model's hand is successfully placed on the keypad, then **t** is returned. If there is no current model, then no change is made, a warning is printed, and **nil** is returned. If there is no keyboard device installed then one will be installed automatically, a warning will be printed to indicate that, and **t** will be returned.

Examples:

```
> (start-hand-at-keypad)
T
E> (start-hand-at-keypad)
#|Warning: No current model. Cannot set hand at keypad. |#
NIL
E> (start-hand-at-keypad )
#|Warning: Keyboard device installed automatically by start-hand-at-keypad |#
```

start-hand-at-key

Syntax:

```
start-hand-at-key hand key -> [t | nil ]
```

Remote command name:

start-hand-at-key

Arguments and Values:

```
hand ::= [ left | right ] key ::= the name of a key on the keyboard device
```

Description:

The start-hand-at-key command is used to position a hand of the current model on the virtual keyboard over a specified key instead of the default home row position. It should be called before running the model, and generally it would be placed into the model definition. It is not intended for moving the model's hand, only specifying its initial location. If the model's hand is successfully placed over the indicated key, then **t** is returned. If there is no current model or an invalid key name is provided, then no change is made, a warning is printed, and **nil** is returned. If there is no keyboard device installed then one will be installed automatically, a warning will be printed to indicate that, and **t** will be returned.

Examples:

```
> (start-hand-at-key 'right 'return)
T
E> (start-hand-at-key 'left "a")
#|Warning: No current model. Cannot start hand at key. |#
NIL
E> (start-hand-at-key 'right "bad-key")
#|Warning: Invalid key "bad-key" in start-hand-at-key. |#
NIL
E> (start-hand-at-key 'left "a")
#|Warning: Keyboard device installed automatically by start-hand-at-key. |#
T
```

set-hand-location

Syntax:

```
set-hand-location hand x y {device} -> [t | nil ]
set-hand-location-fct hand xy-loc {device} -> [t | nil ]
```

Arguments and Values:

```
hand ::= [ left | right ]

x ::= a number specifying the x coordinate of the cell for the specified hand's position
y ::= a number specifying the y coordinate of the cell for the specified hand's position
xy-loc ::= a list of two numbers specifying the starting x and y coordinates respectively of the cell for
the specified hand's position
device ::= a device list indicating the device which that hand is currently using
```

Description:

The set-hand-location command can be used to set the position of the specified hand of the current model and indicate which device it is using. It should not be called while the model is running to avoid conflicts with any model generated hand movements, but can be called before running the model or when it is stopped. The x and y coordinates specify the cell over which the specified hand and its index finger are placed, and the other fingers will be located relative to that location as they would for a hand on the home row of a keyboard (each finger in a separate cell of the same row offset one column in the appropriate direction for the hand and the thumb being two rows below the index finger and one column away in the opposite direction from the other fingers). If the position of the hand is set for the model then **t** is returned. If there is no current model or the position or device provided is invalid then no change is made, a warning is printed, and **nil** is returned.

Examples:

```
> (set-hand-location left 0 0)
T

> (set-hand-location-fct 'right '(10 4))
T

> (set-hand-location right 3 3 ("motor" "keyboard"))
T

E> (set-hand-location right a b)
#|Warning: Invalid location (A B) provided to set-hand-location-fct. |#
NIL

E> (set-hand-location-fct 'right '(10 4) '("bad" "device"))
#|Warning: Invalid device ("bad" "device") given to set-hand-location-fct. |#
NIL

E> (set-hand-location left 0 0)
#|Warning: No current model. Cannot set hand location. |#
NIL
```

set-cursor-position

Syntax:

```
set-cursor-position x y { z {cursor-name}} -> [ xyz-loc | nil ]
set-cursor-position-fct new-loc {cursor-name} -> [ xyz-loc | nil ]
```

Remote command names:

set-cursor-position set-cursor-position-fct

Arguments and Values:

```
x ::= a number specifying the x coordinate for the cursory ::= a number specifying the y coordinate for the cursorz ::= a number specifying the z coordinate for the cursor
```

new-loc ::= a list of two or three values representing a new location for the cursor cursor-name ::= a string naming an installed cursor device which defaults to "mouse" xyz-loc ::= a list of three values representing the current location of the cursor

Description:

The set-cursor-position command can be used to set the position of an installed cursor device for the the current model. If a z coordinate is not provided or provided as a non-numeric value, then it will get a default value based on the wiewing-distance and pixels-per-inch parameters of the model. It should not be called while the model is running to avoid conflicts with any model generated cursor movements, but can be called before running the model or when it is stopped. If the named cursor is installed and its position is updated then a list with the current cursor coordinates is returned. If there is no current model, the named cursor is not installed for the motor interface, or an invalid value is provided then no change is made, a warning is printed, and nil is returned.

Examples:

```
> (set-cursor-position 1 1)
  (1 1 1080)
> (set-cursor-position-fct '(10 10))
  (10 10 1080)
> (set-cursor-position 1 1 200)
  (1 1 200)
> (set-cursor-position 30 30 200 "mouse")
  (30 30 200)
> (set-cursor-position 30 30 nil "mouse")
  (30 30 1080)
```

```
E> (set-cursor-position 10 20)
#|Warning: No current model. Cannot set cursor position. |#
NIL

E> (set-cursor-position 0 0)
#|Warning: No cursor device named "mouse" is currently installed for the motor interface.
|#
NIL

E> (set-cursor-position-fct 'invalid)
#|Warning: Location for set-cursor-position-fct must be a list of two values but INVALID provided. |#
NIL
```

extend-manual-requests

Syntax:

```
extend-manual-requests chunk-type-def request-function -> [t | nil] extend-manual-requests-fct chunk-type-def request-function -> [t | nil]
```

Arguments and Values:

```
chunk-type-def ::= a list with a valid definition for a new chunk-type request-function ::= a symbol which is the name of a function to call to handle the new request
```

Description:

The extend-manual-requests command allows one to add new requests to those which are accepted by the manual buffer. Extend-manual-requests only needs to be called once for each new request being added, and it does not have to occur within the context of a model. The chunk-type-def parameter must be a list which is valid for passing to chunk-type-fct. That chunk-type definition will have an additional slot called cmd specified with a default value that matches the name of the chunk-type from the defintion and then be passed to chunk-type-fct. If that chunk-type name is not also defined as a chunk then one will be defined using that same name as the chunk-type and it will be marked as immutable. Thus, if one were to provide this chunk-type-def value:

```
(new-motor-action hand finger pressure)
This chunk-type would be defined:
  (chunk-type new-motor-action hand finger pressure (cmd new-motor-action))
and this chunk would be created and marked as immutable:
  (define-chunks (new-motor-action is a new-motor-action))
```

When a request to the manual buffer is made with the cmd slot specifying the chunk-type-name indicated then the function specified by request-function will be called with the current model's motor module as the first parameter and the chunk-spec of the request as the second parameter. There are no restrictions on what the new request may do, nor are there any default operations performed – it is entirely up to the extension to handle all scheduling of events as necessary to change the state of the motor module and perform the actions necessary. [Note however, that the internal representation of the motor module and its state is not currently part of the API and thus there is no documentation on how to use it directly in that manner at this time. Also, because the motor module itself is passed to the request function it cannot be passed to an external command. Both of those issues will be addressed in the future to make this more accessible and usable.]

Once a new request has been added it cannot be overwritten by a new request with the same name. However, it can be removed using the <u>remove-manual-request command</u> and then be defined again.

If chunk-type-def is not a valid list, request-function does not name a currently defined function or the chunk-type being specified is already used for an extension then extend-manual-requests will print a warning, no new request extension will be made, and **nil** will be returned.

If successfully created, the new request will be available to all models from that point on and **t** will be returned.

The recommended use of this command is to place a file which has the necessary request function and any support code needed along with a call to extend-manual-requests into one of the directories for which the files are loaded automatically. That way the request function is compiled with the rest of the sources and is made available to all models right from the start. If it is called while there are models already defined the new request will not be available to those models until they are reset.

Most of the default requests which the motor module accepts are created using extend-manual-requests.

Examples:

These examples assume that there are functions named handle-right-click and handle-hold already defined.

```
> (extend-manual-requests (right-click) handle-right-click)
T

1> (extend-manual-requests-fct '((hold-key (:include motor-command)) key) 'handle-hold)
T
```

```
2E> (extend-manual-requests-fct '((hold-key (:include motor-command) key)) 'handle-hold)
#|Warning: Request HOLD-KEY is already an extension of the manual buffer. To redefine you
must remove it first with remove-manual-request. |#
NIL

E> (extend-manual-requests bad-type handle-right-click)
#|Warning: Invalid chunk-type specification BAD-TYPE. Manual requests not extended. |#
NIL

E> (extend-manual-requests-fct '(chord finger1 finger2) 'not-a-function)
#|Warning: NOT-A-FUNCTION does not name a function. Manual requests not extended. |#
NTI
```

remove-manual-request

Syntax:

```
remove-manual-request chunk-type-name -> [t \mid nil] remove-manual-request-fct chunk-type-name -> [t \mid nil]
```

Arguments and Values:

chunk-type-name ::= a symbol which is the name of a chunk-type used to extend the manual requests

Description:

Remove-manual-request is used to remove a request that has been added to the manual buffer through the use of <u>extend-manual-requests</u>. The chunk-type-name parameter should be the name of a chunk-type which was defined with a call to extend-manual-requests. The request of that chunk-type will be removed from the set of requests that the manual buffer will process for all models and that chunk-type will no longer be defined in any new models (its definition will still remain in any existing models until they are reset).

If chunk-type-name does name an extended request, then after removing the request this command will return **t**. If chunk-type-name is not the name of a previously extended request then a warning will be printed and **nil** will be returned.

This command is typically only needed when one is developing some extensions to the manual module and needs to change some of the requests under development. It is not recommended for use in other situations.

Examples:

These examples assume that there are functions named handle-right-click and handle-hold already defined.

```
1> (extend-manual-requests (right-click) handle-right-click)
```

```
T

2> (extend-manual-requests-fct '((hold-key (:include motor-command)) key) 'handle-hold)
T

3> (remove-manual-request-fct 'right-click)
T

4> (remove-manual-request hold-key)
T

5E> (remove-manual-request hold-key)
#|Warning: HOLD-KEY is not a previously extended request for the manual module. |#
NIL

E> (remove-manual-request-fct 'bad-chunk-name)
#|Warning: BAD-CHUNK-NAME is not a previously extended request for the manual module. |#
NIL
```

Speech module

The speech module gives a model a rudimentary ability to speak. This system is not designed to provide a sophisticated simulation of human speech production, but to allow a model to speak words and short phrases for simulating verbal responses in experiments and for subvocalizing text internally. The module has one buffer, vocal, and works in much the same way as the <u>motor module</u>.

The vocal world

The model's speech output is fairly limited. When it speaks or subvocalizes it will hear its own words through the <u>audio module</u>. Those speak and subvocalize actions are also detectable through the installation of a device for the "speech" interface, described below.

Operation

Like the motor module, the speech module takes requests that specify a style of action and the appropriate attributes for that style. There are only two styles available for the speech module:

- Speak to produce normal speech output.
- Subvocalize to produce internal speech the model speaking to itself with no external output.

The only attribute for each of those styles is a string of text to speak.

The speech module does not place any chunks into its buffer in response to the requests. The vocal buffer should always be empty, and it is the state of the module that is most important to the model in this case. As described above for all the perceptual and motor modules, the speech module has three internal states: preparation, processor, and execution. How a request progresses through those states is described in detail below.

An important thing to note is that while the vocal buffer does not receive a chunk in response to a speech action the <u>aural-location buffer</u> might. Because the model hears its own speech acts the automatic buffer stuffing of the aural-location buffer may occur as a result of a vocal request.

When a request is received by the speech module, it goes through three phases: preparation, initiation, and execution. The amount of time that speech output preparation takes depends on the history of previous speech acts. The speech module records the last string which it has output. If there is no previous string which has been spoken, then the module requires the preparation of three

features (which by default take 50ms each). If there is a previously spoken string, then there are no features to prepare if the same string is being output again or two features if it is not the same string.

After preparation is complete, the speech module makes the specified vocal output. The first 50ms of that output is initiation. During this interval, the preparation state becomes free and the processor and execution states become busy. After initiation ends, the processor state becomes free. It is at that time that speech output is made available to the device and the auditory system. Note that the typical detection delay and recoding times still apply for the encoding of sounds as described in the audio module, but speech output though subvocalizing has a separate parameter for the detection delay and a recoding time of 0 seconds. The amount of time that the speech takes to finish after initiation depends on the articulation time of the string which defaults to .15 seconds per assumed syllable, but can be changed in various ways (see the get-articulation-time command below for details).

The speech module can only prepare one output at a time. If the speech module is in the process of preparing output and another request is received, the later request will be ignored and the speech module is said to be "jammed." When the module is jammed it will output a warning indicating when the jamming occurred like this:

```
#|Warning: Module :SPEECH jammed at time 0.1 |#
```

The way to avoid jamming, as with all modules, is to test the state of the module before making a request. Testing that state free is true will avoid jamming the module, but it is possible to issue speech requests faster than that – because the state will not be free until the previous output has been completed. Instead, one usually only needs to test that the preparation state is free to be able to issue a new request to the speech module, but a more conservative approach would be to test the processor state because it is still busy during the initiation time of the last output request.

Interface & Devices

The speech module has an interface called "speech" which can be used to install a single device. If a device is installed for the speech interface then it will be notified at the start and end of every speech output. It will also be notified at installation time with a list containing only the item check-subvocalize. If the device responds to that notification with a non-nil result then the device will also be notified at the start and end of subvocalize actions, otherwise it will not be notified for subvocalize actions. The features provided to the device will be described with the requests that generate them.

Microphone

There is one device provided for use with the speech interface called "microphone". If a microphone

device is installed for the speech interface (which will happen automatically for the experiment

window devices of the AGI) it will respond to the start of speech output by generating an "output-

speech" signal at that time which has two parameters: the name of the model which spoke and the

string of the text that is being spoken. Installing a microphone device and monitoring the output-

speech signal is the recommended way to detect and record a model's speech output.

Parameters

:char-per-syllable

This parameter controls how the model breaks a text string into syllables and is measured in a number

of characters (see get-articulation-time for how it applies). It can be set to any positive number and

defaults to 3.

:subvocalize-detect-delay

This parameter sets the detect delay timing for the sound events generated by a subvocalize action

(see the <u>audio module</u> for details on the detect delay). It is measured in seconds and can be set to any

non-negative value. It defaults to .3 (which is the same value that normal text has).

:syllable-rate

This parameter controls the time it takes the model to articulate each syllable in a text string and is

measured in seconds (see get-articulation-time below for how it applies). It can be set to any non-

negative number and defaults to 0.15.

Vocal buffer

The speech module does not place any chunks into the vocal buffer. The preparation timing for the

actions will be set using the randomize-time function, but all other action times will be fixed

regardless of the :randomize-time parameter setting.

Activation spread parameter: :vocal-activation

Default value: 0.0

430

Queries

'State busy' will be **t** when any of the internal states of the module (listed below) also report as being busy. Essentially, it will be **t** while there is any request to the vocal buffer that has not yet completed. It will be **nil** otherwise.

'State free' will be **t** when all of the internal states of the module (listed below) also report as being free. Essentially, it will be **t** only when all requests to the vocal buffer have completed. It will be **nil** otherwise.

'State error' will always be nil.

Unlike the perceptual modules, the internal states of the speech module may be useful to track in a model because it is possible to send new requests while the module is partially busy. Only the preparation stage of the module needs to be free to avoid jamming. For each request that is received the module will progress through three stages as described above: preparation, initiation, and execution.

'Preparation busy' will be **t** after a request has been received and until it completes the preparation of the features needed for that request which depends on how many features there are and whether or not they overlap with the last features prepared. It will be **nil** otherwise.

'Preparation free' will be **nil** after a request has been received and until it completes the preparation of the features needed for that request which depends on how many features there are and whether or not they overlap with the last features prepared. It will be **t** otherwise.

'Processor busy' will be **t** while preparation is busy and will continue to be **t** after the features have been prepared until the additional initiation time (fixed at .05 seconds) has passed. It will be **nil** otherwise.

'Processor free' will be **nil** while preparation is busy and will continue to be **nil** after the features have been prepared until the additional initiation time (fixed at .05 seconds) has passed. It will be **t** otherwise.

'Execution busy' will be **t** once the preparation of a request's features has completed and will remain **t** until the time necessary to complete the action has passed. It will be **nil** otherwise.

'Execution free' will be **nil** once the preparation of a request's features has completed and will remain **nil** until the time necessary to complete the action has passed. It will be **t** otherwise.

'Last-command *command*' *command* should be a symbol which corresponds to one of the vocal buffer's requests or the symbol none. The query will be **t** if that is the name of the last request received by the vocal buffer otherwise it will be **nil**.

Here is a summary indicating the state transitions for a single vocal request assuming that the module is entirely free at the start of the request:

Preparation state Processor state Execution state When

FREE	FREE	FREE	Before event arrives
BUSY	BUSY	FREE	When event is received
FREE	BUSY	BUSY	After preparation time
FREE	FREE	BUSY	After initiation (.05 seconds)
FREE	FREE	FREE	When speech completes (articulation time)

Requests

clear

[cmd clear | clear t]

A clear request can be sent to clear the history of the last string vocalized. A clear request will make the preparation state busy for 50ms. These events will show in the trace for a clear request to the vocal buffer:

0.050	SPEECH	CLEAR	
• • •			
0.100	SPEECH	CHANGE-STATE LAST NONE PREP FRE	ΞE

Note, that after the clear request completes the last-command recorded by the module will be none and not clear – the clear request has effectively cleared the history of its own request as well.

While this request makes the preparation state busy, unlike other requests it does not require that it be free. That makes it possible to use the clear request to terminate an action which has not yet started its execution.

speak

cmd speak string text

A speak request causes the model to generate vocal output. The output that is made is the string specified by text. That speech output is made available to the model's <u>audio module</u> as a word sound with a location of self. That may trigger buffer stuffing of the aural-location buffer. It will also generate two notifications for an installed device. The first notification occurs when the initiation phase ends and execution begins. That notification will be a list of three elements:

(start speak text)

where text is the string that is being spoken. The second notification will occur when the execution phase ends and will also be a list of three elements:

(end speak text)

Here are the events which will show in the trace for a speak request showing the text that is to be output and the progression through the stages of the action:

0.050	SPEECH	SPEAK TEXT hello
0.200	SPEECH	PREPARATION-COMPLETE
0.250	SPEECH	INITIATION-COMPLETE
0.250	SPEECH	SPEAK hello
0.500	SPEECH	FINISH-MOVEMENT

If a microphone device is installed then instead of the speak event an output-speech event will show in the trace indicating the current model and the text spoken:

```
0.250 MICROPHONE output-speech SPEECH-TEST hello
```

If an invalid text value is given this warning will show in the trace and no action will be taken by the module:

```
\ensuremath{\mbox{\#}}\xspace\ensuremath{\mbox{|Warning: String slot in a speak request must be a string. }\ensuremath{\mbox{|\#}}\xspace
```

subvocalize

cmd subvocalize string text

A subvocalize request causes the current model to generate internal speech (the model is talking to itself). That speech output is made available to the model's <u>audio module</u> as a word sound with a

location of internal. That may trigger buffer stuffing of the aural-location buffer. It will also generate two notifications for an installed device if that device responding non-nil to the check-subvocalize notification when it was installed. The first notification occurs when the initiation phase ends and execution begins. That notification will be a list of three elements:

(start subvocalize *text*)

where text is the string that is being subvocalized. The second notification will occur when the execution phase ends and will also be a list of three elements:

(end subvocalize text)

Here are the events which will show in the trace for a subvocalize request showing the text that is to be subvocalized and the progression through the stages of the action:

```
0.050 SPEECH SUBVOCALIZE TEXT hello
...
0.200 SPEECH PREPARATION-COMPLETE
...
0.250 SPEECH INITIATION-COMPLETE
...
0.500 SPEECH FINISH-MOVEMENT
```

If an invalid text value is given this warning will show in the trace and no action will be taken by the module:

```
#|Warning: String slot in a subvocalize request must be a string. |#
```

Chunks & Chunk-types

The speech module creates a chunk-type for each of the requests it accepts with the same name as the request and which has a cmd slot with a default value set to a chunk which also has that same name and is defined using that same chunk-type. Here are the chunk-type definitions that are executed by the speech module:

```
(chunk-type speech-command (cmd "speech command"))
(chunk-type (speak (:include speech-command)) (cmd speak) string speak)
(chunk-type (subvocalize (:include speech-command)) (cmd subvocalize) string subvocalize)
```

These are the chunks which are created if not already defined. These chunks are marked as immutable if defined by the speech module:

```
(define-chunks
  (speak isa speak)
  (subvocalize isa subvocalize)
  (internal name internal)
  (self name self))
```

Commands

get-articulation-time/register-articulation-time

Syntax:

get-articulation-time string {time-in-ms} -> [time | nil]
register-articulation-time string time -> [time | nil]

Remote command names:

get-articulation-time register-articulation-time

Arguments and Values:

string ::= a string for which a specific articulation time is required (case insensitive) time-in-ms ::= a generalized boolean indicating the units to use for the returned time time ::= a non-negative number indicating the time in seconds that it takes to articulate the string

Description:

These commands are used to get the articulation time for a text string and to set an explicit time to articulate a string in the current model. That time will be used by the audio module as the duration of such a string if it is heard by the model and will be the length of time that the model requires to speak such a string using the speech module.

Register-articulation-time sets the articulation time for the provided string in the current model in seconds. If such a value is set then time is returned. If there is no current model or one of the parameters is invalid, then a warning is printed and **nil** is returned.

Get-articulation-time returns the time it takes to articulate a string of text for the current model. That time will be either the explicit time that was set using register-articulation-time if one was set, or computed based on the length of the string and the values of the parameters <u>:syllable-rate</u> and <u>:charper-syllable</u> using this equation:

AT = r * L/c

AT := articulation time for the string r := value of the :syllable-rate parameter L := the length of the string

c := value of the :char-per-syllable parameter

If the optional parameter time-in-ms is provided as non-nil then the return value will be measured in milliseconds, otherwise it will be measured in seconds.

If the string is invalid or there is no current model then a warning is printed and **nil** is returned instead.

Examples:

```
1> (sgp :char-per-syllable :syllable-rate)
:CHAR-PER-SYLLABLE 3 (default 3) : Characters per syllable.
:SYLLABLE-RATE 0.15 (default 0.15) : Seconds per syllable.
(30.15)
2> (get-articulation-time "Hello")
3> (get-articulation-time "Hello" t)
250
4> (get-articulation-time "Goodbye")
0.35
5> (get-articulation-time "A")
0.05
6> (register-articulation-time "Hello" .185)
7> (get-articulation-time "Hello")
0.185
E> (register-articulation-time "Hello" .25)
#|Warning: No current model. Cannot set articulation time. |#
NIL
E> (get-articulation-time "Hello")
#|Warning: No current model. Cannot get articulation time. |#
NIL
E> (get-articulation-time 'hello)
#|Warning: Must specify a string for which to get the articulation time. |#
NIL
E> (register-articulation-time 'hello .2)
#|Warning: Must specify a string for which the articulation time is to be set. |#
NIL
E> (register-articulation-time "Hello" -1)
#|Warning: Articulation time must be a non-negative number. |#
NIL
E> (get-articulation-time "Hello" t)
#|Warning: No current model. Cannot get articulation time. |#
E> (register-articulation-time "Hello" .185)
#|Warning: No current model. Cannot set articulation time. |#
NIL
```

Temporal Module

The temporal module provides a model with a means of determining time intervals and is based on research by Taatgen, van Rijn, & Anderson (2007). It does so by providing a timer which counts the number of "ticks" which have passed since the timer was started. The tick lengths are noisy and also increase in duration as time progresses. Thus it is more accurate for timing shorter intervals than longer ones. The current tick count is available to the model via a chunk in the temporal buffer which has a slot called ticks. Once the timer is started the module will continue to update the ticks slot of the chunk in the buffer with the current count automatically. The timer can be explicitly reset to start a new count or stopped by the model at any time, and if the chunk is removed from the buffer it will implicitly stop the count from incrementing.

The tick lengths are generated based on the following equations for the nth tick (the tick count is equal to n, and the first tick happens at t):

```
t_0 = start + \varepsilon_1
t_n = a \cdot t_{n-1} + \varepsilon_2

start := value of the :time-master-start-increment parameter (default 0.011 seconds)

a := value of the :time-mult parameter (default 1.1)

b := value of the :time-noise parameter (default 0.015)

\varepsilon_1 := noise generated with the act-r-noise command with an s of b * 5 * start

\varepsilon_2 := noise generated with the act-r-noise command with an s of b * a * t<sub>n-1</sub>
```

Parameters

:record-ticks

This parameter controls whether or not the time incrementing event generates an action which the <u>buffer trace module</u> will detect. If it is set to **t** then there will be an extra event in the trace for each clock increment which will be associated with activity in the temporal buffer. It can be set to **t** or **nil** and the default value is **t**.

:time-master-start-increment

This parameter controls the length of the 0_{th} tick in seconds. It can be set to any positive number and defaults to 0.011.

:time-mult

This parameter sets the multiplier for increasing the tick length. It can be set to any positive number

and defaults to 1.1.

:time-noise

This parameter scales the s value of the noise added to the tick lengths. It can be set to any positive

number and defaults to 0.015.

Temporal buffer

The temporal module sets the temporal buffer to **not** be strict harvested.

Activation spread parameter: :temporal-activation

Default value: 0.0

Queries

The temporal buffer only responds to the default queries and like the goal module is always available

and never in an error state.

'State busy' will always be nil.

'State free' will always be t.

'State error' will always be **nil**.

Requests

time

ticks value

request will reset the internal tick counter to 0, put a chunk into the temporal buffer with a ticks slot

A time request requires that the ticks slot be specified with any value (which will be ignored). A time

value of 0, and start the timer which will increment the value in the ticks slot of that chunk as

described above. These actions will happen at the time of the request indicating the creation of the

new chunk and setting it into the buffer:

438

0.050	TEMPORAL	create-new-buffer-chunk isa time
0.050	TEMPORAL	SET-BUFFER-CHUNK TEMPORAL TIMEO

The updating of the timer will happen at the appropriate times in the future and will generate multiple events in the trace for each update. If the <u>:record-ticks parameter</u> is set to **t** then there will be three events for each timer update:

0.063	TEMPORAL	Incrementing time ticks to 1
0.063	TEMPORAL	MODULE-MOD-REQUEST TEMPORAL
0.063	TEMPORAL	MOD-BUFFER-CHUNK TEMPORAL

whereas if :record-ticks is set to **nil** there will only be two events for each update:

0.063	TEMPORAL	Incrementing time ticks to 1
0.063	TEMPORAL	MOD-BUFFER-CHUNK TEMPORAL

clear

[cmd clear | clear t]

The clear request will stop the temporal counter if it is incrementing. This is often done in a model when a time estimation finishes i.e. the ticks count is no longer needed. Stopping the counter will eliminate the incrementing and modification events from being scheduled. The reason one may want to stop the counter is because as long as those events are being scheduled there will be events in the queue to keep the model running and the procedural module will continue to attempt conflict resolution when those events occur. Typically, that will just be wasted effort by the software if the model is not intended to be doing anything during that time, thus it can improve the software performance without affecting the model's operation. It may also useful if one is recording the temporal module's activity for comparison to BOLD or other neurophysiological data because otherwise the module will show continuous activity instead of only during a meaningful time estimation period. The clear action will occur at the time of the request and will generate an event like this in the trace:

```
15.559 TEMPORAL Clear
```

Note: clearing the chunk from the temporal buffer will have the same effect as issuing an explicit clear request to the temporal module because that will also stop the incrementing, but it will not result in the event being generated by the temporal module if that is important for buffer tracing purposes.

Modification requests

Technically, the temporal module allows modification requests because they are used internally to update the ticks count when the <u>:record-ticks parameter</u> is set to t. However, that capability is not intended for general use and modification requests should not be made to the temporal buffer.

Chunks & Chunk-types

The temporal module defines one chunk-type and no chunks:

```
(chunk-type time (ticks 0))
```

Commands

The temporal module provides no user commands. All of its operation is controlled through the requests that it accepts.

Advanced Topics

The previous sections of the manual have covered the basic operation of the system and the operation of most of the modules that are provided. That is the information which should be of general use to those using ACT-R to build models. However, there are other capabilities which one can use in the system in addition to being able to extend the system itself. The following sections will describe more of the low level subsystems that are available for working with ACT-R and will cover more advanced topics in using the system like running multiple models, defining new modules for the model to use, and adjusting how the model operates in real-time mode. These sections will assume that one has a good grasp of the concepts from the earlier sections.

One note about the advanced topics is that the purpose is to describe the components that the system makes available. Because the system is available as source code it is entirely possible for the user to modify or change the definition of the system itself. That is not the sort of thing that will be covered in this, or any, section of the reference manual.

Extending Possible Chunk Slots

As has been mentioned in other places in the manual it is possible for a model to add new slots to

chunks as it runs. The mechanism which does that is also available to the user for use in new

modules or other extensions of the system. In ACT-R 6.0 this was referred to as extending the

chunk-types, but now that chunks no longer have a specific type the mechanism is more appropriately

referred to as extending the possible slots of chunks.

Extending the possible chunk slots creates a new possible slot name for use in chunks. It will happen

automatically when chunks or productions are defined which specify names for slots which do not

currently exist. In those situations a warning will be displayed to indicate that the extension has

occurred. It will also happen through dynamic chunk modifications which use slot names that are not

currently valid, and when that happens there will be an event in the trace to indicate the extension

occurred. It is also possible to explicitly extend the set of possible slot names in code to avoid the

warnings which would occur for defining chunks or productions that use new slot names

Commands

extend-possible-slots

Syntax:

extend-possible-slots new-slot {warn?} -> [new-slot | nil]

Remote command names:

extend-possible-slots

Arguments and Values:

new-slot ::= the name of a slot to add to chunks

warn? ::= a generalized boolean which indicates whether or not to print a warning for an existing slot

Description:

The extend-possible-slots command is used to add a new slot name for use in chunks. It requires one

parameter which should be non-nil name which starts with an alphanumeric character and names the

new slot to add for chunks. A second optional parameter may be provided and if it is non-nil then a

warning will be output if the new slot name specified already names a valid slot in chunks (it is t by

default). If the new slot name provided is a valid name and not already the name of a possible slot

442

for chunks then it is added to the possible slot names for the current model and that slot name is returned.

If the slot name is not valid or there is no current model then a warning is printed and **nil** is returned.

Examples:

```
1> (extend-possible-slots 'new-slot-name)
NEW-SLOT-NAME
2E> (extend-possible-slots 'new-slot-name)
#|Warning: NEW-SLOT-NAME already names a possible slot for chunks. |#
NIL
3> (extend-possible-slots 'new-slot-name nil)
NIL
E> (extend-possible-slots nil)
#|Warning: Nil is not a valid slot name when trying to extend slots. |#
E> (extend-possible-slots '&bad-slot-name)
#|Warning: &BAD-SLOT-NAME cannot be used as a slot name because it does not start with an
alphanumeric character. |#
NIL
E> (extend-possible-slots 'new-slot-name)
#|Warning: Chunk-type info not available so the slot NEW-SLOT-NAME cannot be added. |#
NIL
```

Chunk-Specs

A chunk-spec is an internal representation for the specification of a chunk (*chunk-spec*ification). Chunk-specs consist of a set of constraints for the slots of a chunk along with specifications for request parameters. An individual slot or request parameter specification in a chunk-spec is referred to as a slot-spec. Chunk-specs can be used for a variety of purposes and are a key component in the communication between modules. They were used implicitly in several of the commands of the modules described above and occasionally showed up in the text of a warning message. The best example of chunk-specs shown in the modules is in the commands for defining productions. The LHS buffer tests and RHS module requests are both direct applications of chunk-specs. That also describes the two primary uses of chunk-specs: testing (or finding) whether chunks match a specification and making a request to a module.

The description of a slot in a chunk-spec can use modifiers and variables in much the same way that the production pattern matching does. The same modifiers used in productions are available in a chunk-spec: =,-,<,>,<=, and >= for specifying slots. The default behavior is the same as used in productions: = means that the slots must be equal, - means they must differ, and the inequality tests are only valid for numbers. However, one is not restricted to only that usage. How each of those modifiers is used to match or find a chunk with a chunk-spec can be controlled individually in the commands which do so. An example where one might want to change that would be to allow using the inequality tests among a set of qualitative sizes like {tiny, small, normal, big, gigantic}. Names starting with an '=' character are considered as variables for both the slot name and for the slot value positions of a slot-spec by default when using the provided matching commands, but that character can also be changed for those commands and one can also implement their own matching mechanisms using chunk-specs which do not need to use that convention (note however that when creating a chunk-spec only the '=' character is considered a variable and thus any other name specified in the slot name position must be valid for slot names).

Unlike a slot's specification, the specification for a request parameter cannot include a modifier other than =. Variables however may still be used for the values in a request parameter specification. The request parameter specifications are ignored by the provided commands for matching chunks to a chunk-spec, and their purpose is determined entirely by the code that uses the chunk-spec.

The most common place where one will need to use chunk-specs is when developing a new module. All requests to the module will be encoded as chunk-specs. Thus any module which accepts requests will have to process chunk-specs. If the module also holds a set of chunks internally for some purpose, like the vision module does for the features of the visual scene, then one may also find the matching and search commands which are available with chunk-specs to be useful.

Because the semantics of the modifiers and the specification of a variable in a chunk-spec are configurable, a chunk-spec does not really have any particular meaning on its own. Without knowing the context in which the chunk-spec will be used it is impossible to know what it represents. Thus any particular chunk-spec is effectively meaningless outside of the context in which it is created and used.

The internal representation of a chunk-spec is not part of the API for the system therefore one should only operate on them using the provided commands. It is not possible to pass an internal chunk-spec directly through the remote interface, but there are commands which will convert a chunk-spec to an id value which can be used anywhere a chunk-spec can (as long as that id is still valid). The remote versions of the commands will always return a chunk-spec id. The only difference between using an internal chunk-spec and a chunk-spec id is that when using a chunk-spec id one should release it when done using it for efficiency reasons, and once it is released it will no longer be a reference to a valid chunk-spec.

Commands

define-chunk-spec

Syntax:

```
define-chunk-spec specification -> [chunk-spec | nil] {(extended*)}
define-chunk-spec-fct (specification) {extend} {warn} -> [chunk-spec | nil] {(extended*)}
```

Remote command names:

```
define-chunk-spec ' specification '
define-chunk-spec-fct ' (specification) ' {extend} {warn}
```

Arguments and Values:

```
specification ::= [ chunk-name | {isa chunk-type} [ {modifier} slot value | {=} request-param value ]* ] extend ::= a generalized boolean indicating whether to extend the possible slots for invalid slot names warn ::= a generalized boolean indicating whether to print a warning if possible slots are extended chunk-name ::= the name of a chunk in the current model chunk-type ::= the name of a chunk-type in the current model
```

```
modifier ::= [= | - | < | > | <= | >=]
```

slot ::= the name of a valid slot for the chunk-type specified, the name of a slot valid for any chunk if no chunk-type provided and extend is **nil**, a variable, any name which can represent a slot if extend is true

 $\hbox{request-param} ::= a \ keyword \ (\hbox{name beginning with a colon}) \ \hbox{naming a valid request-parameter}$

variable ::= a name which begins with the = character

value ::= any value (a name which has a first character of = is considered to be a variable)

chunk-spec ::= an internal chunk-spec (Lisp calls) or a chunk-spec id (remote calls)

extended ::= the name of a slot that was passed to extend-possible-slots

Description:

The define-chunk-spec command is used to create a chunk-spec. There are two ways to define a chunk-spec. If a chunk-name is given as the only parameter then a chunk-spec will be created that matches that chunk exactly. It will include a slot-spec for each slot in that chunk with the = modifier and the current value of that slot in the chunk. Alternatively, an optional chunk-type may be provided and then any number of slot-specs and request parameters may be specified for the chunk-spec.

The two optional parameters for the function allow one to indicate whether the set of possible slots should be extended automatically with newly named slots in the definition of the chunk-spec and whether warnings are displayed when that occurs. If the extend parameter is provided as true (which is the default value) then any slots which are specified that are not variables and not currently possible slot names will be extended using the extend-possible-slots command. If the warn parameter is provided, then that is passed as the warn? parameter to extend-possible-slots when a new slot needs to be added for the chunk-spec. The default value of the warn parameter is t if not provided.

The define-chunk-spec macro does not accept the optional parameters for extending and warning. When define-chunk-spec is used the default of **t** is used for each of the optional parameters.

A slot specified using a variable (a symbol which begins with an "=" character) is not tested as a possible slot and will not result in extending the possible slots through the definition of the chunk-spec.

If the syntax of the specification is valid and all of the components are valid two values are returned. The first is a chunk-spec (or chunk-spec id) and the second is a list of all the slot names which were passed to extend-possible-slots.

If the syntax is incorrect, any of the components are invalid, or there is not a current model then a warning is displayed and a single value of **nil** is returned.

As indicated in the general description of a chunk-spec, the chunk-spec representation itself is not part of the API. Thus the specific return value of this command should not be used directly and is only intended to be passed to other chunk-spec processing commands, and if it is a remote call the chunk-spec id should be released when no longer needed.

Examples:

```
1> (chunk-type goal value state)
GOAL
2> (define-chunks (g isa goal value 2 state start))
(G)
```

The following three chunk-spec calls all result in the same chunk-spec being returned:

```
3> (define-chunk-spec g)
#S(ACT-R-CHUNK-SPEC ...)
NIL

4> (define-chunk-spec-fct '(isa goal = value 2 = state start))
#S(ACT-R-CHUNK-SPEC ...)
NIL

5> (define-chunk-spec value 2 state start)
#S(ACT-R-CHUNK-SPEC ...)
NIL
```

The purpose of the next chunk-spec is ambiguous without knowing a context in which it will be used because the @ may be used to represent a variable, or perhaps the symbol @value has a particular meaning where it will be used:

```
1> (chunk-type compare val1 val2)
COMPARE
2> (define-chunk-spec-fct '(isa compare val1 @value <= val2 @value - val2 10))
#S(ACT-R-CHUNK-SPEC ...)
NIL
> (define-chunk-spec-fct '(new-slot1 start value true))
#|Warning: Chunks extended with slot NEW-SLOT1 during a chunk-spec definition. |#
#S(ACT-R-CHUNK-SPEC ...)
(NEW-SLOT1)
> (define-chunk-spec-fct '(new-slot1 start value true) t nil)
#S(ACT-R-CHUNK-SPEC ...)
(NEW-SLOT1)
> (define-chunk-spec =variable-slot =variable-value)
#S(ACT-R-CHUNK-SPEC ...)
NIL
E> (define-chunk-spec-fct '(new-slot1 start value true) nil)
```

```
#|Warning: Invalid slot-name NEW-SLOT1 in call to define-chunk-spec. |#
NIL

E> (define-chunk-spec not-a-chunk)
#|Warning: define-chunk-spec's 1 parameter doesn't name a chunk: (NOT-A-CHUNK) |#
NIL

E> (define-chunk-spec isa bad-name)
#|Warning: Element after isa in define-chunk-spec isn't a chunk-type. (ISA BAD-NAME) |#
NIL

E> (define-chunk-spec)
#|Warning: define-chunk-spec-fct called with no current model. |#
NII
```

chunk-spec-to-id

Syntax:

chunk-spec-to-id chunk-spec -> [id | nil]

Arguments and Values:

chunk-spec ::= a chunk-spec which was returned from define-chunk-spec id ::= a chunk-spec id which can be passed through the remote interface

Description:

The chunk-spec-to-id command is used to generate a chunk-spec id for a chunk spec which can be passed to commands through the remote interface. If a valid chunk-spec is provided then a unique id value is returned which can be used to reference that chunk-spec. [Currently, that id will be an integer, but that might change in the future.] If the value passed in is not a valid chunk-spec then **nil** is returned instead.

When an id returned from this command is no longer needed it should be released for efficiency reasons.

Examples:

```
> (chunk-spec-to-id (define-chunk-spec isa text))
1
E> (chunk-spec-to-id "not-a-chunk-spec")
NIL
```

release-chunk-spec-id

Syntax:

release-chunk-spec-id id -> result

Remote command name:

release-chunk-spec-id

Arguments and Values:

id ::= a chunk-spec id returned from a remote call to define-chunk-spec or chunk-spec-to-id result ::= a generalized boolean which will be true if the id was valid and released otherwise **nil**

Description:

The release-chunk-spec-id command is used to free up the memory resources used for a chunk-spec and its mapping to an id when that chunk-spec is no longer needed. If the id provided is a valid chunk-spec id then that chunk-spec will be removed from the mapping table and can be gargabe collected (assuming that there are not any other internal references to it), that id will no longer refer to a valid chunk-spec, and a true value will be returned. If the id provided is not valid then **nil** will be returned.

Examples:

```
1> (chunk-spec-to-id (define-chunk-spec isa chunk))
4
2> (release-chunk-spec-id 4)
T
3> (release-chunk-spec-id 4)
```

chunk-name-to-chunk-spec

Syntax:

chunk-name-to-chunk-spec name -> [chunk-spec | nil]

Remote command name:

chunk-name-to-chunk-spec

Arguments and Values:

```
name ::= the name of a chunk in the current model chunk-spec ::= an internal chunk-spec (Lisp calls) or a chunk-spec id (remote calls)
```

Description:

The chunk-name-to-chunk-spec command is a function which works the same as <u>define-chunk-spec</u> does when provided a chunk name as its only parameter. A chunk-spec will be created that matches that chunk exactly. It will include a slot-spec for each slot in that chunk with the = modifier and the current value of that slot in the chunk. Chunk-name-to-chunk-spec can be used as a short-cut to calling define-chunk-spec-fct with a list of a chunk name.

If the chunk-name provided names a chunk in the current model then a chunk-spec which matches that chunk is returned. If the parameter provided does not name a chunk in the current model or there is no current model then a warning will be displayed and **nil** is returned.

Examples:

```
> (chunk-name-to-chunk-spec 'free)
#S(ACT-R-CHUNK-SPEC ...)

E> (chunk-name-to-chunk-spec :not-a-chunk)
#|Warning: Chunk-name-to-chunk-spec called with a non-chunk :NOT-A-CHUNK. |#
NIL

E> (chunk-name-to-chunk-spec 'free)
#|Warning: get-chunk called with no current model. |#
#|Warning: Chunk-name-to-chunk-spec called with a non-chunk FREE. |#
NIL
```

pprint-chunk-spec

Syntax:

pprint-chunk-spec chunk-spec -> nil

Remote command name:

pprint-chunk-spec

Arguments and Values:

chunk-spec ::= a valid chunk-spec or chunk-spec id

Description:

The pprint-chunk-spec command can be used to print a chunk-spec to the model's command output trace. If the chunk-spec provided is valid then a description of that chunk-spec will be output on the model's command output trace. Each slot-spec will be output on a separate line. The = modifiers will not be printed in the output, but all other modifiers will be. If the provided parameter is not a

valid chunk-spec, then no output will be performed. If there is no current model then a warning will be printed and no output will occur. The command will always return **nil**.

Examples:

printed-chunk-spec

Syntax:

printed-chunk-spec chunk-spec {flat} -> [output | nil]

Remote command name:

printed-chunk-spec

Arguments and Values:

```
chunk-spec ::= a valid chunk-spec or chunk-spec id flat ::= a generalized boolean which indicates whether the result should contain newlines output ::= a string containing the printed chunk-spec representation
```

Description:

The printed-chunk-spec command is very similar to the pprint-chunk-spec command except that instead of printing the representation to the command trace it will be returned in a string. If the optional parameter is provided as a non-nil value then the string will not add newline characters between the slot specs. If the provided parameter is not a valid chunk-spec then it will return **nil**, and if there is no current model a warning will be printed and it will return **nil**.

Examples:

match-chunk-spec-p

Syntax:

```
match-chunk-spec-p chunk-name chunk-spec {:=test test-fn} {:-test test-fn} {:>test test-fn}
```

Remote command name:

```
match-chunk-spec-p chunk-name chunk-spec { < =test test-fn, -test test-fn, <test test-fn, <=test test-fn, <=test test-fn, variable-char var > }
```

Arguments and Values:

Description:

The match-chunk-spec-p command is used to determine if a chunk matches a chunk-spec. If it matches, then a true value is returned and if it does not match **nil** is returned.

A chunk matches the chunk-spec if every slot specified in the chunk-spec with a non-nil value exists in that chunk, every slot specified in the chunk-spec with a nil value does not exist in that chunk, and

the test of every slot in the specification with the corresponding slot value in the chunk results in a true value. Any request parameters which are a part of the chunk-spec are ignored for the purposes of matching the chunk with this command. To test the slot values, the test function which corresponds to the modifier on that slot in the chunk-spec will be called with the chunk's slot's value as the first parameter and the chunk-spec's slot-spec value as the second parameter unless the slot value specified is a variable. If the slot-spec's value is a variable, then the value bound to that variable (as described next) will be passed to the testing function. If a slot name is specified as a variable that test will be performed on the slot named by the value to which that variable is bound.

If there are any variables in the chunk-spec they are first tested for consistency and to determine their bindings before performing the slot tests. Each variable in the chunk-spec must appear as a value in at least one slot-spec which uses the = modifier. If there is a variable which does not meet that requirement the match fails. If more than one slot-spec using the = modifier contains the same variable as a value, then all slots where the = test is used with that variable as a value must have the same value (using the function for the = test) or the match will fail. If those conditions are true, then the value in that slot(s) will be bound to the variable for the remainder of the slot tests in the chunk-spec. If a variable is bound in a slot which is named with a variable then that slot name variable will be bound before the slot value can be bound. Unlike productions the specification of variablized slot names is not restricted to a single level of indirection, but if there are dependencies among the variablized slot names such that there is no valid order in which to bind the slots the matching fails.

If there is not a variable-character provided then the default character of '=' is used to denote variables in the chunk-spec.

If no test functions are specified then the default chunk matching functions are used. Those functions work as follows:

- O The = test is <u>chunk-slot-equal</u>
- O The test is the negation of using chunk-slot-equal
- O All of the inequality tests are true if
 - Both values are numbers and
 - The specified inequality holds between them with the chunk's slot value being the left of the items in the test and the chunk-spec's slot value the right.

If chunk-name, chunk-spec or one of the testing functions is invalid or there is no current model then a warning is displayed and **nil** is returned. .

Examples:

```
1> (chunk-type test slot1 slot2 slot3)
TEST
2> (define-chunks (tiny) (small) (medium) (large)
                 (slot1) (slot2)
                 (a isa test slot1 10 slot2 5)
                 (b isa test slot1 large slot2 small)
                 (c isa test slot1 medium slot2 small slot3 tiny)
                 (d isa test slot1 10 slot2 slot1)
                 (e isa test slot1 10 slot2 slot1 slot3 slot2))
(TINY SMALL MEDIUM LARGE SLOT1 SLOT2 A B C D E)
3> (defun smaller-size (x y)
     (let ((valid '(tiny small medium large huge)))
       (and (find x valid)
            (find y valid)
            (< (position x valid) (position y valid)))))</pre>
SMALLER-SIZE
4> (match-chunk-spec-p 'a (define-chunk-spec - slot1 7 >= slot2 1))
5> (match-chunk-spec-p 'a (define-chunk-spec slot1 4))
NIL
6> (match-chunk-spec-p 'a (define-chunk-spec slot1 =v < slot2 =v))
7> (match-chunk-spec-p 'a (define-chunk-spec slot1 10 :attended t))
8> (match-chunk-spec-p 'a (define-chunk-spec slot3 nil))
9> (match-chunk-spec-p 'c (define-chunk-spec slot3 nil))
10> (match-chunk-spec-p 'b (define-chunk-spec slot1 =v < slot2 =v))
NIL
11> (match-chunk-spec-p 'b (define-chunk-spec slot1 =v < slot2 =v) :<test 'smaller-size)
12> (match-chunk-spec-p 'b (define-chunk-spec slot1 $v < slot2 $v) :<test 'smaller-size)
NIL
13> (match-chunk-spec-p 'b (define-chunk-spec slot1 $v < slot2 $v) :<test 'smaller-size
                        :variable-char #\$)
Т
14> (match-chunk-spec-p 'd (define-chunk-spec =slot 10 =slot2 =slot slot3 =slot2))
15> (match-chunk-spec-p 'e (define-chunk-spec =slot 10 =slot2 =slot slot3 =slot2))
E> (match-chunk-spec-p 'bad-chunk (define-chunk-spec))
#|Warning: BAD-CHUNK does not name a chunk in call to match-chunk-spec-p. |#
NIL
E> (match-chunk-spec-p 'a 'not-a-chunk-spec)
#|Warning: NOT-A-CHUNK-SPEC is not a valid chunk-spec or chunk-spec id in call to match-
chunk-spec-p. |#
NIL
```

```
E> (match-chunk-spec-p 'a (define-chunk-spec slot1 10) :=test 'not-a-function)
#|Warning: Error #<UNDEFINED-FUNCTION @ #x2283eb5a> encountered in matching chunk A. |#
NIL

E> (match-chunk-spec-p 'a (define-chunk-spec isa chunk) :variable-char 3)
#|Warning: 3 is not a valid variable character in call to match-chunk-spec-p. |#
NIL

E> (match-chunk-spec-p nil nil)
#|Warning: Match-chunk-spec-p called with no current model. |#
NIL
```

find-matching-chunks

Syntax:

```
find-matching-chunks chunk-spec {:chunks [:all | (chunk*)]} {:=test test-fn} {:-test test-fn} {:<test test-fn} {:<test test-fn} {:variable-char var} -> result
```

Remote command name:

```
find-matching-chunks chunk-spec { [ (chunk*) | "all" ] { (< =test test-fn, -test test-fn, <test test-fn, <test test-fn, >=test test-fn, >=test test-fn, variable-char var > ) }}
```

Arguments and Values:

Description:

The find-matching-chunks command tests each chunk provided in the list of chunks provided or all chunks in the current model if it is omitted or specified as :all (or "all" for remote calls), against the chunk-spec provided. It returns the list of chunk names which match the chunk-spec using the same matching as described in match-chunk-spec-p which includes the possibility of specifying alternate testing functions and a variable character other than the default of "=".

If the chunks list contains items which do not name chunks, then for each such item a warning will be printed and that item will be ignored, but the matching will still occur for the valid chunks.

If chunk-spec, chunks, or a testing function is invalid or there is no current model then a warning is displayed and **nil** is returned.

Examples:

```
1> (chunk-type test slot1 slot2 slot3)
TEST
2> (define-chunks (tiny) (small) (medium) (large)
                   (slot1) (slot2)
                   (a isa test slot1 10 slot2 5)
                   (b isa test slot1 large slot2 small)
                   (c isa test slot1 medium slot2 small slot3 tiny)
                   (d isa test slot1 10 slot2 slot1)
                   (e isa test slot1 10 slot2 slot1 slot3 slot2))
(TINY SMALL MEDIUM LARGE SLOT1 SLOT2 A B C D E)
3> (defun smaller-size (x y)
     (let ((valid '(tiny small medium large huge)))
        (and (find x valid)
             (find y valid)
             (< (position x valid) (position y valid)))))</pre>
SMALLER-SIZE
4> (find-matching-chunks (define-chunk-spec - slot1 nil))
(ACEBD)
5> (find-matching-chunks (define-chunk-spec - slot1 nil) :chunks '(a b free busy))
(B A)
6> (find-matching-chunks (define-chunk-spec < slot1 large) :<test 'smaller-size)
7E> (find-matching-chunks (define-chunk-spec < slot1 large) :<test 'bad-function-name)
#|Warning: Function BAD-NAME passed to dispatch-apply is not a local function or valid remote command string |#
#|Warning: Function BAD-NAME passed to dispatch-apply is not a local function or valid remote command string |#
#|Warning: Function BAD-NAME passed to dispatch-apply is not a local function or valid remote command string |# #|Warning: Function BAD-NAME passed to dispatch-apply is not a local function or valid remote command string |#
#|Warning: Function BAD-NAME passed to dispatch-apply is not a local function or valid remote command string |#
NTI
E> (find-matching-chunks :not-a-chunk-spec)
#|Warning: :NOT-A-CHUNK-SPEC is not a valid chunk-spec or chunk-spec id in call to find-matching-chunks. |#
NIL
E> (find-matching-chunks (define-chunk-spec) :chunks '(not-a-chunk))
#|Warning: NOT-A-CHUNK does not name a chunk in call to match-chunk-spec-p. |#
NIL
E> (find-matching-chunks (define-chunk-spec) :chunks 'not-a-list)
#|Warning: NOT-A-LIST is not a valid value for the :chunks keyword parameter to find-matching-chunks. |#
E> (find-matching-chunks :not-a-chunk-spec)
#|Warning: Find-matching-chunks called with no current model. |#
NTI
```

chunk-spec-slots

Syntax:

chunk-spec-slots chunk-spec -> (slot*)

Remote command name:

chunk-spec-slots

Arguments and Values:

```
chunk-spec ::= a valid chunk-spec or chunk-spec id
slot ::= the name of a slot or request parameter specified in chunk-spec
```

Description:

The chunk-spec-slots command returns a list of the names of the slots and request parameters that are used in the provided chunk-spec. Each slot will occur only once in the return list no matter how many times it may be tested in chunk-spec, and the list is in no particular order. That list will include any variables which are used in the slot name position.

If chunk-spec is not a valid chunk-spec or chunk-spec-id then a warning is printed and **nil** is returned.

Examples:

```
> (chunk-spec-slots (define-chunk-spec))
NIL
> (chunk-spec-slots (define-chunk-spec color blue size =x))
(COLOR SIZE)
> (chunk-spec-slots (define-chunk-spec - color red - color green))
(COLOR)
> (chunk-spec-slots (define-chunk-spec :attended t =slot t))
(:ATTENDED =SLOT)
E> (chunk-spec-slots 'not-a-spec)
#|Warning: Chunk-spec-slots called with something other than a chunk-spec or chunk-spec-id |# NIL
```

slot-in-chunk-spec-p

Syntax:

slot-in-chunk-spec-p *chunk-spec slot ->* result

Remote command name:

slot-in-chunk-spec-p

Arguments and Values:

```
chunk-spec ::= a valid chunk-spec or chunk-spec id
slot ::= the name of a slot, variable, or request parameter
result ::= a generalized boolean indicating whether slot was found in chunk-spec
```

Description:

The slot-in-chunk-spec-p command tests whether the given slot occurs in some slot-spec of the chunk-spec provided. It returns a non-**nil** value if that slot is specified in chunk-spec and **nil** if it is not.

If chunk-spec is not a valid chunk-spec or valid chunk-spec id or if slot does not name a valid slot for chunks, a valid request parameter, or a variable then a warning is printed and **nil** is returned.

Examples:

```
> (slot-in-chunk-spec-p (define-chunk-spec size 10) 'color)
NIL
> (slot-in-chunk-spec-p (define-chunk-spec color blue size =x) 'color)
T
> (slot-in-chunk-spec-p (define-chunk-spec slot1 10 =x 20 slot2 =x) '=x)
T
E> (slot-in-chunk-spec-p 'not-a-spec nil)
#|Warning: Slot-in-chunk-spec-p called with something other than a chunk-spec or chunk-spec-id |#
NIL
E> (slot-in-chunk-spec-p (define-chunk-spec screen-x 10) 'not-slot)
#|Warning: NOT-SLOT does not name a valid slot in the current model. |#
NIL
```

chunk-spec-slot-spec

Syntax:

```
chunk-spec-slot-spec chunk-spec {slot} -> (spec-list*)
```

Remote command name:

```
chunk-spec-slot-spec chunk-spec {slot} -> ' (spec-list*) '
```

Arguments and Values:

```
chunk-spec ::= a valid chunk-spec or chunk-spec id
slot ::= the name of a slot, variable, or request parameter to find in chunk-spec
spec-list ::= (modifier slot-name value)
slot-name ::= the name of a slot, variable, or request parameter
modifier ::= [= | - | < | > | <= | >=]
value ::= any value
```

Description:

The chunk-spec-slot-spec command is used to get the slot specifications from a chunk-spec. It returns a list of specification lists. A specification list is a list of three elements. The first item in a specification list is the modifier for the slot-spec, the second element is the slot name in the slot-spec

(which could be a variable or request parameter), and the third element is the value in the slot-spec. If no slot is specified, then a specification list is returned for each slot-spec in the chunk-spec and the specification lists will be in the same order as the slot-specs were provided when the chunk-spec was defined.

If a slot is specified, then only the specification lists which reference that slot are returned, again in the order that they were provided when the chunk-spec was defined. If a slot is specified for chunk-spec-slot-spec and there are no slot-specs in the chunk-spec which use that slot then **nil** will be returned.

If chunk-spec is not a valid chunk-spec then a warning is printed and **nil** is returned.

Examples:

```
1> (defvar *test-spec* (define-chunk-spec < screen-x 10
                                          > screen-x 0
                                          screen-x =var
                                          color blue
                                          - screen-y =var
                                          :attended t))
*TEST-SPEC*
2> (chunk-spec-slot-spec *test-spec*)
((< SCREEN-X 10) (> SCREEN-X 0) (= SCREEN-X =VAR) (= COLOR BLUE) (- SCREEN-Y =VAR)
 (= :ATTENDED T))
3> (chunk-spec-slot-spec *test-spec* 'color)
((= COLOR BLUE))
4> (chunk-spec-slot-spec *test-spec* 'screen-x)
((< SCREEN-X 10) (> SCREEN-X 0) (= SCREEN-X =VAR))
5> (chunk-spec-slot-spec *test-spec* :attended)
((= :ATTENDED T))
6> (chunk-spec-slot-spec *test-spec* 'size)
NIL
E> (chunk-spec-slot-spec 'not-a-spec)
#|Warning: Chunk-spec-slot-spec was not passed a valid chunk-spec or chunk-spec id |#
NIL
```

slot-spec-modifier/slot-spec-slot/slot-spec-value

Syntax:

```
slot-spec-modifier slot-spec-list -> modifier
slot-spec-slot slot-spec-list -> slot
slot-spec-value slot-spec-list -> value
```

Remote command name:

slot-spec-modifier slot-spec-slot slot-spec-value

Arguments and Values:

```
slot-spec-list ::= a three element list describing a slot-spec as returned by chunk-spec-slot-spec modifier ::= [= |-| < | > | <= | >=] slot ::= the name of the slot, request parameter, or variable in the slot name position of slot-spec-list value ::= the value from the value position of slot-spec-list
```

Description:

The slot-spec-* commands can be used to access the corresponding components of a slot-spec list as returned by <u>chunk-spec-slot-spec</u>. They are not really necessary since a slot-spec list is just a three element list, but it can be cleaner in code to see an accessor name than a generic index function like first, second, third, or something like nth.

If the slot-spec-list isn't a three element list then all of these will print a warning and return **nil**. [There is currently no way to distinguish an actual slot-spec-value of **nil** from one returned because of an invalid list other than the warning message, but if the slot-spec-list comes from one of the other commands it should always be valid.]

Examples:

```
1> (setf *spec-list* (first (chunk-spec-slot-spec (define-chunk-spec color blue))))
(= COLOR BLUE)

2> (slot-spec-modifier *spec-list*)
=
3> (slot-spec-slot *spec-list*)
COLOR

4> (slot-spec-value *spec-list*)
BLUE

E> (slot-spec-modifier nil)
#|Warning: Invalid slot-spec list NIL passed to slot-spec-modifier. |#
NIL

E> (slot-spec-slot nil)
#|Warning: Invalid slot-spec list NIL passed to slot-spec-slot. |#
NIL

E> (slot-spec-value nil)
#|Warning: Invalid slot-spec list NIL passed to slot-spec-value. |#
NIL

E> (slot-spec-value nil)
#|Warning: Invalid slot-spec list NIL passed to slot-spec-value. |#
NIL
```

chunk-spec-variable-p

Syntax:

chunk-spec-variable-p value {var} -> result

Remote command name:

chunk-spec-variable-p

Arguments and Values:

```
value ::= any value
var ::= a character (Lisp command) or one character string (remote)
result ::= a generalized boolean
```

Description:

The chunk-spec-variable-p command can be used to determine if a value would be considered as a variable in a chunk-spec. If the value is a name with length greater than one and the first character of the name is the same as var (or '=' if var is not specified) then a true value is returned otherwise **nil** is returned.

Examples:

```
> (chunk-spec-variable-p 'value)
NIL
> (chunk-spec-variable-p '=value)
T
> (chunk-spec-variable-p '@value #\@)
T
> (chunk-spec-variable-p '=value #\@)
NIL
> (chunk-spec-variable-p "=value")
NIL
```

chunk-spec-to-chunk-def

Syntax:

```
chunk-spec-to-chunk-def chunk-spec -> [ chunk-def | nil]
```

Remote command name:

```
chunk-spec-to-chunk-def chunk-spec -> [ ' chunk-def ' | nil]
```

Arguments and Values:

```
chunk-spec ::= a valid chunk-spec or chunk-spec id chunk-def ::= a chunk definition list which is valid for passing to <u>define-chunks</u>
```

Description:

The chunk-spec-to-chunk-def command can be used to convert a chunk-spec into a list which can be passed to <u>define-chunks</u> for creating a chunk. To be able to create a chunk definition the chunk-spec must meet the following conditions:

- It must specify each slot no more than once
- It must not have any modifiers other than =
- There must not be any variables in the specification

Any request parameters in the chunk-spec are ignored unless they contain variables, in which case they fall under the third case above. If chunk-spec is a valid chunk-spec and meets the three criteria shown then this command returns a list which contains a definition for a chunk based on the slot-specs in the chunk-spec. If chunk-spec is not a valid chunk-spec or one or more of the three conditions specified above is not true then a warning is printed and **nil** is returned. Note that although **nil** would be a valid return value for a chunk-spec that has no slots, instead such a situation will return the list (isa chunk) to provide a non-**nil** value upon success.

The primary use of this command is by modules like <u>goal</u> and <u>imaginal</u> which create new chunks based on requests.

Examples:

```
> (chunk-spec-to-chunk-def (define-chunk-spec))
(ISA CHUNK)
> (chunk-spec-to-chunk-def (define-chunk-spec color blue = size 10))
(COLOR BLUE SIZE 10)
> (chunk-spec-to-chunk-def (define-chunk-spec color blue :attended t))
(COLOR BLUE)
E> (chunk-spec-to-chunk-def (define-chunk-spec - color blue))
#|Warning: Chunk-spec may only use the = modifier in a call to chunk-spec-to-chunk-def. |#
NIL
E> (chunk-spec-to-chunk-def (define-chunk-spec color blue color red))
#|Warning: Chunk-spec may only specify a slot once in a call to chunk-spec-to-chunk-def. |#
NIL
E> (chunk-spec-to-chunk-def (define-chunk-spec color blue :attended =val))
#|Warning: Chunk-spec has variables in the values in a call to chunk-spec-to-chunk-def. |#
NIL
E> (chunk-spec-to-chunk-def (define-chunk-spec =slot value))
#|Warning: Chunk-spec has variablized slots in a call to chunk-spec-to-chunk-def. |#
NIL
E> (chunk-spec-to-chunk-def 'not-a-chunk-spec)
#|Warning: Chunk-spec-to-chunk-def called with something other than a chunk-spec. |#
```

verify-single-explicit-value

Syntax:

verify-single-explicit-value chunk-spec slot-name module-name cmd { var } -> [value | nil] [t | nil]

Remote command name:

verify-single-explicit-value chunk-spec slot-name module-name cmd { var } -> [' value ' | nil] [t | nil]

Arguments and Values:

```
chunk-spec ::= a valid chunk-spec or chunk-spec id
slot-name ::= the name of a slot or request parameter
module-name ::= a name of a module to display in the warning
cmd ::= a value to display as a command in a warning
var ::= a character or string of a character to consider as the variable indicator
value ::= the value from the specified slot of the chunk-spec
```

Description:

The verify-single-explicit-value command can be used to get the value of a particular slot or request parameter slot-spec in a chunk-spec while also testing for the following conditions:

- the slot occurs exactly once in the chunk-spec
- it uses the = modifier
- it has a non-variable value based on the var character specified or '=' if var is not provided

If any of those conditions are violated then a warning is printed using the module-name and cmd value provided to create the warning message. After printing the warning message it returns two **nil** values.

If all of those conditions are satisfied then the function will return the value of that slot in the chunkspec as its first return value and **t** as its second return value to indicate success since **nil** could be the value of the slot in the chunk-spec.

This command is used by several of the provided modules in processing their requests and may be of use to those implementing new modules.

Examples:

```
1> (setf *test-spec* (define-chunk-spec color blue - size 10 :attended =x value 3 value 4
                                        name &x))
#S(ACT-R-CHUNK-SPEC ...)
2> (verify-single-explicit-value *test-spec* 'color 'test-module 'test-command)
Т
3E> (verify-single-explicit-value *test-spec* 'size 'test-module 'test-command)
#|Warning: TEST-COMMAND command to TEST-MODULE module requires a value for the SIZE slot. |#
NTI
NIL
4E> (verify-single-explicit-value *test-spec* 'value 'test-module 'test-command)
#|Warning: VALUE slot may only be specified once in a TEST-COMMAND command to the TEST-
MODULE module. |#
NIL
NIL
5E> (verify-single-explicit-value *test-spec* :attended 'test-module 'test-command)
#|Warning: ATTENDED slot must be explict - not a variable in a TEST-COMMAND command to the
TEST-MODULE module. |#
NIL
NIL
6> (verify-single-explicit-value *test-spec* :attended 'test-module 'test-command #\&)
=X
Т
7> (verify-single-explicit-value *test-spec* 'name 'test-module 'test-command)
ХS
Т
8E> (verify-single-explicit-value *test-spec* 'name 'test-module 'test-command #\&)
#|Warning: NAME slot must be explict - not a variable in a TEST-COMMAND command to the
TEST-MODULE module. |#
NIL
NIL
9E> (verify-single-explicit-value 'not-a-spec 'name 'test-module 'test-command #\&)
#|Warning: NOT-A-SPEC is not a chunk-spec in TEST-COMMAND command to the TEST-MODULE
module. I#
NIL
NIL
```

test-for-clear-request

Syntax:

test-for-clear-request chunk-spec -> result

Remote command name:

test-for-clear-request

Arguments and Values:

chunk-spec ::= a valid chunk-spec or chunk-spec id
result ::= a generalized boolean indicating whether the chunk-spec indicates a typical clear request

Description:

The test-for-clear-request command can be used to determine if a chunk-spec has the format of the "clear" requests handled by many modules. It will return true if it is passed a chunk-spec that has only one slot-spec in it and that slot-spec is either: "= **cmd clear**" or "= **clear** *true*" where *true* is any non-**nil** value. Otherwise it will return **nil**.

This command is used by several of the provided modules in processing their requests and may be of use to those implementing new modules.

Examples:

```
> (test-for-clear-request (define-chunk-spec clear t))
T
> (test-for-clear-request (define-chunk-spec cmd clear))
T
> (test-for-clear-request (define-chunk-spec isa clear))
T
> (test-for-clear-request (define-chunk-spec clear nil))
NIL
> (test-for-clear-request (define-chunk-spec - cmd clear))
NIL
> (test-for-clear-request (define-chunk-spec clear t cmd clear))
NIL
> (test-for-clear-request (define-chunk-spec clear t cmd clear))
NIL
```

chunk-difference-to-chunk-spec

Syntax:

chunk-difference-to-chunk-spec chunk1 chunk2 -> [chunk-spec | nil]

Remote command name:

chunk-difference-to-chunk-spec

Arguments and Values:

```
chunk1 ::= the name of a chunk
chunk2 ::= the name of a chunk
chunk-spec ::= a chunk-spec (internal) or chunk-spec id (remote)
```

Description:

The chunk-difference-to-chunk-spec command can be used to create a chunk-spec that contains the modifications necessary to convert chunk2 into chunk1. That chunk-spec could be passed to modbuffer-chunk to perform the modifications if chunk2 were in the desired buffer. If chunk1 and chunk2 are the names of chunks in the current model then a chunk-spec is created which has all of the slots from chunk1 as would be created from chunk-name-to-chunk-spec for that chunk and also includes slot-specs for each of the slots of chunk2 which must be removed specified with **nil**.

If either chunk1 or chunk2 is not the name of a chunk in the current model or there is no current model then warnings will be displayed and **nil** will be returned.

Examples:

```
1> (define-chunks (a value 1 color blue) (b value 3 color blue size 5))
(A B)
2> (chunk-difference-to-chunk-spec 'a 'b)
#S(ACT-R-CHUNK-SPEC ...)
3> (pprint-chunk-spec *)
    SIZE NIL
    COLOR BLUE
    VALUE 1
NIL
E> (chunk-difference-to-chunk-spec :bad :names)
#|Warning: Chunk-difference-to-chunk-spec called with :BAD and :NAMES which are not both
chunks. |#
NIL
E> (chunk-difference-to-chunk-spec 'a 'b)
#|Warning: get-chunk called with no current model. |#
#|Warning: get-chunk called with no current model. |#
#|Warning: Chunk-difference-to-chunk-spec called with A and B which are not both chunks. |#
NIL
```

Using Buffers

In the <u>earlier section on buffers</u> their role in the system was described and the commands which a modeler may use to inspect and query the buffers were presented. This section is going to describe the commands that allow one to manipulate the chunk in a buffer and to use the buffer to interact with modules directly. These commands are generally used when one is creating a new module, but may also be useful for other purposes.

There are several things which one can do with a buffer. They are: read the chunk that it holds, test if the buffer is empty, query the state of the buffer and its module, request an action of the buffer's module, modify the chunk in the buffer, clear the chunk from the buffer, place a new chunk into the buffer, overwrite the chunk in the buffer, and set the failure flag of the buffer. The commands for performing those actions will be detailed below. Creation of buffers is not described in this section because buffers are only created when modules are defined – buffers only exist in conjunction with a module. Thus buffer creation will be described in the section on <u>creating modules</u>.

Any buffer may be accessed for any of the operations at any time. With the provided modules, only the <u>procedural module</u> directly accesses the buffers belonging to other modules, but there is nothing that prevents other module-to-module communication or interaction. Modules receive the requests sent to them regardless of where they come from or how they are created. However most modules only accept one request at a time and the procedural module's requests from productions are delayed relative to their testing of a module's state i.e. a production queries the module to determine if it is free to accept requests but does not send a request until 50ms later (by default). So, if you plan on using the buffers for requests between modules you may want to take care with how the productions in any models which operate in that situation also issue requests.

Also, while it is possible to write to any buffer at any time, generally only the owning module should be storing chunks into its buffer. Often the module responds to a request by placing a chunk into the buffer, and thus if one were to arbitrarily write a chunk into the buffer while it was processing a request it could lead to problems in a model which made a request and was expecting a particular result. Again, the procedural module's productions are typically the primary source of requests and are typically written to expect a result consistent with the request. Thus, if you write a module or other code which modifies buffers explicitly, care should be taken when using that in conjunction with the normal production processing of a model.

For many of these commands there are two versions. One which performs an immediate action and one which schedules the action to occur as an event. In general, the scheduled versions of the requests and modifications are preferable to the non-scheduled ones because they will then be recorded in the trace and thus be detectable by other things and also be ordered appropriately. However, sometimes it may be necessary to use the immediate version, and in particular, the reading and testing functions often need to be done immediately because the current result is what is important.

In addition to the commands for using the buffers, there are also some additional commands described below for accessing other buffer information. One allows one to find the name of the buffer's owning module. This may be useful when implementing tracing tools or other event monitoring utilities which might have access to only the buffer names. Another allows one to find the value of the buffer's activation spread parameter without knowing the name of the parameter the module has made available for that purpose. That may be useful when developing alternative equations for the spreading activation calculation or for creating tools for monitoring and tracking the activation calculations.

Commands

buffer-read

Syntax:

Remote command name:

buffer-read

Arguments and Values:

```
buffer ::= the name of a buffer
chunk-name ::= the name of a chunk which is in the buffer
time-delta ::= a number indicating when to schedule the event
module ::= a symbol which will be used as the module of the event in the trace
priority ::= [ :max | :min | priority-val]
priority-val ::= a number indicating the priority to use for the event
output ::= [t | high | medium | low | nil]
time-units ::= a generalized boolean indicating whether time-delta is in seconds or milliseconds
```

(default is **nil** which means seconds) event-id ::= an integer which can be used to reference the event created

Description:

The buffer-read commands are used to read the name of the chunk which is currently in the named buffer of the current model.

For buffer-read, the name of the chunk is returned directly. If the buffer is empty the return value is **nil.** If the buffer named is invalid or there is no current model or current meta-process then a warning is printed and **nil** is returned.

Schedule-buffer-read is used to record a buffer reference in the trace of the model. It schedules an event to occur as if the following was executed:

The default values for the parameters are **:none** for module, 0 for priority, and **t** for output if not provided. The buffer-read-action function essentially does nothing and is only there to record a reference for the trace. It returns the event that is scheduled. If any of the parameters are not valid or there is no current model or current meta-process then a warning is printed, **nil** is returned and nothing is scheduled.

Buffer-read-report is used to read a buffer's chunk and have a record of the buffer-read recorded in the trace of the model. It is essentially a combination of buffer-read and schedule-buffer-read. It schedules an event to occur as if the following were executed:

The name of the chunk currently in the named buffer is returned. If the buffer is empty then **nil** is returned. If the buffer named is invalid or there is no current model then a warning is printed and **nil** is returned.

This example assumes that the model starts with no chunk in the goal buffer and has the :trace-detail parameter set to **high**.

```
1> (buffer-read 'goal)
NIL
2> (goal-focus free)
FREE
3> (run .1)
    0.000
             GOAL
                                    SET-BUFFER-CHUNK GOAL FREE REQUESTED NIL
                                    CONFLICT-RESOLUTION
    0.000
             PROCEDURAL
    0.000
                                    Stopped because no events left to process
             -----
0.0
NIL
4> (buffer-read 'goal)
FREE-0
5> (schedule-buffer-read 'goal .2)
6> (mp-show-queue)
Events in the queue:
    0.200
            NONE
                                    BUFFER-READ-ACTION GOAL
    0.200
             PROCEDURAL
                                    CONFLICT-RESOLUTION
2
7> (run .2)
     0.200
             NONE
                                    BUFFER-READ-ACTION GOAL
     0.200
             PROCEDURAL
                                    CONFLICT-RESOLUTION
     0.200
             _ _ _ _ _
                                    Stopped because time limit reached
0.2
2
NIL
8> (buffer-read-report 'goal :module 'test-module)
FREE-0
9> (mp-show-queue)
Events in the queue:
           TEST-MODULE
    0.200
                                    BUFFER-READ-ACTION GOAL
    0.200
             PROCEDURAL
                                    CONFLICT-RESOLUTION
2
E> (buffer-read 'bad-name)
#|Warning: Buffer-read called with an invalid buffer name BAD-NAME |#
NIL
E> (schedule-buffer-read 'bad-name .1)
#|Warning: schedule-buffer-read called with an invalid buffer name BAD-NAME |#
E> (schedule-buffer-read 'goal 'bad-time)
#|Warning: schedule-buffer-read called with a non-number time-delta: BAD-TIME |#
NIL
E> (schedule-buffer-read 'goal '.1 :priority 'bad)
#|Warning: schedule-buffer-read called with an invalid priority BAD |#
NIL
E> (buffer-read-report 'bad-name)
#|Warning: buffer-read-report called with an invalid buffer name BAD-NAME |#
```

```
NIL
E> (buffer-read 'goal)
#|Warning: buffer-read called with no current model. |#
```

query-buffer

Syntax:

Arguments and Values:

Description:

The query-buffer commands are used to query the state of the buffer and/or its module in the current model. The query provided may be specified either as a list of query items, a chunk-spec containing slot-specs that are valid queries, or a chunk-spec id of a valid query chunk-spec. A query list must contain two or three items per query and may contain any number of queries. Within a single query the optional item is a modifer to use which can be either = or -, with = being a test that the query is true and - being a test that it is false. The default is = if not provided. The next item in the query is the name of the query and that is followed by the value to be tested for that query. A valid chunk-spec for a query would be one that was created with a specification as described for the query list.

For query-buffer each of the queries specified is tested from left to right and if they all return true then query-buffer returns **t**. If any query fails, then **nil** is returned without making any more queries.

If the buffer named is invalid, any of the queries are not valid for the buffer or module, or there is no current model then a warning is printed and **nil** is returned.

Schedule-query-buffer is used to record buffer querying in the trace of the model. It schedules an event to occur as if the following was executed:

The default values for the parameters are **:none** for module, 0 for priority, and **t** for output if not provided. The query-buffer-action function essentially does nothing and is only there to record a reference for the trace. It returns the event-id of the scheduled event. If any of the parameters are not valid or there is no current model then a warning is printed, **nil** is returned and nothing is scheduled.

Examples:

This example assumes that the model starts with no chunk in the goal and buffer and has the :trace-detail parameter set to **high**.

```
1> (query-buffer 'goal '(state free))
2> (query-buffer 'goal '(= buffer empty error nil))
3> (query-buffer 'goal (define-chunk-spec - buffer full error nil))
4> (query-buffer 'goal nil)
5> (query-buffer 'goal '(state busy))
6> (schedule-query-buffer 'goal '(buffer empty) .1)
7> (mp-show-queue)
Events in the queue:
                                    CHECK-FOR-ESC-NIL #S(CENTRAL-PARAMETERS ...)
     0.000
             NONE
    0.000
             PROCEDURAL
                                    CONFLICT-RESOLUTION
    0.100
             NONE
                                    QUERY-BUFFER-ACTION GOAL
3
8> (run .1)
     0.000
             PROCEDURAL
                                    CONFLICT-RESOLUTION
    0.100
             NONE
                                    QUERY-BUFFER-ACTION GOAL
    0.100
             PROCEDURAL
                                    CONFLICT-RESOLUTION
    0.100
                                    Stopped because time limit reached
             -----
```

```
0.1
4
NIL
E> (query-buffer 'bad-name nil)
#|Warning: query-buffer called with an invalid buffer name BAD-NAME |#
E> (query-buffer 'goal '(bad-query free))
#|Warning: Invalid query name BAD-QUERY in call to define-query-spec. |#
#|Warning: Invalid query-buffer of buffer GOAL with queries-list-or-spec (BAD-QUERY FREE)
NIL
E> (schedule-query-buffer 'bad-name nil .1)
#|Warning: schedule-query-buffer called with an invalid buffer name BAD-NAME |#
NIL
E> (query-buffer 'goal '(< state free))</pre>
#|Warning: Query specs only allow = or - modifiers. |#
#|Warning: Invalid query-buffer of buffer GOAL with queries-list-or-spec (< STATE FREE) |#
E> (schedule-query-buffer 'goal (define-chunk-spec < state free) .1)
#|Warning: schedule-query-buffer called with an invalid query specification
 #S(ACT-R-CHUNK-SPEC ...))) |#
NIL
E> (schedule-query-buffer 'goal nil nil)
#|Warning: schedule-query-buffer called with non-number time-delta: NIL |#
NIL
E> (schedule-query-buffer 'goal nil 1.0 :priority 'bad)
#|Warning: schedule-query-buffer called with an invalid priority BAD |#
E> (query-buffer 'goal nil)
#|Warning: query-buffer called with no current model. |#
NTI
```

clear-buffer

Syntax:

Remote command name:

clear-buffer

Arguments and Values:

```
buffer ::= the name of a buffer chunk-name ::= the name of the chunk which is in the buffer time-delta ::= a number indicating when to schedule the event module ::= a name which will be used to as the module of the event and in the trace priority ::= [:max | :min | priority-val]
```

Description:

The clear-buffer commands are used to clear any chunk which may be in a buffer which will leave the buffer empty, and it will also clear the buffer's failure flag if it is set. Any module which is monitoring for buffer clearing will be notified that the chunk has been cleared – in particular the declarative module will merge the cleared chunk into the model's declarative memory.

For clear-buffer, the buffer is cleared immediately and the name of the chunk which is in the buffer currently is returned. If the buffer is empty the return value is **nil**. If the buffer named is invalid or there is no current model then a warning is printed and **nil** is returned.

Schedule-clear-buffer is used to schedule the clearing of the buffer such that it occurs during the running of the model. It schedules an event to occur as if the following was executed:

The default values for the parameters are **:none** for module, 0 for priority, and **low** for output if not provided. It returns the event that is scheduled. If any of the parameters are not valid or there is no current model then a warning is printed, **nil** is returned and nothing is scheduled.

Examples:

This example assumes that the model starts with no chunk in the goal buffer.

```
4> (clear-buffer 'goal)
FREE-0
5> (buffer-read 'goal)
NIL
6> (goal-focus free)
FREE
7> (schedule-clear-buffer 'goal .2 :module 'example)
8> (run 1)
    0.200
            EXAMPLE
                                    CLEAR-BUFFER GOAL
    0.200 PROCEDURAL
                                    CONFLICT-RESOLUTION
    0.200
                                    Stopped because no events left to process
0.2
2
NIL
9> (buffer-read 'goal)
NIL
E> (clear-buffer 'bad-name)
#|Warning: clear-buffer called with an invalid buffer name BAD-NAME |#
E> (schedule-clear-buffer 'bad-name .1)
#|Warning: schedule-clear-buffer called with an invalid buffer name BAD-NAME |#
E> (schedule-clear-buffer 'goal nil)
#|Warning: schedule-clear-buffer called with a non-number time-delta: NIL |#
E> (clear-buffer 'goal)
#|Warning: clear-buffer called with no current model. |#
```

set-buffer-chunk

Syntax:

Remote command name:

```
set-buffer-chunk
schedule-set-buffer-chunk buffer chunk-name time-delta { < module module, priority priority,
time-in-ms time-units, requested requested, output output > }
```

Arguments and Values:

```
buffer ::= the name of a buffer
chunk-name ::= the name of a chunk
new-chunk-name ::= the name of a new chunk
```

```
requested ::= a generalized boolean

time-delta ::= a number indicating when to schedule the event

module ::= a name which will be used to as the module of the event and in the trace

priority ::= [ :max | :min | priority-val]

priority-val ::= a number indicating the priority to use for the event

output ::= [t | high | medium | low | nil]

time-units ::= a generalized boolean indicating whether time-delta is in seconds or milliseconds

(default is nil which means seconds)

event-id ::= an integer which can be used to reference the event created
```

Description:

The set-buffer-chunk commands are used to copy a chunk into a buffer. It will always make a copy of the chunk specified, and then place that copy into the buffer. Before it places the new chunk into the buffer, it will first clear the buffer. Thus, any chunk which may be there will be cleared as described for the <u>clear-buffer command</u>. The buffer clearing is not scheduled, thus there will not be an event in the trace to indicate explicitly that the buffer was cleared.

For set-buffer-chunk, the buffer is cleared and then set immediately with the copied chunk and the name of the chunk which is placed into the buffer is returned. If either the buffer or chunk named is invalid or there is no current model then a warning is printed and **nil** is returned.

The optional requested parameter specifies whether the buffer will indicate that the chunk was requested or not. If requested is specified as **t** (which is the default) or any other true value, then the setting of the chunk is to be interpreted as being the result of a request to a module and the query of that buffer for "buffer requested" will be true. If the requested parameter is specified as **nil**, which should be done when the setting of the chunk is not the result of a module request, then the "buffer requested" query for the buffer will be **nil** and the "buffer unrequested" query will be true. An example of when the requested value should be **nil** is the buffer stuffing which the <u>visual-location</u> <u>buffer</u> performs when there is a screen change. That does not happen because of an explicit request to the module, and thus if a chunk is placed into the buffer it should be marked accordingly.

Schedule-set-buffer-chunk is used to schedule the setting of the buffer such that it occurs during the running of the model. It schedules an event to occur as if the following was executed:

The default values for the parameters are **:none** for module, 0 for priority, and **low** for output if not provided. It returns the event that is scheduled. If any of the parameters are not valid or there is no current model then a warning is printed, **nil** is returned and nothing is scheduled.

```
1> (define-chunks (a) (b color b) (c name c))
(A B C)
2> (dm)
NIL
3> (set-buffer-chunk 'goal 'a)
A-0
4> (buffer-chunk goal)
GOAL: A-0 [A]
A-0
(A-0)
5> (dm)
NIL
6> (schedule-set-buffer-chunk 'goal 'b .1)
7> (run 1)
     0.000
             PROCEDURAL
                                     CONFLICT-RESOLUTION
     0.100
                                     SET-BUFFER-CHUNK GOAL B
             NONE
     0.100
             PROCEDURAL PROCEDURAL
                                     CONFLICT-RESOLUTION
     0.100
                                     Stopped because no events left to process
0.1
NIL
8> (dm)
A-0
(A-0)
9> (buffer-chunk goal)
GOAL: B-0 [B]
B-0
   COLOR B
(B-0)
10> (query-buffer 'goal '(buffer requested))
11> (set-buffer-chunk 'goal 'c :requested nil)
C-0
12> (buffer-chunk goal)
GOAL: C-0 [C]
C-0
   NAME C
(C-0)
13> (dm)
```

```
B-0
  COLOR B
A-0
(B-0 A-0)
14> (query-buffer 'goal '(buffer requested))
15> (query-buffer 'goal '(buffer unrequested))
E> (set-buffer-chunk 'bad-name 'a)
#|Warning: set-buffer-chunk called with an invalid buffer name BAD-NAME |#
NIL
E> (set-buffer-chunk 'goal 'bad-name)
#|Warning: set-buffer-chunk called with an invalid chunk name BAD-NAME |#
E> (schedule-set-buffer-chunk 'goal 'b nil)
#|Warning: schedule-set-buffer-chunk called with time-delta that is not a number: NIL |#
E> (set-buffer-chunk 'goal 'a)
#|Warning: set-buffer-chunk called with no current model. |#
NİL
```

overwrite-buffer-chunk

Syntax:

Arguments and Values:

Description:

The overwrite-buffer-chunk commands are used to copy a chunk into a buffer like <u>set-buffer-chunk</u>. It will always make a copy of the chunk specified, and then place that copy into the buffer. The difference between overwrite-buffer-chunk and set-buffer-chunk is that the overwrite operation does not clear the buffer first. Thus, if there is a chunk in the buffer when the overwrite-buffer-chunk command is issued there will be no clearing of that chunk and no modules will be notified that it has been cleared. One specific consequence of that is that the previous chunk in the buffer, if there was one, will not be collected by the declarative module and added to the model's declarative memory.

Typically, one will use set-buffer-chunk when building a module or otherwise working with the buffers. However, there are rare situations where the model or a module may want to destructively erase a chunk which is in a buffer with this command.

The requested keyword parameter specifies whether the buffer will indicate that the chunk was requested or not. If requested is specified as **t** or any other true value, then the setting of the chunk is to be interpreted as being the result of a request to a module and the query of that buffer for "buffer requested" will be true. If the requested keyword parameter is specified as **nil** (which is the default value), which should be done when the setting of the chunk is not the result of a module request, then the "buffer requested" query for the buffer will be **nil** and the "buffer unrequested" query will be true.

For overwrite-buffer-chunk, the buffer is set immediately to hold the newly copied chunk and the name of the copy of the chunk which is placed into the buffer is returned. If either the buffer or chunk named is invalid or there is no current model then a warning is printed and **nil** is returned.

Schedule-overwrite-buffer-chunk is used to schedule the setting of the buffer such that it occurs during the running of the model. It schedules an event to occur essentially as if the following was executed:

The default values for the parameters are **:none** for module, 0 for priority, and **low** for output if not provided. It returns the event that is scheduled. If any of the parameters are not valid or there is no current model then a warning is printed, **nil** is returned and nothing is scheduled.

```
1> (define-chunks (a) (b color b) (c name c))
```

```
(A B C)
2> (dm)
NIL
3> (overwrite-buffer-chunk 'goal 'a)
4> (buffer-chunk goal)
GOAL: A-0 [A]
A-0
(A-0)
5> (dm)
NIL
6> (schedule-overwrite-buffer-chunk 'goal 'b .1)
7> (run 1)
     0.000
             PROCEDURAL
                                    CONFLICT-RESOLUTION
                                    OVERWRITE-BUFFER-CHUNK GOAL B REQUESTED NIL
     0.100
             NONE
             PROCEDURAL
     0.100
                                    CONFLICT-RESOLUTION
     0.100
                                    Stopped because no events left to process
             -----
0.1
4
NIL
8> (dm)
NIL
9> (buffer-chunk goal)
GOAL: B-0 [B]
B-0
  COLOR B
(B-0)
10> (query-buffer 'goal '(buffer requested))
11> (overwrite-buffer-chunk 'goal 'c :requested t)
12> (buffer-chunk goal)
GOAL: C-0 [C]
C-0
  NAME C
(C-0)
13> (dm)
NIL
14> (query-buffer 'goal '(buffer requested))
E> (overwrite-buffer-chunk 'bad-name 'a)
#|Warning: overwrite-buffer-chunk called with an invalid buffer name BAD-NAME |#
E> (overwrite-buffer-chunk 'goal 'bad-name)
#|Warning: overwrite-buffer-chunk called with an invalid chunk name BAD-NAME |#
E> (schedule-overwrite-buffer-chunk 'goal 'a nil)
```

```
#|Warning: schedule-overwrite-buffer-chunk called with a non-number time-delta: NIL |#
NIL

E> (overwrite-buffer-chunk 'goal 'a)
#|Warning: overwrite-buffer-chunk called with no current model. |#
NII
```

mod-buffer-chunk

Syntax:

```
mod-buffer-chunk buffer modifications -> [ chunk-name | nil ]
schedule-mod-buffer-chunk buffer modifications time-delta {:module module} {:priority priority}
{:output output} {:time-in-ms time-units} -> [event-id | nil]
```

Remote command name:

```
mod-buffer-chunk schedule-mod-buffer-chunk buffer modifications time-delta { < module module, priority priority, time-in-ms time-units, output output > }
```

Arguments and Values:

Description:

The mod-buffer-chunk commands are used to make modifications to the chunk which is in a buffer. It works similar to the <u>mod-chunk command</u>, but there are a few differences between mod-chunk and mod-buffer-chunk. The first is that instead of providing the name of a chunk, a buffer is named and the chunk which is in that buffer is the one which is modified. Another is that in addition to providing a list of slot-value pairs to specify the modifications to make mod-buffer-chunk will also accept a <u>chunk-spec</u> with slot-specs that indicate the modifications to make (such a chunk-spec must

only use the modifier = in the slot-specs). Finally, if a slot specified in the modification is not currently a possible slot it will be added to the possible slots using the <u>extend-possible-slots</u> <u>command</u> before the modifications are performed.

If there is a chunk in the buffer which is named and the modifications provided are valid then those modifications are made to that chunk. To be valid, the modifications may only specify each slot once. If any value specified for a slot in the modification is a symbol and not the name of a chunk in the current model then it is created as a new chunk with no slots and a warning is displayed before the modification is made.

For mod-buffer-chunk, if there is not a chunk in the named buffer, the modifications provided are not valid, or there is no current model then a warning is displayed, no changes are made, and **nil** is returned.

If there is a chunk in the buffer and the modifications are valid, then the chunk is modified and the name of that chunk is returned.

Schedule-mod-buffer-chunk is used to schedule the modifications to the chunk in the buffer such that it occurs during the running of the model. It schedules an event to occur as if the following was executed:

The default values for the parameters are **:none** for module, 0 for priority, and **low** for output if not provided. It returns the event that is scheduled. If any of the parameters are not valid or there is no current model then a warning is printed, **nil** is returned and nothing is scheduled.

When schedule-mod-buffer-chunk is called with a slot that is not currently a possible slot name the extention will be performed immediately at the time it is called and not at the scheduled time for the modification.

```
1> (define-chunks (a))
(A)
```

```
2> (set-buffer-chunk 'goal 'a)
A-0
3> (buffer-chunk goal)
GOAL: A-0 [A]
A-0
(A-0)
4> (mod-buffer-chunk 'goal '(color blue))
A-0
5> (buffer-chunk goal)
GOAL: A-0
A-0
  COLOR BLUE
(A-0)
6> (schedule-mod-buffer-chunk 'goal (define-chunk-spec size 10) .1)
7> (mp-show-queue)
Events in the queue:
    0.000
            NONE
                                    CHECK-FOR-ESC-NIL #S(CENTRAL-PARAMETERS ...)
    0.000
             PROCEDURAL
                                    CONFLICT-RESOLUTION
    0.100
            NONE
                                    MOD-BUFFER-CHUNK GOAL
8> (run .1)
             PROCEDURAL
    0.000
                                    CONFLICT-RESOLUTION
    0.100
            NONE
                                    MOD-BUFFER-CHUNK GOAL
    0.100
            PROCEDURAL
                                    CONFLICT-RESOLUTION
    0.100
                                    Stopped because time limit reached
0.1
NIL
9> (buffer-chunk goal)
GOAL: A-0
A-0
  COLOR BLUE
  SIZE 10
(A-0)
10E> (mod-buffer-chunk 'goal '(size 11 new-slot new-chunk))
#|Warning: Chunks extended with slot NEW-SLOT during a chunk-spec definition. |#
#|Warning: Creating chunk NEW-CHUNK with no slots |#
A-0
11> (buffer-chunk goal)
GOAL: A-0
A-0
  COLOR BLUE
   SIZE 11
  NEW-SLOT NEW-CHUNK
12E> (schedule-mod-buffer-chunk 'goal '(new-new-slot t color nil) .1)
#|Warning: Chunks extended with slot NEW-NEW-SLOT during a chunk-spec definition. |#
13> (buffer-chunk goal)
GOAL: A-0
A-0
```

```
COLOR BLUE
  SIZE 11
  NEW-SLOT NEW-CHUNK
(A-0)
14> (run .1)
     0.200
             NONE
                                    MOD-BUFFER-CHUNK GOAL
    0.200
             PROCEDURAL
                                    CONFLICT-RESOLUTION
    0.200
                                    Stopped because time limit reached
             _ _ _ _ _ _
0.1
2
NIL
15> (buffer-chunk goal)
GOAL: A-0
A-0
  SIZE 11
  NEW-SLOT NEW-CHUNK
  NEW-NEW-SLOT T
(A-0)
E> (mod-buffer-chunk 'not-a-buffer nil)
#|Warning: mod-buffer-chunk called with an invalid buffer name NOT-A-BUFFER |#
NIL
E> (mod-buffer-chunk 'goal '(color blue color red))
#|Warning: mod-buffer-chunk called with an invalid modification (COLOR BLUE COLOR RED) |#
E> (schedule-mod-buffer-chunk 'goal '(color blue) nil)
#|Warning: schedule-mod-buffer-chunk called with non-number time-delta: NIL |#
E> (mod-buffer-chunk 'goal nil)
#|Warning: mod-buffer-chunk called with no current model. |#
```

set-buffer-failure

Syntax:

set-buffer-failure buffer {:requested requested} {:ignore-if-full if-full} -> [t | nil]

Arguments and Values:

```
buffer ::= a symbol which should name a buffer
requested ::= a generalized boolean
if-full ::= a generalized boolean
```

Description:

The set-buffer-failure command is used to set the failure flag in a buffer. A buffer's failure flag will remain set until the buffer is cleared. If the flag is successfully set then the function returns **t**.

If buffer does not name a buffer in the current model, or there is no current model then a warning is printed and **nil** is returned.

The requested keyword parameter specifies whether the buffer will indicate that the failure was requested or not. If requested is specified as **t** (which is the default) or any other true value, then the setting of the failure flag is to be interpreted as being the result of a request to a module having failed and the query of that buffer for "buffer requested" will be true. If the requested keyword parameter is specified as **nil**, then the "buffer requested" query for the buffer will be **nil** and the "buffer unrequested" query will be true.

The failure flag cannot be set when there is currently a chunk in the specified buffer. The ignore-if-full parameter specifies what to do if there is a chunk in the buffer when set-buffer-failure is called. If the parameter is specified as **nil** (the default value) then it will print a warning and return **nil** if there is a chunk in the buffer. If the parameter is true then no warning will be displayed and **nil** will be returned.

```
1> (buffer-status goal)
GOAL:
  buffer empty
                        : T
  buffer full
                        : NIL
  buffer failure
                        : NIL
  buffer requested
                        : NIL
  buffer unrequested
                        : NIL
  state free
                        : T
  state busy
                        : NIL
  state error
                        : NIL
(GOAL)
2> (set-buffer-failure 'goal)
3> (buffer-status goal)
GOAL:
  buffer empty
                        : NIL
  buffer full
                        : NIL
  buffer failure
                        : T
  buffer requested
                        : T
  buffer unrequested
                        : NIL
  state free
                        : T
  state busy
                        : NIL
  state error
                        : NIL
(GOAL)
4> (clear-buffer 'goal)
NIL
5> (buffer-status goal)
GOAL:
  buffer empty
                        : T
```

```
buffer full : NIL
buffer failure : NIL
buffer requested : NIL
buffer unrequested : NIL
state free : T
state busy : NIL
state error : NIL
(GOAL)
6> (set-buffer-failure 'goal :requested nil)
7> (buffer-status goal)
GOAL:
  buffer empty
                                 : NIL
 buffer full : NIL
buffer failure : T
buffer requested : NIL
buffer unrequested : T
state free : T
state busy : NIL
state error : NIL
(GOAL)
8> (set-buffer-chunk 'goal 'red)
RED-0
9> (buffer-status goal)
GOAL:
  burier empty : NIL
buffer full : T
buffer failure : NIL
buffer requested : T
buffer upgested
  buffer requested : T
buffer unrequested : NIL
state free : T
state busy : NIL
                                  : NIL
  state error
(GOAL)
10E> (set-buffer-failure 'goal)
#|Warning: cannot set the failure flag when there is a chunk in the GOAL buffer |#
11> (set-buffer-failure 'goal :ignore-if-full t)
12> (buffer-status goal)
GOAL:
  buffer empty
                                   : NIL
  buffer full : T
buffer failure : NIL
buffer requested : T
buffer unrequested : NIL
state free : T
  state busy
                                  : NIL
  state error
                                  : NIL
(GOAL)
E> (set-buffer-failure 'not-a-buffer)
#|Warning: set-buffer-failure called with an invalid buffer name NOT-A-BUFFER |#
E> (set-buffer-failure 'goal)
#|Warning: set-buffer-failure called with no current model. |#
```

module-request

Syntax:

```
module-request buffer chunk-spec-> [t | nil ]
schedule-module-request buffer chunk-spec time-delta {:module module} {:priority priority}
{:output output} {:details details} {:time-in-ms time-units}
-> [event-id | nil ]
```

Remote command name:

```
module-request schedule-module-request buffer chunk-spec time-delta { < module module, priority priority, output output, details details, time-in-ms time-units > }
```

Arguments and Values:

```
buffer ::= the name of a buffer
chunk-spec ::= an ACT-R chunk-spec or chunk-spec-id
time-delta ::= a number indicating when to schedule the event
module ::= a name which will be used as the module of the event and in the trace
priority ::= [ :max | :min | priority-val]
priority-val ::= a number indicating the priority to use for the event
output ::= [t | high | medium | low | nil]
details ::= a string to display in the trace when the request occurs
time-units ::= a generalized boolean indicating whether time-delta is in seconds or milliseconds
event-id ::= an integer which can be used to reference the event created
```

Description:

The module-request commands are used to send a request to a module through its buffer. This is the only recommended way to interact with a module to make requests.

If the buffer name is valid and a valid chunk-spec is provided, then that chunk-spec will be sent to the buffer's module as a request. Note that the command does not implicitly clear the buffer as occurs for requests from the productions of a model. If the buffer should be cleared that must be done explicitly in conjunction with the request.

For module-request, if the buffer name and chunk-spec are valid and the named buffer's module accepts requests then a value of **t** is returned. If the buffer name is invalid, an invalid chunk-spec is provided, the buffer's module does not accept requests, or there is no current model then a warning is displayed and **nil** is returned.

The only test performed upon the chunk-spec to determine if it is valid (assuming that it is a chunk-spec) is to verify that any request parameters provided are valid for the buffer to which it is being sent. Any other processing of the request for validity is up to the module which receives the request.

When using module-request, even though the request itself is not scheduled the actions performed by the module in response to that request should be (at least if the module is written according to the recommended guidelines). Thus, it is likely that no changes will occur until the model is run.

It is recommended that all requests be scheduled using schedule-module-request.

Schedule-module-request is used to schedule the sending of the request to the buffer's module such that it occurs during the running of the model. It schedules an event to occur as if the following was executed:

The default values for the parameters are **:none** for module, 0 for priority, **medium** for output, and **nil** for details. It returns the event that is scheduled. If any of the parameters are not valid or there is no current model then a warning is printed, **nil** is returned and nothing is scheduled. Note that for schedule-module-request the test whether the module accepts requests is not performed until the event occurs. Thus any warning about that will not occur until the model is run.

Examples:

These examples assume that there is a module called dummy with a buffer called dummy which does not accept requests.

```
1> (buffer-chunk goal)
GOAL: NIL
(NIL)

2> (module-request 'goal (define-chunk-spec value free))
T

3> (buffer-chunk goal)
GOAL: NIL
(NIL)

4> (mp-show-queue)
Events in the queue:
```

```
0.000
             NONE
                                     CHECK-FOR-ESC-NIL
     0.000
             GOAL
                                     CREATE-NEW-BUFFER-CHUNK GOAL
     0.000
             PROCEDURAL
                                     CONFLICT-RESOLUTION
3
5> (run .001)
     0.000
             GOAL
                                     SET-BUFFER-CHUNK GOAL CHUNKO
     0.000
             PROCEDURAL
                                     CONFLICT-RESOLUTION
     0.000
                                     Stopped because no events left to process
             -----
0.0
5
NIL
6> (buffer-chunk goal)
GOAL: CHUNKO-0
CHUNK0-0
   VALUE FREE
(CHUNKO-0)
7> (schedule-module-request 'goal (define-chunk-spec value busy) .1)
8> (buffer-chunk goal)
GOAL: CHUNKO-0
CHUNKO-0
   VALUE FREE
(CHUNKO-0)
9> (mp-show-queue)
Events in the queue:
     0.100
             NONE
                                     MODULE-REQUEST GOAL
     0.100
             PROCEDURAL PROCEDURAL
                                     CONFLICT-RESOLUTION
2
10> (run .1)
     0.100
             NONE
                                     MODULE-REQUEST GOAL
                                     SET-BUFFER-CHUNK GOAL CHUNK1
     0.100
             GOAL
     0.100
             PROCEDURAL
                                     CONFLICT-RESOLUTION
                                     Stopped because time limit reached
     0.100
             _ _ _ _ _
0.1
NIL
11> (buffer-chunk goal)
GOAL: CHUNK1-0
CHUNK1-0
   VALUE BUSY
(CHUNK1-0)
E> (module-request 'dummy (define-chunk-spec))
#|Warning: Module DUMMY does not handle requests. |#
NİL
1> (schedule-module-request 'dummy (define-chunk-spec) 0)
12
2E> (run .1)
                                     MODULE-REQUEST DUMMY
     0.100
             NONE
#|Warning: Module DUMMY does not handle requests. |#
                                     CONFLICT-RESOLUTION
     0.100
            PR0CEDURAL
     0.100
                                     Stopped because no events left to process
0.0
NIL
```

```
E> (module-request 'not-a-buffer (define-chunk-spec))
#|Warning: module-request called with an invalid buffer name NOT-A-BUFFER |#
NIL

E> (module-request 'goal 'not-a-chunk-spec)
#|Warning: module-request called with an invalid chunk-spec NOT-A-CHUNK-SPEC |#
NIL

E> (schedule-module-request 'goal (define-chunk-spec) nil)
#|Warning: schedule-module-request called with a non-number time-delta: NIL |#
NIL

E> (module-request 'goal *spec*)
#|Warning: module-request called with no current model. |#
NIL
```

module-mod-request

Syntax:

```
module-mod-request buffer modifications -> [t | nil ]
schedule-module-mod-request buffer modifications time-delta {:module module} {:priority priority}
{:output output} {:time-in-ms time-units}
-> [event-id | nil ]
```

Arguments and Values:

```
buffer ::= the name of a buffer
modifications ::= [ mod-list | mod-spec ]
mod-list ::= ({slot-name slot-value }*)
mod-spec ::= a chunk-spec which contains valid modification information
slot-name ::= the name of a slot of the chunk in the named buffer
slot-value ::= a value to set for the corresponding slot-name of the chunk in the named buffer
time-delta ::= a number indicating when to schedule the event
module ::= a name which will be used to as the module of the event and in the trace
priority ::= [ :max | :min | priority-val]
priority-val ::= a number indicating the priority to use for the event
output ::= [t | high | medium | low | nil]
time-units ::= a generalized boolean indicating whether time-delta is in seconds or milliseconds
event-id ::= an integer which can be used to reference the event created
```

Description:

The module-mod-request commands are used to send a modification request to a module through its buffer. This is the only recommended way to interact with a module to make modification requests. A modification request requires that there be a chunk in the specified buffer at the time these commands are issued.

For module-mod-request, if the buffer name is valid, the modifications are valid, there is a chunk in the specified buffer, and the named buffer's module accepts modification requests then a value of **t** is returned. If the buffer name is invalid, an invalid modification is provided, the buffer is empty, the buffer's module does not accept modification requests, or there is no current model then a warning is displayed and **nil** is returned.

The modifications may be specified as a list of slot-value pairs or a <u>chunk-spec</u> with slot-specs that indicate the modifications to make (such a chunk-spec must only use the modifier = in the slot-specs and may contain request parameters valid for the specified buffer). If a slot specified in a modification list is not currently a possible slot it will be added to the possible slots using the <u>extend-possible-slots command</u> at the time the module-mod-request function is called. There is no test performed by module-request to determine if the modification list provided is acceptable to the module prior to sending it other than the test for valid request parameters. All processing of that nature is done by the module once it has received the modification request.

When using module-mod-request, even though the request itself is not scheduled the actions performed by the module in response to the request should be (at least if the module is written according to the recommended guidelines). Thus, it is likely that no changes will occur until the model is run.

It is recommended that all modification requests be scheduled using schedule-module-mod-request.

Schedule-module-mod-request is used to schedule the sending of the modification request to the buffer's module such that it occurs during the running of the model. It schedules an event to occur as if the following was executed:

The default values for the parameters are **:none** for module, 0 for priority, and **low** for output if not provided. It returns the event that is scheduled. If any of the parameters are not valid or there is no current model then a warning is printed, **nil** is returned and nothing is scheduled. Note that for schedule-module-mod-request the test whether the module accepts modification requests is not performed until the event occurs. Thus the warning will not occur until the model is run.

Examples:

These examples assume that there is a module called dummy with a buffer called dummy which does not accept modification requests.

```
1> (set-buffer-chunk 'goal 'free)
2> (module-mod-request 'goal '(value t))
3> (buffer-chunk goal)
GOAL: FREE-0 [FREE]
FREE-0
  NAME FREE
(FREE-0)
4> (mp-show-queue)
Events in the queue:
    0.000
             NONE
                                    CHECK-FOR-ESC-NIL #S(CENTRAL-PARAMETERS ...)
    0.000
             GOAL
                                    MOD-BUFFER-CHUNK GOAL
    0.000
             PROCEDURAL
                                    CONFLICT-RESOLUTION
3
5> (run .01)
             GOAL
    0.000
                                    MOD-BUFFER-CHUNK GOAL
    0.000
             PROCEDURAL
                                    CONFLICT-RESOLUTION
    0.000
                                    Stopped because no events left to process
0.0
NIL
6> (buffer-chunk goal)
GOAL: FREE-0
FREE-0
  NAME FREE
  VALUE T
(FREE-0)
7> (schedule-module-mod-request 'goal (define-chunk-spec name busy) 0)
8> (mp-show-queue)
Events in the queue:
                                    MODULE-MOD-REQUEST GOAL
    0.000
             NONE
    0.000
             PROCEDURAL
                                    CONFLICT-RESOLUTION
2
9> (buffer-chunk goal)
GOAL: FREE-0
FREE-0
  NAME FREE
  VALUE T
(FREE-0)
10> (run .1)
    0.000
             NONE
                                    MODULE-MOD-REQUEST GOAL
    0.000
             GOAL
                                    MOD-BUFFER-CHUNK GOAL
    0.000
             PROCEDURAL
                                    CONFLICT-RESOLUTION
    0.000
                                    Stopped because no events left to process
             -----
0.0
```

```
3
NIL
11> (buffer-chunk goal)
GOAL: FREE-0
FREE-0
  NAME BUSY
  VALUE T
(FREE-0)
1E> (module-mod-request 'dummy nil)
#|Warning: module-mod-request called with no chunk in buffer DUMMY |#
2> (set-buffer-chunk 'dummy 'busy)
BUSY-1
3E> (module-mod-request 'dummy nil)
#|Warning: Module DUMMY does not support buffer modification requests. |#
NIL
E> (module-mod-request 'not-a-buffer nil)
#|Warning: module-mod-request called with an invalid buffer name NOT-A-BUFFER |#
NIL
E> (module-mod-request 'goal 'bad-modification)
#|Warning: module-mod-request called with an invalid modification BAD-MODIFICATION |#
NIL
E> (module-mod-request 'goal '(new-slot t))
#|Warning: Chunks extended with slot NEW-SLOT during a chunk-spec definition. |#
E> (schedule-module-mod-request 'goal nil nil)
#|Warning: schedule-module-mod-request called with a non-number time-delta: NIL |#
NIL
E> (module-mod-request 'goal nil)
#|Warning: module-mod-request called with no current model. |#
NIL
```

buffer-spread

Syntax:

buffer-spread buffer -> [spread-value | nil]

Remote command name:

buffer-spread

Arguments and Values:

buffer ::= the name of a buffer spread-value ::= a number indicating the buffer spreading parameter value for the buffer

Description:

For the <u>spreading activation calculation</u> in declarative memory each buffer has associated with it a value for the amount of activation it can spread. Each module may specify a particular name for that parameter for each buffer which it owns. This command allows one to get the value of that parameter for any buffer without knowing the specific name of the parameter which the module assigned for it.

If the buffer name given is the name of a buffer in the current model, then the value of that buffer's activation spread parameter will be returned. If the buffer name is invalid or there is no current model then a warning will be printed and **nil** will be returned.

This command is not likely to be used by the typical modeler or module developer, but it may be useful when investigating alternative equations for implementing the spreading activation and is used internally by the declarative module.

Examples:

```
1> (sgp :ga 1.5 :imaginal-activation 2.0)
(1.5 2.0)

2> (buffer-spread 'goal)
1.5

3> (buffer-spread 'imaginal)
2.0

4> (buffer-spread 'retrieval)
0

E> (buffer-spread 'bad)
#|Warning: buffer-spread called with an invalid buffer name bad |# nil

E> (buffer-spread 'goal)
#|Warning: buffer-spread called with no current model. |# nil
```

buffers-module-name

Syntax:

buffers-module-name buffer -> [name | nil]

Remote command name:

buffers-module-name

Arguments and Values:

```
buffer ::= the name of a buffer name ::= the name of the module that owns the buffer specified
```

Description:

The buffers-module-name command can be used to find the name of a module when you know the name of a buffer. If the buffer name given names a valid buffer in the current model then the name of the module which owns that buffer is returned. If the buffer name is not valid or there is no current model then **nil** is returned.

This command will typically be used if one is building general tools for tracing events or otherwise producing code which will be monitoring the model's event stream and need to determine module names from buffer actions.

```
> (buffers-module-name 'goal)
goal
> (buffers-module-name 'visual-location)
:vision
E> (buffers-module-name 'bad)
#|Warning: invalid buffer name bad |#
NIL
E> (buffers-module-name 'goal)
#|Warning: buffers-module-name called with no current model. |#
NIL
```

Extending Chunks

Sometimes it may be convenient to associate supporting information with chunks i.e. information which is not appropriate to encode within the chunk using the slots. This is often useful when creating a new module. As noted in the general description of chunks, each chunk has associated with it a set of parameters which can be used to hold such information. This section will describe how to add and use new chunk parameters.

The command to add a new parameter to chunks is called <u>extend-chunks</u> and will be described in detail below. Here the general concepts and support for chunk parameters will be described.

The first thing to note is that extending chunks is a system wide operation. Once the parameter is added all chunks in all models will have such a parameter available. Thus, extending chunks is a one-time operation. It is recommended that chunk parameters be added when there are no models defined and thus no preexisting chunks. If there are chunks defined when a new parameter is added, then an attempt to access that new parameter value in one of those existing chunks will have unpredictable consequences and could result in errors. The recommended way to add a new parameter is to place the extend-chunks call at the top-level in a file that is loaded automatically by ACT-R at initial load time. That will ensure that the functions for setting and accessing the parameter value are compiled with the rest of the code and that there will be no problems or warnings with attempts to redefine that parameter. There is no mechanism provided for removing a chunk parameter once it has been added and redefinition of an existing chunk parameter is not allowed.

Adding a new chunk parameter causes two internal user functions to be created and two remote commands. One of each is the accessor for the parameter, internally a setf function is created for the accessor, and remotely a command to set the value is created. The accessor function and remote command will both have the name **chunk**-*param* where param is the name of the parameter which was added. Thus, if you were to add a parameter named foo to chunks the accessor for that parameter would be **chunk**-**foo** and the remote command would be "**chunk**-**foo**". The accessor takes one parameter which should be the name of a chunk in the current model and it will return the current value of that parameter for that chunk. To change the parameter internally you can use setf in conjunction with the accessor. Thus, assuming one has added a parameter called foo this shows how one could get and set the value of that parameter for a chunk named free:

```
1> (chunk-foo 'free)
```

```
2> (setf (chunk-foo 'free) 10)
10
3> (chunk-foo 'free)
10
```

The remote function for setting the value will be called "**set-chunk-***param*" and it takes two parameters. The first of which is the name of a chunk and the second of which is the new value for that parameter of the chunk.

The accessor function will test that there is a current model and that the chunk name is valid and it will print warnings and return **nil** if there is a problem:

```
E> (chunk-foo 'bad-name)
#|Warning: Chunk BAD-NAME does not exist in attempt to access CHUNK-F00. |#
NIL

E> (chunk-foo 'free)
#|Warning: get-chunk called with no current model. |#
#|Warning: Chunk FREE does not exist in attempt to access CHUNK-F00. |#
NII
```

After adding a parameter, it will be shown when the <u>pprint-chunks-plus</u> command is called and will display the current value just like all of the other chunk parameters which are currently defined:

```
> (pprint-chunks-plus free)
FREE
   ISA CHUNK
--chunk parameters--
   F00   10
   FAN-LIST (FREE)
   ACTIVATION  0
```

When creating a parameter for the chunks it is also possible to control how that parameter is treated under the following conditions:

- How it is initially set when a chunk is created
- How it is set in the copy when a chunk is copied
- How it is set when two chunks are merged

The details of how to specify those controls when creating a chunk parameter and examples of their use are provided with the details of the extend-chunks command. How they apply to the operation of the system will be described here.

There are two possible ways one can specify the initial value for the parameter. If neither is used, then the initial value for the parameter when a chunk is created will be **nil**. The first option is to specify a default value. The parameter will be set to that value for each new chunk created. The other method for setting the initial value is to provide a function or remote command to set the value. If a default value function or command is provided, then that will be called to get the initial value for the parameter. It will be called with one parameter, which will be the name of the chunk in which the default value is being set. The return value will be the initial setting of that chunk parameter. The parameters for a chunk will be initialized in no particular order, and thus the initialization function should not rely on any other parameters of the chunk having been set. Also, the initialization will not happen until the first time that the chunk's parameter value is requested. Thus, it may not be called for every chunk and may not be called until well after the initial creation time of the chunk.

When a chunk is copied using the copy-chunks command the settings of the parameters for the new copy are determined as follows. By default, the parameter will be set in the same manner as the initial value for a newly created chunk i.e. either **nil**, the specified default value, or the result of calling the default value function or command. However, it is possible to instead specify a function or remote command to use to set the value for the copy which is different from the function or command used to set the initial value. The copy function or command will be passed one parameter and its return value will be the setting for the parameter in the copied chunk. There are two options available for specifying a function to set a parameter value in a copied chunk and the difference between them is what value is passed to the function or command. One option is to set the "copy" function which will be passed the current value of the parameter from the chunk which is being copied. The other option is to set the "copy from chunk" function which will be passed the name of the chunk which is being copied. Only one of the copying mechanisms can be used, and if both are specified then the "copy" function will be the one that gets used. If one wants to have the copied chunk's parameter set the same as the original chunk's parameter specifying the copy function as the Lisp function identity is recommended.

When two chunks are merged using the <u>merge-chunks command</u> (which will happen automatically when the declarative module collects chunks cleared from the buffers) the values of the parameters for the merged chunk after the merging are set by default to the values that existed for the primary chunk (the first one in the call to merge-chunks) prior to the merge. That can be overridden by providing a merge function or remote command for the parameter. If a merge function or command is provided then when two chunks are merged it will be called with the names of the chunks being merged as its only two parameters. They will be passed to the parameter's merge function or

command in the same order as they were given to merge-chunks, and the return value of that call will be the setting of that parameter in the merged chunk.

Commands

extend-chunks

Syntax:

```
extend-chunks parameter-name {:default-value value} {:default-function def-fn} {:copy-function copy-fn} {:copy-from-chunk-function copy-from-fn} {:merge-function merge} -> [accessor | :duplicate-parameter | nil]
```

Remote command name:

```
extend-chunks parameter-name { < default-value 'value', default-function 'def-fn', copy-function 'copy-fn', copy-from-chunk-function 'copy-from-fn', merge-function 'merge' >}
```

Arguments and Values:

Description:

The extend-chunks command is used to add a new parameter to chunks. If chunks do not already have a parameter by that name, then an accessor called chunk-parameter-name (where parameter-name is the parameter-name symbol provided) will be created which takes one parameter which should always be a chunk name. That accessor can be used to get the corresponding parameter of a chunk or used with setf or a remote setting command to change the value of that parameter for the chunk. The Lisp command is a macro which does not evaluate its parameters and there is not a corresponding Lisp function.

The initial value for the new parameter when a chunk is created will be **nil** unless either the default-value or default-function keyword parameter is provided. If a default-value is specified then that will

be set as the value of the parameter for a newly created chunk. If a default-function is specified, then that will be called with the name of the chunk as its only parameter and the return value of that call will be used as the initial value. If both a default-value and default-function are given, then the default-function will be used.

When a copy of a chunk is being made the parameter value for the new copy of the chunk will be set to the default value as determined above unless either a copy-function or a copy-from-chunk-function is provided. If one of those is provided, then the new chunk will have its value set to the value returned from calling that item. The difference between the copying mechanisms is that the copy-function is called with the current parameter value of the chunk which is being copied and the copy-from-chunk-function gets called with the name of the chunk which is being copied. If both are specified then the copy-from-chunk-function will be used.

If a merge-function is provided as a non-keyword value, then when two chunks are being merged that function or remote command will be called with the names of those chunks in the order which they were merged and the value it returns will be the setting for the parameter in the merged chunk. If no merge-function is given, then the merged chunk will take the value of the parameter from the first of the two chunk names specified in the merging. If the merge-function is specified with the keyword :second, then the value of the parameter in the merged chunk will be the value from the second of the chunks being merged, and if it is the keyword :second-if then it will be the value of the second chunk only if that value is non-nil otherwise it will be the value from the first chunk.

If a new parameter is created, then the name of that accessor is returned.

If a parameter by that name already exists, then a warning will be printed and the keyword :duplicate-parameter will be returned.

If parameter-name is not valid a warning is printed and **nil** is returned.

If there is already a function with the same name as the accessor or the update function created then a warning will be printed to indicate that and those functions will be redefined for the chunk parameter. In some cases, that warning may appear if a file containing an extend-chunks call is compiled and then loaded. In those circumstances the warning can typically be safely ignored, and if one wants to eliminate the warning then the extend-chunks command can be called between calls to the functions suppress-extension-warnings and unsuppress-extension-warnings to prevent the output of the warnings:

```
(suppress-extension-warnings)
(extend-chunks ...)
(unsuppress-extension-warnings)
```

The use of the warning suppression function is only recommended for use when an extend-chunks call occurs at the top level of a file and one is certain the parameter name's redefinition of the function(s) is not a problem.

```
1> (defun count-copies (n) (1+ n))
COUNT-COPIES
2> (defun merge-use-second (a b) b)
MERGE-USE-SECOND
3> (defun start-with-name (x) (string x))
START-WITH-NAME
4> (extend-chunks simple)
CHUNK-SIMPLE
5> (extend-chunks counter :default-value 0 :copy-function count-copies)
CHUNK-COUNTER
6> (extend-chunks merge-demo :default-function start-with-name
                             :merge-function merge-use-second)
CHUNK-MERGE-DEMO
7> (define-chunks (a))
(A)
8> (pprint-chunks-plus a)
  --chunk parameters--
  MERGE-DEMO
  COUNTER 0
  SIMPLE NIL
   . . .
(A)
9> (copy-chunk a)
10> (pprint-chunks-plus a-0)
A-0
  --chunk parameters--
  MERGE-DEMO "A-0"
  COUNTER 1
  SIMPLE NIL
(A-0)
11> (merge-chunks a a-0)
12> (pprint-chunks-plus a)
```

```
--chunk parameters--
   MERGE-DEMO A-0
   COUNTER 0
   SIMPLE NIL
   . . .
(A)
13E> (extend-chunks simple)
#|Warning: Parameter SIMPLE already defined for chunks. |#
:DUPLICATE-PARAMETER
1> (defun chunk-dummy ())
CHUNK-DUMMY
2E> (extend-chunks dummy)
#|Warning: Function CHUNK-DUMMY already exists and is being redefined. |#
CHUNK-DUMMY
E> (extend-chunks "not a symbol")
#|Warning: "not a symbol" is not a valid symbol for specifying a chunk parameter. |#
NIL
```

Defining New Modules

The primary means of extending the system, both in terms of extending the cognitive capabilities of models and extending the software system itself, is through adding new modules. This section will describe the mechanism for defining a new module and detail how it interacts with the system.

To create a new module one uses the <u>define-module command</u>. A module can only be defined when there are currently no models in the system. The typical way to do that for a Lisp based module is to place the file with the module definition into one of the directories from which all of the .lisp files are loaded automatically at startup. That way the new module will be compiled and loaded with the rest of the ACT-R files. However it is not necessary to do it that way, and one can define modules using the define-module command at any time when there are no models defined.

When a module is defined it must be given a name. That name must be unique among the currently defined modules i.e. only one module with a given name may exist in the system. Once a module is defined it cannot be overwritten with a new definition for a module with the same name. However, one can use the <u>undefine-module command</u> to explicitly remove a module from the system if it is necessary to replace it. Undefining a module can also only happen when there are no models defined.

Once a module is defined every model which gets defined will have its own instance of that module. What constitutes an "instance" is determined by the module's creation function (described in detail below). The recommendation is that a new instance should be created for each model and that there should be no sharing of state between modules in separate models, particularly for the cognitive modules. However, there is nothing which prevents such operation and in some circumstances that may be useful, for example, a module might make one connection to an external simulation and then allow all the models to access that same connection through their own instances of the module.

There are several items which may be specified when defining a module. It is not necessary for a module to specify all of them, and other than a name no others are required. All of these items will be described in the following sections.

Documentation

When the module is defined one should provide a string for the version number of the module and a string containing the description of the module. These strings are displayed when the system is initially loaded and when the <u>mp-print-versions command</u> is called. There are no requirements on

what the string must contain, but the recommendation is to provide some sort of number for the version string and a one sentence description of the module for the documentation. If documentation strings are not provided then a warning will be displayed indicating that they should be, but that will not prevent the module from being created.

Buffers

When the model is defined it may have any number of buffers associated with it. This is the only way to add new buffers to the system – they do not exist independently of a module. The buffers for a module will provide the interface for other modules to interact with the new module. The buffers provide the means of making requests and queries to the module, and it may respond to requests or other actions by placing chunks into its buffers. Note that every module has access to all of the buffers of the system and can place chunks into any of them, but the recommendation is that a module should only manipulate its own buffers. Of the default modules, the only one which does not follow that recommendation is the procedural module where the productions are allowed to manipulate, clear, or place chunks in any buffer.

There are several options which can be given when creating a new buffer. The only required component is a name. Each buffer must be given a name and that name must be unique in the system – there is can only be one buffer with any given name. The other options are described in the following sections.

spreading activation weight

The name of the parameter used to set that buffer's weight for the spreading activation calculation and the default value for that parameter may be specified. If they are not specified then the parameter will be named *buffer*-activation where *buffer* is the name of the buffer and the default value for the parameter will be 0.

request parameters

Any request parameters which are to be used with the buffer must be specified when the module is defined. Only those request parameters which are specified when the module is created will be considered valid when making a request to that buffer through the provided module request functions. However, there is no constraint placed on the generation of a chunk-spec since it does not make reference to any buffer at its creation time. Therefore, it is possible for code which doesn't use normal request mechanisms to pass a chunk-spec with invalid request parameters to the handler

functions of a module. It is not recommended that one use the request handler functions of a module directly in that fashion, but if those functions are to be used that way they should perform additional tests in verifying the validity of any request parameters in the chunk-spec provided.

queries

Any queries which the module will accept through the buffer, other than the default query of state which all modules must accept, need to be specified when the module is defined. Only those queries which are specified at definition time will be accepted as valid when using the <u>query-buffer command</u>. However, as described with the specification of a buffer's request parameters, if one calls the module's query function directly there is no pre-testing of the values and it should not assume that all queries are valid.

query printing

By default, buffer-status will print out the results of querying the buffer's buffer and state queries (those to which every buffer must respond). If the module has other queries that one would like to show when <u>buffer-status</u> is called that can be done by providing a query printing command to do so. That function should use the <u>command-output command</u> to print any additional status information desired for the buffer, and that output will be displayed after the normal output by buffer-status.

multi-buffer

A buffer may indicate whether or not it is to be treated as a "multi-buffer". A multi-buffer is a construct which allows one to specify a set of chunks which can be used with the buffer that will not be copied when placed into the buffer – they will be placed directly into the buffer. Details on <u>multi-buffers</u> are described in their own section and will not be covered further here.

Parameters

Each module may specify a set of parameters which it will use. Those parameters can be either new parameters which the module will "own" and make available to the system, or existing parameters owned by other modules which it would like to be informed about when they change. Whenever a parameter is changed through the use of the sgp command the module which owns that parameter is given the new value specified in the sgp call. The module is responsible for recording that new value, or whatever value it wants to use based on that value, and then return the current value for the

parameter. If any other modules are watching that parameter as non-owners, then they are notified of the new value which the owning module has reported.

In Lisp the parameters are specified using the <u>define-parameter command</u>, and remotely one provides a list of values which appear similar to the define-parameter syntax. These are the items that can be provided for a parameter in the module.

name

Each parameter must specify the name of the parameter. The name must be a Lisp keyword. If it is the name of a parameter that has already been defined by another module then it is only valid if this definition explicitly claims that it is not the "owner" of that parameter. If it specifies that it is the owner of the parameter, then that name must not already be taken by a parameter of another module.

owner

When defining the parameter it must be specified whether it should be created as a new parameter or one which is to be watched and assumed to already exist. If it is being specified as a new parameter, that is, the specification claims that it is being defined by its owner, then the remaining properties may also be specified for the parameter. If the specification claims to not be the owner of the parameter then only the name of the parameter is relevant.

documentation

A string describing the parameter can be specified. That string will be printed by the sgp command when displaying the details of the parameter.

default-value

The value the parameter will have by default. If no default value is given then the default value will be **nil**.

valid-test

A function or remote command may be given to use when testing the parameter values set by the sgp command. If a valid-test is specified, then that will be passed one value, which is the requested setting from an sgp call. If the test returns a non-**nil** value then the setting is passed on to the module

to handle. If the test returns **nil** then a warning is displayed and that parameter setting is not passed to the module.

warning

If a parameter value fails the valid-test the warning which is printed is constructed based on the warning string provided when the parameter is defined. The warning will always be of this form:

```
#|Warning: Parameter param cannot take value val because it must be warn. |#
```

where *param* is the name of the parameter, *val* is the invalid value given and *warn* is the warning string specified when defining the parameter.

Interaction commands

A module interacts with the rest of the system by providing functions or commands to be called at the appropriate times. None of these items are required unless the module also provides one or more buffers or one or more parameters for the system. If the module has a buffer then it must provide handle queries of the buffer, and if it has any parameters then it must handle the setting and getting of the parameter values.

Here are the possible situations for which a module may provide command and the parameters which it will be passed and how the return value is used.

creation

Whenever a new model is defined it will create an instance of each module in the system. To create that instance each module's creation command is called. That command will be passed one parameter which will be the name of the model being defined. The value returned will be saved as the instance of that module in that model. The module's instance should be a data structure capable of holding any parameter values and state information necessary for the module to operate or a unique indicator which the module code will use to locate that model specific information (because the remote calling mechanisms do not provide shared access to items a unique identifier should always be used for a module not defined in Lisp since it would not be possible to mainpulate the actual instance held by ACT-R remotely). That instance will be passed to all of the other interface commands which the module provides. If a module does not provide a creation command then its instance will be the value **nil** for the purpose of calling any of its other interface commands.

reset

The module may specify one, two or three commands to call when a model is reset. Those commands will be called with the instance of the module as their only parameter. The three reset commands are called at different times during the resetting of a model and a module may use any or all of them if needed. The primary reset is called before any parameters get reset to their default values. The secondary reset gets called after the default parameters have been set and before any user code is evaluated. The tertiary reset gets called after the user code of the model definition has been evaled. Most modules are likely only going to need one of the reset commands, and typically only the primary reset is necessary. However, if a module needs to modify the value of another module's parameter at reset time it will have to do so in a secondary or tertiary reset, otherwise any change will be overwritten. Although using the secondary or tertiary reset is necessary to adjust another module's parameter from the default value, it may not be sufficient because other modules may also have secondary or tertiary reset actions which will also adjust or restore that value. In such cases, watching the parameter, by adding it to the module as a parameter which it does not own, will allow for more control and monitoring of the changes. The return value of a module's reset command is not used.

delete

The module may specify a command to be called when the model in which it has been created is deleted. The delete function will be passed the instance of the module in the model being deleted as its only parameter. The instance of the module will not be referenced by the given system code after it has been deleted and thus may be destructively modified, deallocated, or any other explicit cleanup as needed may be performed upon it. To ensure that deleted module instances are not referenced, one should not access any parameters using sgp in a module's delete action. The return value of the module's delete command is not used.

parameters

If the module makes parameters available to the system or is monitoring the parameters of other modules then it must provide a command for setting and getting those parameter values. The module's parameter command will be called with two parameters. The first will be the instance of the module in the current model. The second depends upon whether the module was defined from within the Lisp running ACT-R or externally. If it was defined in Lisp then it will be either the name of a parameter, in which case this is a request for the current value of the parameter which the

command should return, or it will be a cons of a parameter name and a new value for that parameter which the module should set. If the module was defined externally then the second parameter will always be a list. If it is a request for the current value that list will contain one item which is the name of the parameter, and if it is a request to set a new value for the parameter the list will have two items which will be the name of the parameter and the new value for it respectively. When a new value is indicated for a parameter, the module should set the parameter as needed based on that value and then return the current value of the parameter (which may or may not be the same as the value which was provided). A module's parameter function will only be called with parameters which the module has specified when it was defined. For those which it owns it will get both calls for the current value and calls to change the value. If a module does not own the parameter it will only be sent notifications of changes to the parameter and the return value from the function in those cases is ignored.

queries

If the module has one or more buffers, then it must provide a command to handle queries of those buffers. The module's query command will be called whenever the query-buffer command is used. It will be called with four parameters. The first will be the instance of the module in the current model. The second will be the name of the buffer being queried. The third will be one of the valid queries for the module – either state, which all modules must accept, or one of the ones given when the buffer was specified. The fourth parameter will be the value of the query to test. There are no constraints on the values which may be used. Thus, a module should be able to handle any value which is provided, but it does not have to consider them all valid and may display warnings when invalid values are given. Every module with a buffer is expected to respond to queries of state with values of free, busy, or error, but other than those there are no prespecified queries to which a module must respond. The return value of the query function is considered as a generalized boolean. If the query of the given value is true then the module should return a true value and if the query of the given value is not true the function should return nil.

requests

If the module has one or more buffers then it may provide a command to handle requests to those buffers, but it is not required that a module with buffers accept requests. If a request command is specified for the module then it will be called whenever the <u>module-request command</u> is called for one of the module's buffers. It will be called with three parameters. The first will be the instance of the module in the current model. The second will be the name of the buffer to which the request was

made, and the third will be a chunk-spec (or chunk-spec-id) which represents the request being made. The chunk-spec provided may include any number of slot tests and request parameters, but only those request parameters which are specified with the buffer's definition will be included. Other than that there are no tests performed on the chunk-spec before it is passed to the module. Therefore the module's request command is responsible for testing and verification of whether the request being made is something which the module is able to handle and should signal warnings to indicate invalid or malformed requests. The return value of the request command is ignored.

What a module does in response to a request is entirely up to the module writer — there are no mandatory actions which must occur. It is recommended however that the module should schedule events to handle all of the actions which it performs in response to the request. By doing so, the trace will show those actions, other modules will be able to detect that they have occurred (for instance the procedural module may schedule another conflict-resolution event if there is not one pending), the model debugging tools will allow one to see that the events have been scheduled, and the stepping tools can be used for testing and debugging of the module's actions.

buffer modification requests

If the module has one or more buffers then it may provide a command to handle buffer modification requests, but a module is not required to handle such requests. If a command for buffer modification requests is provided for the module then it will be called whenever the <u>module-mod-request command</u> is called for one of the module's buffers. The module's buffer modification request command will be called with three parameters. The first will be the instance of the module in the current model. The second will be the name of a buffer to which the request was made, and the third will be a chunk-spec (or chunk-spec-id) of modification information (a chunk-spec that only uses the modifier = in the slot-specs, specifies each slot only once, and may contain request parameters valid for the specified buffer). A buffer modification request will only occur when there is a chunk in the buffer, but the slots specified may or may not exist in that chunk. The return value of the modification request command is ignored.

What a module does in response to a buffer modification request is entirely up to the module writer – there are no mandatory actions which must occur. It is recommended however that the module should schedule events to handle all of the actions which it performs in response to the request. The general purpose of the modification request is to allow the module to perform an action like modchunk which has a time cost during which time the module will be busy and unable to handle other

requests. However, it does not have to be used that way and may be used to perform other module actions.

notify upon clearing

A module may specify a command to be called when any buffer is cleared. If a module provides a command to be notified when buffers clear it will be called with three parameters after every buffer clearing occurs. The first parameter will be the instance of the module in the current model. The second parameter will be the name of a buffer, and the third parameter will be the name of the chunk which was cleared from the buffer. The module may use that information however it wants, but the one thing that it should not do is modify the chunk which was cleared from the buffer because other modules may also need the information which is in that chunk. The return value of the notify upon clearing command will be ignored.

notify at the start of a new call to run the system

A module may specify a command to be called whenever one of the <u>system running commands</u> is called. If a module provides a command to be notified when a run starts then that command will be called with one parameter before the first event of the run is executed. That parameter will be the instance of the module in the current model. This notification function is not recommended for the normal operations of a module because it should not depend on how or when the system is run. The intended use of this notification is to allow a module an opportunity to perform some safety or verification tests before the system runs. The return value of this command is ignored.

Some examples of its current use are the procedural module and the module which handles the ACT-R environment connections. The procedural module uses it to make sure that there is always a conflict-resolution or other appropriate procedural event scheduled or waiting. This avoids a problem that could occur because of an unusual run termination (a Lisp break in the middle of a conflict-resolution action for example) which would leave the procedural module without any events on the queue and thus unable to fire any more productions until it is reset. The environment connection uses it to initialize the stepper tool if it is open when the model starts running.

An important note is that this command will be called regardless of how the running command was called. Some of the running commands may actually result in multiple start/stop pairs because they can involve multiple calls to running commands internally. Thus, start/stop pairs may not map 1:1 with user calls to run the system.

notify upon a completion of a call to run the system

A module may also specify a command to be called whenever one of the system running commands is finished running the system. If a module provides a command to be notified when a run ends then it will be called with one parameter after the last event of the run is executed. That parameter will be the instance of the module in the current model. Like the run start notification, this is not recommended for the normal operations of a module because it should not depend on how or when the system is run. The intended use of this notification is to allow a module an opportunity to perform some safety or verification tests after the system runs.

One example of this being used is the module which handles the ACT-R Environment connection. It uses this to disable the stepper controls when there is no longer a model running.

As noted with the run start description, this command will be called regardless of how the running command was called. Some of the running commands may actually result in multiple start/stop pairs because they can involve multiple calls to running commands internally. Thus, start/stop pairs may not map 1:1 with user calls to run the system.

warning of an upcoming request

A module may specify a command which will be called to provide the module with a warning of an upcoming request. If a warning command is provided it will be called with three parameters. The first parameter will be the instance of the module. The second will be the name of one of the module's buffers and the third will be the chunk-spec (or chunk-spec-id) of the request. The procedural module will call a module's warning command, if it has one, at production selection time to warn about any requests which will be made when the selected production fires. This is the only time that the warning command will be called — requests from other modules or from explicit requests made by other code will not be preceded by warnings. Having a warning command allows a module to know that a production will be making a request which may be dependent on information which was true at the time the production was selected. The module gets called with the warning at the selection time and thus may suspend pending actions or note the relevant information necessary at that time to use when handling the request. The return value of this command is ignored.

The only module which currently uses a warning command is the vision module. It allows the vision module to suspend the processing of a screen update during a production which will be making a move-attention request so that the visual-location chunk which is used in the production does not get invalidated by a change in the display before the request is handled.

search and offset

Two additional commands can be specified when the module has one or more searchable buffers. How those functions are used is described in the <u>searchable buffers</u> section.

Common Class of Modules - Goal Style

There is a particular type of module which modelers often find useful to create for various situations. That type of module is one which works like the <u>goal</u> and <u>imaginal</u> modules where a request is a direct specification of a chunk to create and be placed into the buffer. Those are referred to as "goal style" modules. There are three Lisp functions which exist to make creating such modules easy (those functions are not currently available remotely). Those functions can be used as the query, request, and modification request functions for creating such a module, and they are the functions goal-style-query, goal-style-request, and goal-style-mod-request respectively.

Using those functions, one can create a new module which acts just like the default goal module and buffer using something like this:

Where *name* is the name you want to give to the module and buffer, which must be the same for the assumptions in the goal-style-* functions.

Those commands do not have to only be used in that manner, and it is possible to call them from other functions. For example, one could specify a different request function when creating the module which performs some error checking or possible restrictions on the requests which can be made to the module before then calling goal-style-request to do the rest of the work.

The file which defines the goal-style components is included in the support directory of the distribution. Therefore it is not loaded automatically when the system loads. So, any file which uses those commands should include this line near the top of the file:

```
(require-compiled "GOAL-STYLE-MODULE" "ACT-R-support:goal-style-module")
```

That will ensure that the goal style support code is loaded appropriately. Typically, the main goal module will already have loaded that support, but it is safest to be certain that it has been loaded, especially when creating modules or other code which may be shared with others who may have made other changes to the modules or default system.

Writing Module Code

When writing code to handle the module's operations there are some assumptions which can be made and practices which should be followed. This section will cover those assumptions and recommended practices.

Because the module commands which one provides will always be passed the current model's instance of the module one can assume that there is a current model in handling those calls. However, if one has additional functions which go along with the module that may be called at other times, or without requiring an instance of the module as a parameter, then the use of the get-module command is recommended to get the current model's instance of the module to work with. The get-module command takes one parameter which should be the name of a module and it returns the instance of that module in the current model. If there is no current model then get-module will print a warning and return nil.

When a module performs actions in a running model, particularly actions relating to the buffers, it should always schedule those as events instead of directly calling commands which make those changes. When scheduling such events, it should always indicate the module's name when the event is generated. Doing those things makes it much easier to debug a model which uses the module and also makes it easier to integrate new modules from different sources because any unexpected interactions should then be detectable in the model's trace.

If a module needs to reference the values of parameters of other modules then it is recommended that they be specified as non-owned parameters for the module. Those parameters' values should then be recorded in some way in the instance of the module with the module's parameter function even if the module has no parameters of its own. That is recommended for performance reasons because using sgp to get parameter values is a relatively slow process and often also requires suppressing the output which also may have a significant cost to performance relative to the work done by the module.

Any chunk-types and chunks which a module is going to define should be defined in the module's primary reset function if possible. If the module depends on the chunks or chunk-types of other

modules it should not reference those items during the primary reset function because there is no guarantee that the other module's primary reset function will be called prior to the current module's.

If the module will be <u>extending chunks</u> or productions with new parameters for its use that should be done at the top level in the module's definition file because extending those items should only occur once. Such calls do not belong in either the creation or reset function for the module.

Module examples

The examples provided below will generally only show the basic syntax of the commands, and will not have "working" module definitions as examples because the necessary support code is outside of the scope of the examples for the reference manual. Also, one often needs a model which uses the module to really have an example that shows the components in operation. In the examples directory of the source code distribution one can find a directory called creating-modules. In that directory are new module definition files which implement demonstration modules along with corresponding models which use the features provided by those modules. The documentation for the modules and how to run the associated models are included in the comments of those files.

Commands

get-module

Syntax:

```
get-module name -> [instance | nil] [t | nil]
get-module-fct name -> [instance | nil] [t | nil]
```

Remote command name:

get-module

Arguments and Values:

```
name ::= the name of a module instance ::= the named module's instance in the current model
```

Description:

The get-module command is used to get the instance of a module in the current model. It returns two values. If there is a module with that name in the system then the first return value is the instance of that module and the second return value will be **t**. If that name does not name a module in the current model or there is no current model then a warning will be printed and both return values will be **nil**.

The purpose of the second return value to indicate that the module instance exists is because a module may use **nil** as its instance.

Examples:

```
> (get-module goal)
#S(GOAL-MODULE ...)
T
> (get-module-fct 'imaginal)
#S(IMAGINAL-MODULE ...)
T

E> (get-module foo)
#|Warning: FOO is not the name of a module in the current model. |#
NIL
NIL

E> (get-module-fct 'goal)
#|Warning: get-module called with no current model. |#
NIL
NIL
```

define-buffer

Syntax:

Arguments and Values:

```
name ::= a symbol which is the name of the buffer
param ::= a keyword that names the source activation parameter for the buffer
default ::= the default value for the source activation of this buffer
request-params ::= (request-param*)
request-param ::= a keyword indicating a valid request parameter for this buffer
queries ::= (query*)
query ::= a symbol indicating a valid query for this buffer
status ::= a function or name of a function to be called when buffer-status reports on this buffer
multi ::= a generalized boolean indicating whether this is a regular multi-buffer
search ::= a generalized boolean indicating whether this is a searchable multi-buffer
copy ::= a generalized boolean indicating whether this is a multi-buffer which should copy chunks
buffer-lst ::= (name (p-name p-default) request-params gueries status multi-type)
p-name ::= param if it is provided, otherwise the keyword :name-activation
p-default ::= default if it is provided, otherwise nil
multi-buffer ::= [ :multi | :search | :multi-copy | :search-copy | nil ] depending on the values of multi
              search and copy
```

Description:

The define-buffer command can be used to create a buffer definition list for use in a module definition. The value returned from this function has no real use in the system other than as a member of the list of buffers when defining a module. It is recommended that define-buffer be used to create a buffer definition list whenever the buffer uses any of the needed components to make the definition more understandable. If a value is not provided for one of the keyword parameters then a **nil** value will be placed into the definition list for that component, with two exceptions: if the paramname is not provided but a param-default is then the standard default activation name will be used, and both the search and multi values must be **nil** (or not provided) for the multi-buffer specifier to be **nil**.

Define-buffer does not test any of the values for validity and just creates an appropriately formatted list for use in a module definition.

Examples:

define-parameter

Syntax:

Arguments and Values:

```
param-name ::= a keyword for the name of the parameter being defined owner ::= a generalized boolean indicating whether this definition is specifying the parameter's owner default ::= a value which will be the default value for the parameter docs ::= a string describing the parameter test ::= a function, function name or nil used to test value for this parameter through sgp warn ::= a string to print when an invalid parameter value is detected parameter ::= an instance of an ACT-R internal parameter item
```

Description:

The define-parameter command is used to create a parameter for a module. The value returned from this function has no use in the system other than as a member of the list of parameters when defining a module. A parameter defined through this command will not be available to the system until it is part of a module which owns it.

The only parameter required when calling define-parameter is the name of the parameter which must be a Lisp keyword.

The owner parameter specifies whether the module which uses this parameter definition is to be considered the owner of that parameter. If not provided the default value is \mathbf{t} .

The default parameter specifies the value the parameter should have as its default when the system is reset. If not provided, then the default value for the parameter will be **nil**. The only restriction on the default value is that it cannot be a Lisp keyword because it is not possible to use sgp to set a single parameter to a keyword value.

The docs parameter should be a string which describes the parameter. That string is printed by sgp when the parameter value is displayed.

The valid test may be specified as a function or the name of a function. That function is called whenever this parameter's value is changed using the sgp command. The test function will be passed the new value specified in the sgp call. If the test function returns a true value then the new value is considered valid and it is passed on to the owning module's parameter function to set. If the test function returns **nil** then a warning is printed and the parameter value is left unchanged. If no test is specified in the definition for the parameter then no testing is performed on the values for.

If a test function is provided, then when it reports an invalid value the warning which gets printed will look like this:

#|Warning: Parameter param-name cannot take value val because it must be warn. |#

where *param-name* is the name of the parameter, *val* is the invalid value given and *warn* is the warn string specified when defining the parameter. If no warn string is provided, then it defaults to an empty string.

If any of the parameters passed to define-parameter are invalid then a warning will be displayed and **nil** will be returned.

Examples:

```
> (define-parameter :new :documentation "A new parameter")
#S(ACT-R-PARAMETER ...)
> (define-parameter :count :valid-test 'fixnump :warning "a fixnum")
#S(ACT-R-PARAMETER ...)
> (define-parameter :bll :owner nil)
#S(ACT-R-PARAMETER ...)
E> (define-parameter 'not-a-keyword)
#|Warning: Parameter name must be a keyword. |#
NIL
E> (define-parameter :new :documentation 'not-a-string)
#|Warning: documentation must be a string. |#
NIL
E> (define-parameter :new :valid-test 'not-a-function)
#|Warning: valid-test must be a function, the name of a function, or nil. |#
NIL
E> (define-parameter :new :default-value :keywords-not-allowed)
#|Warning: default-value cannot be a keyword. |#
NIL
E> (define-parameter :new :warning 'not-a-string)
#|Warning: warning must be a string. |#
```

define-module

Syntax:

Remote command name:

```
define-module module-name (buffer-def*) (remote-param*)
{ < version version, documentation doc-string, creation create, reset reset, request request,

query query, buffer-mod mod, params params, delete delete, notify-on-clear clear,
warning warn, run-start run-start, run-end run-end, search search, offset offset >}
```

Arguments and Values:

module-name ::= the name for the module being defined

```
buffer-def ::= [buffer-name
             (buffer-name {buff-params { (req-param*) { (query-names*) { [print-status | nil ]
                           {multi-buffer}}}}) ]
buffer-name ::= a name of the buffer being defined
buff-params ::= [pname | (pname pdefault) | (nil pdefault) | (pname nil) | nil]
pname ::= a name for the parameter to create for the buffer's spreading activation value
pdefault ::= a number which will be the default for the buffer's spreading activation value parameter
reg-param ::= a name for a request parameter this buffer will accept
guery-names ::= a name of a new guery which is valid for this buffer
print-status ::= a valid local or remote command to be called when buffer-status reports on this buffer
multi-buffer ::= [ :multi | :search | :multi-copy | :search-copy | nil ]
param ::= a parameter item as returned by the define-parameter command
doc-string ::= a string to provide a brief description of the module
create ::= a valid local or remote command to handle the module creation
reset ::= [primary-reset | ([primary-reset | nil] { [secondary-reset | nil] { [tertiary-reset | nil] }} ) ]
primary-reset ::= a valid local or remote command to handle the module's primary reset
secondary-reset ::= a valid local or remote command to handle the module's secondary reset
tertiary-reset ::= a valid local or remote command to handle the module's tertiary reset
request a valid local or remote command to handle module requests
query ::= a valid local or remote command to handle module queries
mod ::= a valid local or remote command to handle module modification requests
params ::= a valid local or remote command to handle the module's parameter
delete ::= a valid local or remote command to handle the deletion of the module
clear ::= a valid local or remote command to call whenever a buffer is cleared
warn ::= a valid local or remote command to be called to warn of a future request to the module
run-start ::= a valid local or remote command to be called each time a running command is called
run-end ::= a valid local or remote command to be called each time a running command finishes
search ::= a valid local or remote command to be called when searching a multi-buffer
offset ::= a valid local or remote command to be called after a multi-buffer search for preferences
remote-param ::= (param-name {< owner owner, valid-test 'test', default-value 'default', warning warn,
                                 documentation docs > } )
param-name ::= the name of the parameter being defined
owner ::= a generalized boolean indicating whether this definition is specifying the parameter's owner
test ::= a command name or nil used to test the value for this parameter through sgp
default ::= a value which will be the default value for the parameter
warn ::= a string to print when an invalid parameter value is detected
docs ::= a string describing the parameter
version ::= a string providing version information for the module
```

Description:

The define-module command is used to add a new module to the system. A new module may only be added if there are currently no models defined. The first parameter to define-module must be a name for the new module being defined. If there is not already a module defined with that name and all of the remaining parameters provided to describe the module are valid (as described below) then a new module is added to the system and the name of the module is returned. Otherwise, a warning is printed and **nil** is returned.

The second parameter must be a list of the buffer descriptions for the buffers of the module. It may be an empty list, in which case the module has no buffers. If it is not an empty list, then the elements of that list must be either names or lists.

If an element of the buffer definition list is a name, then the module will have a buffer with that name which will be given the default values for its components. If a list is provided then one can specify the other components of the buffer as well. The <u>define-buffer command</u> is recommended for creating a buffer definition list, but is not required. The list may be up to six elements long and the components of the list are as follows:

- The first element must be the name of the buffer.
- The second element specifies the name of the spreading activation parameter to add to the system for this buffer and/or the default value for the buffer's spreading activation parameter.
 - O If it is a keyword which is not already the name of a parameter in the system then that name will be used for the parameter and it will have a default value of 0.
 - o If it is a list, then the first element of the list is the name of the parameter and the second element is the default value, which should be a number. If the name is specified as **nil** then the default name for the parameter is used.
- The third element is the list of request parameters which the buffer will accept. It must be a list of keywords or **nil**. Only those items specified in this list will be considered as valid request parameters by the <u>module-request command</u>.
- The fourth element is the list of queries which may be made to the module in addition to the standard query for state. It must be a list of names or **nil**. Only those items specified in this list will be considered as valid queries by the <u>query buffer command</u>.
- The fifth element should be a valid command. This command will be called after the <u>buffer-status command</u> has printed the default query information for the buffer. This is typically added when one provides additional queries so that their status may be displayed for the user along with the normal queries using buffer-status.
- The sixth element, if provided, indicates that this should be considered as a <u>multi-buffer</u> and specifies which multi-buffer mechanism to use.

If a module has one or more buffers then it must provide a query command. It is not required to provide a request or modification request command.

The third parameter to define-module must be a list of parameter specifications returned by the define-parameter command in Lisp or a list which is formated as shown above for a remote-param. If

the list of parameters is non-empty then each parameter must have an appropriate ownership. If a parameter in the list is specified as being owned by the module then it must not be owned by any other module, and if a parameter in the list is indicated as not being owned then that parameter must be owned by some other module. A module which specifies parameters must also provide a params command to support them.

The version and documentation parameters should be strings and are used to display information about the module when the <u>mp-print-versions command</u> is called. They are not required, but if either is not provided a warning will be displayed before defining the module.

The rest of the keyword parameters are used to specify the commands to call for interfacing the module to the rest of the system. How they interface to the system is described in the <u>interaction</u> <u>commands section</u>. Here the details of the parameters they will be passed and expected return values will be described.

The create command will be passed one parameter. That will be the symbol naming the model in which a new instance of the module is being created. The return value of the module's create function will be the instance used for calling all of the module's other commands from that model.

The module's reset command (or commands) are called with one parameter. That parameter will be the instance of the module in the current model. The return values of the reset commands are ignored by the system.

The request command will be passed three parameters. The first will be the instance of the module in the current model. The second will be a symbol naming one of the module's buffers indicating to which buffer the request was made. The third parameter will be the chunk-spec or chunk-spec-id which describes the request. The return value of the request command is ignored by the system.

The query command will be passed four parameters. The first will be the instance of the module in the current model. The second will be the name of one of the module's buffers indicating which buffer is being queried. The third will be the name of a query being made, and the fourth will be the value being queried. The return value of the query command will be considered as a generalized boolean and should indicate whether the value specified for the query was true or false.

The mod command will be passed three parameters. The first will be the instance of the module in the current model. The second will be the name of one of the module's buffers indicating to which buffer the modification request was made. The third will be a chunk-spec or chunk-spec-id of modification information (a chunk-spec that only uses the modifier = in the slot-specs, specifies each slot only once, and may contain request parameters valid for the specified buffer). The return value of the mod command is ignored by the system.

The params command will be passed two parameters. The first will be the instance of the module in the current model. The second will be either the name of one of the module's owned parameters or an indication of a new value for a parameter. If the second parameter is a name then that indicates that the current value for that parameter is being asked for and the return value of the command should be that parameter's current value in the current model. The specification for a new parameter value in Lisp will be a cons of a parameter name specified for the module and a new value for that parameter, but for a remote command it will be a two element list of those items. If this module owns the parameter being changed then the return value of the params command will be considered the current value of that parameter. If the module does not own the parameter being changed then the return value of the params command is ignored.

The delete command will be passed one parameter. That parameter will be the instance of the module in the model being deleted. The return value of the delete command is ignored by the system.

The clear command will be passed three parameters. The first will be the instance of the module in the current model. The second will be the name of a buffer which is being cleared. The third will be a the name of a chunk which is being cleared from that buffer. The return value of the clear command is ignored by the system.

The warn function will be passed three parameters. The first will be the instance of the module in the current model. The second will be a the name of one of the module's buffers indicating to which buffer the request will be made. The third will be a chunk-spec or chunk-spec-id indicating a request that will be made. The return value of the warn function is ignored by the system.

The run-start function will be passed one parameter. That parameter will be the instance of the module in the current model. The return value of the run-start function is ignored by the system.

The run-end function will be passed one parameter. That parameter will be the instance of the module in the current model. The return value of the run-end function is ignored by the system.

The search function will be passed two parameters. The first will be the instance of the module in the current model. The second will be the name of a multi-buffer of the module. The return value of the

search function should be a list of chunks in that buffer's buffer set, in the order they are to be searched or **nil** indicating no order preference.

The offset function will be passed three parameters. The first will be the instance of the module in the current model. The second will be the name of a multi-buffer of the module. The third will be a list of chunk names from the buffer set of that multi-buffer. The return value of the offset function should be a list of numbers representing the offset value for the matching of the chunks in the list provided or **nil** if no offsets are to be used.

Examples:

Examples of modules along with demo models which use them can be found in the examples/creating-modules directory of the distribution. The examples here are only to show the syntax of the command and some of the warnings and errors which may occur.

```
> (define-module foo nil nil)
#|Warning: Modules should always provide a version and documentation string. |#
1> (define-module bar nil nil :version "" :documentation "")
2E> (define-module bar nil nil :version "" :documentation "")
#|Warning: Module BAR already exists and cannot be redefined. Delete it with undefine-
module first if you want to redefine it. |#
> (define-module-fct 'foo '(foo-1 (foo-2 (:foo-spread 1.5)))
               (list (define-parameter :foo-value))
               iversion "0.3"
               :documentation "example"
               :params 'foo-param-function
               :query 'foo-query-function)
F00
E> (define-module-fct nil nil nil)
#|Warning: Modules should always provide a version and documentation string. |#
#|Warning: Nil is not a valid module-name. No module defined. |#
E> (define-module-fct 'bad '(buffer-1) nil)
#|Warning: Modules should always provide a version and documentation string. |#
#|Warning: A module with a buffer must support queries.
Module BAD not defined. |#
E> (define-module-fct 'bad nil (list 'bad-parameter))
#|Warning: Modules should always provide a version and documentation string. |#
#|Warning: Invalid params-list (BAD-PARAMETER).
Module BAD not defined. |#
E> (define-module-fct 'bad '(buffer-1 (buffer-2 bad-param-name)) nil :query 'query-fn)
```

```
#|Warning: Modules should always provide a version and documentation string. |#
#|Warning: Invalid buffer specification: (BUFFER-2 BAD-PARAM-NAME) |#
#|Warning: Error in module buffer definitions.
Module BAD not defined. |#
NIL

E> (define-module 'bad nil nil)
#|Warning: Modules should always provide a version and documentation string. |#
#|Warning: Cannot create a new module when there are models defined. |#
NIL
```

undefine-module

Syntax:

```
undefine-module module-name -> [t | nil] undefine-module-fct module-name -> [t | nil]
```

Remote command name:

undefine-module

Arguments and Values:

module-name ::= the name of a module

Description:

The undefine-module command is used to remove a module from the system. It takes one required parameter which is the name of the module to remove. If that names a module in the system and there are no models defined then that module, all of its buffers, and all of its parameters are removed from the system and the value **t** will be returned.

If the name does not name a module in the system or there is a model defined then a warning is printed and a value of **nil** is returned.

There are typically two reasons for using this command. The first is when first writing and debugging a module. Often one finds that they need to change something with it and this command is the only way to remove a broken or incomplete module without quitting the system and reloading everything. The other is when one has built a module which is a replacement for an existing module. In that case, the file with a new version of the module undefines the original version of the module before defining the replacement.

```
1> (define-module bar nil nil :version "" :documentation "")
BAR
```

```
2> (define-module foo nil nil :version "" :documentation "")
F00

3> (undefine-module bar)
T

4> (undefine-module-fct 'foo)
T

5E> (undefine-module-fct 'foo)
#|Warning: F00 is not the name of a currently defined module. |#
NIL

E> (undefine-module goal)
#|Warning: Cannot delete a module when there are models defined. |#
NIL
```

goal-style-query

Syntax:

goal-style-query instance buffer slot value -> [t | nil]

Arguments and Values:

```
instance ::= this parameter is ignored
buffer ::= the name of the buffer being queried
slot ::= this parameter is ignored
value ::= the value of the query
```

Description:

The goal-style-query command is designed to be used as the query function for a module's definition. It assumes that only the default queries for state will be made. It responds to those queries as follows: a state busy query will always return **nil**, a state free query will always return **t**, and a state error query will always return **nil**. For any other values it will print a warning indicating that the query was invalid and return **nil**.

```
> (goal-style-query nil 'goal 'state 'free)
T
> (goal-style-query nil 'goal 'state 'busy)
NIL
> (goal-style-query nil 'goal 'state 'error)
NIL
E> (goal-style-query nil 'goal 'state 'bad)
#|Warning: Unknown state query BAD to GOAL buffer |#
NIL
E> (goal-style-query nil 'goal 'bad-query t)
#|Warning: Unknown query BAD-QUERY T to the GOAL buffer |#
```

goal-style-request

Syntax:

goal-style-request instance buffer chunk-spec {delay {priority}} -> [event-id | nil]

Arguments and Values:

```
instance ::= this parameter is ignored
buffer ::= the name of the buffer to which the request was made
chunk-spec ::= a chunk-spec or chunk-spec-id of the request
delay ::= a number indicating how many seconds to wait before creating the chunk
priority ::= [ :max | :min | priority-val]
priority-val ::= a number indicating the priority to use for the event
event-id ::= an integer id for the event which will create the new chunk in the buffer
```

Description:

The goal-style-request command is designed to be used as the request function for a module's definition, but it may also be called by a other functions to handle the creation of a chunk in the buffer and provides optional delay and priority parameters for such use. If the chunk-spec provided is valid for the <u>chunk-spec-to-chunk-def command</u>, then this command schedules an event to create a chunk using that chunk definition and place that chunk into the specified buffer after the provided delay time has passed with the indicated priority. If no delay time is provided, then it default to 0 seconds. If the priority is not specified then it defaults to -100. The id of the event scheduled is returned. If the chunk-spec is invalid then a warning is printed and **nil** is returned.

The scheduled event will result in multiple other events being generated. The first event will have an action of <u>create-new-buffer-chunk</u>. That event's action will create a chunk using the result of the chunk-spec-to-chunk-def call. It will also schedule a set-buffer-chunk event using the <u>schedule-set-buffer-chunk command</u> with that chunk, a delay of 0, and a priority of -1000 and schedule an event with an action named clean-up-goal-chunk with a delay of 0 and a priority of -1001 which will not be shown in the trace. The clean-up-goal-chunk action will <u>delete</u> the chunk that was generated by the create-new-buffer-chunk command and <u>release its name</u> since that chunk is no longer needed because its copy is now in the buffer.

```
1> (goal-style-request nil 'goal (define-chunk-spec isa chunk))
3
2> (goal-style-request nil 'goal (define-chunk-spec isa chunk) .2)
```

```
4
```

```
3> (with-parameters (:trace-detail high)
     (run .25))
     0.000
             GOAL
                                    CREATE-NEW-BUFFER-CHUNK GOAL
     0.000
             GOAL
                                    SET-BUFFER-CHUNK GOAL CHUNKO
     0.000
             PROCEDURAL
                                    CONFLICT-RESOLUTION
     0.200
             GOAL
                                    CREATE-NEW-BUFFER-CHUNK GOAL
                                    SET-BUFFER-CHUNK GOAL CHUNK1
    0.200
             GOAL
                                    CONFLICT-RESOLUTION
    0.200
             PROCEDURAL
    0.200
                                    Stopped because no events left to process
0.2
9
NIL
E> (goal-style-request nil 'goal 'bad-spec)
#|Warning: chunk-spec-to-chunk-def called with something other than a chunk-spec. |#
#|Warning: Invalid request made of the GOAL buffer. |#
NIL
```

create-new-buffer-chunk

Syntax:

create-new-buffer-chunk buffer chunk-description {:priority priority} -> nil

Arguments and Values:

```
buffer ::= the name of a buffer
chunk-description ::= a valid chunk definition
priority ::= [ :max | :min | priority-val]
priority-val ::= a number indicating the priority to use for setting the chunk in the buffer
```

Description:

This command defines a new chunk using the chunk-description provided (which should be a list that is valid for the chunk list of <u>define-chunks-fct</u>), schedules an event to copy that chunk into the buffer specified at the current time with the priority provided (or -1000 if not provided), and schedules an event to <u>delete</u> the chunk that was generated and <u>release its name</u> since that chunk is no longer needed because its copy is now in the buffer. The event which places the chunk into the buffer is a normal event, and the event which deletes the chunk is a maintenance event. This is the function which does the work for a <u>goal-style-request</u>, but it may be useful in other situations as well. It does not do any validity testing on the parameters provided thus care should be taken when using it to avoid errors.

```
1> (buffer-read 'goal)
NIL
2> (create-new-buffer-chunk 'goal '(color blue state free))
```

```
NIL
```

```
3> (mp-show-queue)
Events in the queue:
                                     SET-BUFFER-CHUNK GOAL CHUNKO
     0.000
             GOAL
     0.000
             NONE
                                     Clean-up unneeded chunk
     0.000
             PROCEDURAL
                                     CONFLICT-RESOLUTION
3
4> (run 1)
     0.000
             GOAL
                                     SET-BUFFER-CHUNK GOAL CHUNKO
     0.000
             PROCEDURAL
                                     CONFLICT-RESOLUTION
                                     Stopped because no events left to process
     0.000
0.0
3
NIL
5> (buffer-chunk goal)
GOAL: CHUNKO-0
CHUNKO-0
   STATE FREE
   COLOR BLUE
(CHUNKO-0)
```

goal-style-mod-request

Syntax:

goal-style-mod-request instance buffer mods {delay {priority}} -> [event-id | nil]

Arguments and Values:

```
instance ::= this parameter is ignored
buffer ::= the name of the buffer to which the request was made
mods ::= a modification chunk-spec or chunk-spec-id
delay ::= a number indicating how many seconds to wait before modifying the chunk
priority ::= [ :max | :min | priority-val]
priority-val ::= a number indicating the priority to use for the event
event-id ::= the integer id of the scheduled event which will modify the chunk in the buffer
```

Description:

The goal-style-mod-request command is designed to be used as the buffer modification request function for a module's definition, but it may also be called by other functions to handle the modification of a chunk in the buffer and provides optional delay and priority parameters for such use. This command just calls <u>schedule-mod-buffer-chunk</u> with the buffer, chunk-spec, delay, and priority provided. If no delay time is provided, then it default to 0 seconds. If no priority is provided then the default value is 20. The value returned from that call to schedule-mod-buffer-chunk is returned.

```
1> (set-buffer-chunk 'goal (car (define-chunks (value t))))
CHUNK0-0
2> (goal-style-mod-request nil 'goal (define-chunk-spec value nil))
3> (goal-style-mod-request nil 'goal (define-chunk-spec value 5) .5)
4> (run .5)
     0.000
            GOAL
                                    MOD-BUFFER-CHUNK GOAL
     0.000
            PROCEDURAL
                                    CONFLICT-RESOLUTION
     0.500
             GOAL
                                    MOD-BUFFER-CHUNK GOAL
     0.500
            PROCEDURAL
                                    CONFLICT-RESOLUTION
     0.500
                                    Stopped because time limit reached
            ----
0.5
5
NIL
```

Multi-buffers

A multi-buffer provides some new possibilities for how a module can use its buffer as well as possibly changing how the <u>procedural module</u> will interact with that buffer. These capabilities are still considered an experimental modification to the system and thus the reason for covering them in a separate section instead of in the other sections. If you use multi-buffers in your own modules please let me know of any problems you encounter or suggestions for improvements which you have.

Multi-buffers were introduced as a general mechanism to allow for the implementation of modules which do things which were not easy to do with the system previously. One such module was the threaded cognition module by Salvucci and Taatgen. Prior to the introduction of the multi-buffers, the implementation of the threaded cognition module required making changes to many internal functions of the system. That made that module difficult to maintain since it had to be updated often to stay in line with updates and changes to the main system. Those changes also had the potential to interfere with modules written by other people which could lead to problems integrating different new mechanisms. The current design of multi-buffers was sufficient to allow threaded cognition to be implemented as a module without needing to change any of the main system code, and the expectiation is that the multi-buffer concept may be useful in other areas as well.

The difference between a multi-buffer and a "normal" buffer is that a module with a multi-buffer may specify a set of chunks which can be placed into that buffer without being copied first. Despite the name, a multi-buffer is still restricted to only holding one chunk at any time. It is that additional set of chunks which accompany the buffer to which the multi prefix refers, but when used as a <u>searchable buffer</u> that chunk may be changed among those in the set automatically by the conflict resolution process thus being treated as if it holds any one of them for production matching purposes. When a chunk which is not in the "buffer set" of a multi-buffer is placed into the multi-buffer, it will work like a normal buffer and copy that chunk first.

Some of the buffer related commands described above work slightly differently when the buffer provided is a multi-buffer. Set-buffer-chunk and overwrite-buffer-chunk do not copy the chunk being placed into a multi-buffer if the chunk is a member of the buffer set for that buffer. When clear-buffer is passed a multi-buffer then the chunk being cleared from the buffer is also removed from the buffer set of that buffer. Finally, the buffer-chunk command will show the buffer set of a multi-buffer when that buffer's information is displayed. The buffer set will be shown in curly braces after the name of the chunk currently in the buffer if the buffer set is non-empty.

Not every chunk may be added to the buffer set of a multi-buffer. Essentially, only those chunks which are created by the module which created the multi-buffer are valid members of the multi-set. Chunks which are, or could potentially be, referenced by other modules are marked as being invalid as members of a buffer set. In particular, chunks which have been cleared from a buffer and chunks which have been explicitly added into declarative memory cannot be put into a buffer set. Additionally, one may mark a chunk as explicitly unavailable for the buffer set of any multi-buffer by setting the buffer-set-invalid parameter of the chunk to **t**:

```
(setf (chunk-buffer-set-invalid chunk) t)
```

That may be useful when creating a module which defines chunks that are made available for other uses, but which should not be directly placed into buffers. If a chunk is already in a buffer set when it is marked as invalid then it will remain in that buffer set, but will be copied into the buffer from that point forward.

When working with a multi-buffer a module should be careful to not allow chunks which it wants to remain in the buffer set to be cleared from the buffer. The module should probably use overwrite-buffer-chunk instead of set-buffer-chunk internally to avoid clearing the current chunk first. Similarly, the module may want to turn off strict-harvesting for the multi-buffer to avoid the automatic clearing that the procedural module may perform. Note however that a request to the multi-buffer from a production will still clear the buffer. Thus, care may be required in how a model's productions interact with the multi-buffer if the buffer set is to be maintained.

To create a multi-buffer the module needs to provide a sixth item in the buffer definition list for the buffer in the module definition. A value of :multi will make the buffer a multi-buffer. There are other keyword values which create a searchable buffer described in the section below. If an invalid sixth item is given then a warning will be printed and the module will not be created.

Commands

There are four additional commands that are used to work with the buffer set of a multi-buffer and one other general buffer command which is useful for multi-buffers. For all of the examples shown in the new commands this module with two multi-buffers, foo and bar, is assumed to exist:

As is this model which creates some initial chunks to use in the examples:

```
(define-model foo (sgp :v t)
```

```
(define-chunks (a) (b) (c))
(add-dm (d)))
```

store-m-buffer-chunk

Syntax:

```
store-m-buffer-chunk buffer chunk -> [ chunk | nil ]
```

Arguments and Values:

```
buffer ::= the name of a multi-buffer chunk ::= the name of a chunk to add to the buffer set of buffer
```

Description:

The store-m-buffer-chunk command is used to add a chunk to the buffer set of a multi-buffer. If the buffer name given is the name of a multi-buffer and chunk names a chunk defined in the current model which is not marked as invalid for a buffer set then that chunk will be added to the buffer set of that multi-buffer in the current model and the chunk name will be returned. If the chunk is already a member of the buffer set then no change to the buffer set is made and the chunk name is still returned.

If there is no current model, buffer does not name a multi-buffer, chunk is not a valid chunk name, or chunk names a chunk which is marked as invalid for a buffer set then there will be a warning printed and the value **nil** will be returned.

Examples:

These examples assume the module and model shown above have been defined.

```
1> (reset)
DEFAULT

2> (buffer-chunk foo bar)
F00: NIL
BAR: NIL
(NIL NIL)

3> (store-m-buffer-chunk 'foo 'a)
A

4> (store-m-buffer-chunk 'foo 'b)
B

5> (store-m-buffer-chunk 'bar 'b)
B
6> (buffer-chunk foo bar)
```

```
F00: NIL {A B}
BAR: NIL {B}
(NIL NIL)
7> (set-buffer-chunk 'foo 'a)
8> (buffer-chunk foo)
F00: A {A B}
(A)
9> (set-buffer-chunk 'foo 'b)
10> (buffer-chunk foo)
F00: B {B}
(B)
11> (setf (chunk-buffer-set-invalid 'b) t)
12> (overwrite-buffer-chunk 'foo 'b)
B-0
13> (buffer-chunk foo)
F00: B-0 [B] {B}
B-0
(B-0)
E> (store-m-buffer-chunk 'goal 'a)
#|Warning: store-m-buffer-chunk cannot store a chunk in buffer GOAL because it is not a
multi-buffer |#
NIL
E>: (store-m-buffer-chunk 'foo 'd)
#|Warning: store-m-buffer-chunk cannot store D in a buffer set because it has been marked
as invalid for a buffer set most likely because it has been previously cleared from a
buffer |#
NIL
```

get-m-buffer-chunks

Syntax:

get-m-buffer-chunks buffer -> (chunk*)

Arguments and Values:

buffer ::= the name of a multi-buffer chunk ::= the name of a chunk in the buffer set of buffer

Description:

The get-m-buffer-chunks command is used to get the buffer set of a multi-buffer. If the buffer name given is the name of a multi-buffer then a list of the chunks which are in the buffer set of that multi-buffer in the current model will be returned. There is no specification for the ordering of the chunks in the list which is returned, and one should not assume anything about the buffer set based on that ordering.

If there is no current model or buffer does not name a multi-buffer a warning is printed and **nil** will be returned.

Examples:

These examples assume the module and model shown above have been defined.

```
1> (reset)
DEFAULT

2> (store-m-buffer-chunk 'foo 'a)
A

3> (store-m-buffer-chunk 'foo 'c)
C

4> (store-m-buffer-chunk 'bar 'a)
A

5> (store-m-buffer-chunk 'bar 'b)
B

6> (get-m-buffer-chunks 'foo)
(A C)

7> (get-m-buffer-chunks 'bar)
(A B)

E> (get-m-buffer-chunks 'goal)
#|Warning: get-m-buffer-chunks cannot return a buffer set for buffer GOAL because it is not a multi-buffer |#
NIL
```

remove-m-buffer-chunk

Syntax:

remove-m-buffer-chunk buffer chunk -> [chunk | **nil**]

Arguments and Values:

```
buffer ::= the name of a multi-buffer chunk ::= the name of a chunk to remove from the buffer set of buffer
```

Description:

The remove-m-buffer-chunk command is used to remove a chunk from the buffer set of a multi-buffer. If the buffer name given is the name of a multi-buffer and the chunk names a chunk defined in the current model which is currently in the buffer set of that multi-buffer then that chunk will be removed from that buffer set and the chunk name will be returned. If the chunk is not a member of the buffer set then no change to the buffer set is made and the chunk name is still returned.

If there is no current model, buffer does not name a multi-buffer, or chunk is not a valid chunk name then there will be a warning printed and **nil** will be returned.

Examples:

These examples assume the module and model shown above have been defined.

```
1> (reset)
DEFAULT
2> (store-m-buffer-chunk 'foo 'a)
3> (store-m-buffer-chunk 'foo 'c)
4> (store-m-buffer-chunk 'bar 'a)
5> (store-m-buffer-chunk 'bar 'b)
6> (get-m-buffer-chunks 'foo)
(A C)
7> (get-m-buffer-chunks 'bar)
(A B)
8> (remove-m-buffer-chunk 'foo 'a)
9> (remove-m-buffer-chunk 'bar 'b)
10> (get-m-buffer-chunks 'foo)
11> (get-m-buffer-chunks 'bar)
(A)
12> (remove-m-buffer-chunk 'bar 'd)
13> (get-m-buffer-chunks 'bar)
(A)
E> (remove-m-buffer-chunk 'goal 'a)
#|Warning: remove-m-buffer-chunk cannot remove a chunk from buffer GOAL because it is not
a multi-buffer |#
NIL
E> (remove-m-buffer-chunk 'bar :not-a-chunk)
```

```
#|Warning: remove-m-buffer-chunk cannot remove :NOT-A-CHUNK from the buffer set because it does not name a chunk |#
NIL
```

remove-all-m-buffer-chunks

Syntax:

remove-all-m-buffer-chunks buffer -> [t | nil]

Arguments and Values:

buffer ::= the name of a multi-buffer

Description:

The remove-all-m-buffer-chunks command is used to remove all of the chunks from the buffer set of a multi-buffer. If the buffer name given is the name of a multi-buffer then the buffer set of that multi-buffer in the current model will be cleared and the value **t** will be returned.

If there is no current model or buffer does not name a multi-buffer then there will be a warning printed and the value **nil** will be returned.

Examples:

These examples assume the module and model <u>shown above</u> have been defined.

```
1> (reset)
DEFAULT

2> (store-m-buffer-chunk 'foo 'a)
A

3> (store-m-buffer-chunk 'foo 'b)
B

4> (get-m-buffer-chunks 'foo)
(A B)

5> (remove-all-m-buffer-chunks 'foo)
T

6> (get-m-buffer-chunks 'foo)
NIL

E> (remove-all-m-buffer-chunks 'goal)
#|Warning: remove-all-m-buffer-chunks cannot remove a chunk from buffer GOAL because it is not a multi-buffer |#
NIL
```

erase-buffer

Syntax:

```
erase-buffer buffer -> [ chunk | nil ]
```

Arguments and Values:

```
buffer ::= the name of a buffer chunk ::= the name of a chunk
```

Description:

The erase-buffer command is used to remove a chunk from a buffer without notifying other modules. This can be used with a normal buffer or a multi-buffer. It is similar to <u>clear-buffer</u> except that it skips the notification step. That will prevent the chunk from being collected by declarative memory and thus being marked as invalid for a buffer set. Erase-buffer is to clear-buffer as <u>overwrite-buffer-chunk</u> is to <u>set-buffer-chunk</u>. If the buffer name given is the name of a buffer and there is a chunk in that buffer that chunk will be removed from the buffer and the chunk name will be returned. If the buffer is already empty then **nil** will be returned.

If there is no current model or buffer does not name a buffer then there will be a warning printed and the value **nil** will be returned.

Examples:

These examples assume the module and model <u>shown above</u> have been defined.

```
1> (reset)
DEFAULT

2> (store-m-buffer-chunk 'foo 'a)
A

3> (store-m-buffer-chunk 'foo 'c)
C

4> (set-buffer-chunk 'foo 'a)
A

5> (set-buffer-chunk 'goal 'a)
A-0

6> (buffer-chunk foo goal)
FOO: A {A C}
A

GOAL: A-0 [A]
A-0
   ISA CHUNK

(A A-0)

7> (erase-buffer 'foo)
A
```

```
8> (buffer-chunk foo)
FOO: NIL {A C}
(NIL)

9> (erase-buffer 'goal)
A-0

10> (set-buffer-chunk 'foo 'a)
A

11> (buffer-chunk foo)
FOO: A {A C}
A

(A)

12> (clear-buffer 'foo)
A

13> (buffer-chunk foo)
FOO: NIL {C}
(NIL)

E> (erase-buffer :not-a-buffer)
#|Warning: erase-buffer called with an invalid buffer name :NOT-A-BUFFER |#
NIL
```

Searchable buffers

A searchable buffer is a multi-buffer which the procedural module will treat differently than other buffers. Except for the different treatment from the procedural module, a searchable buffer continues to operate like a <u>multi-buffer</u> as described in the previous section. When the procedural module matches a production's condition against a searchable buffer it does not restrict the matching to only the chunk which is in the buffer. Instead, it will search the buffer set of that buffer to find a chunk which matches. How that search takes place and how the module may influence the search will be detailed in this section.

An important consideration in the development of the searchable buffers was to maintain plausibility. That means avoiding the potential for multiple instantiation issues as well as not allowing the capability to solve NP-hard problems within a single production. The concept that seems to best fit with those constraints is to limit the search such that it is performed in parallel for all searchable buffers within a production and to terminate the search at the first chunk found as a match.

The testing of the conditions for a production thus follows these steps:

- Normal buffer's conditions are tested and variable bindings occur
 - o If it is a dynamic production this includes bindings from the variableized slots
- Other conditions which use only those variables (or none) are tested (!eval!, !bind!, queries)
- Each search buffer has its buffer set searched to find a chunk which matches all of the conditions that are currently defined i.e. involve constants or already bound variables
- Bind all of the variables necessary from the search buffer chunks found
- Test all remaining condition

There are a couple of additional details to add to that. One important issue is that if there is more than one search buffer tested within a production this is not guaranteed to find a set of chunks which satisfy all of the conditions in that production because tests among the search buffer chunks is performed after the search has completed – it will not go back and search again to find other chunks if those conditions fail to match.

Another thing to note relates to dynamic productions. Because the variablized slot bindings occur before the search, a variable bound in a search buffer condition cannot be used as a variablized slot. However, a search buffer could test variablized slots that were bound in the normal buffer conditions.

This is the result of generalizing the constraint of dynamic testing which only allows one level of indirection since searching a multi-buffer is effectively another level of indirection.

Once the conflict set has been determined the production with the highest utility in the set will be selected and fired. If that production involved one or more search buffers, then the chunk(s) found during the search will be placed into the appropriate buffer(s) at the time it is selected.

During the condition matching processes with a search buffer any references to the buffer name variable of the search buffer will reflect a binding to the name of a chunk in the buffer set. However, once a production is selected that variable will be bound to the actual chunk in the buffer. That only differs if it is a search-copy buffer (as described below) because a new chunk will be created as a copy for the buffer instead of placing the buffer set chunk there directly. The reason for that is because actions of the production may need to refer to the actual chunk in the buffer. That changing of the variable after the matching may seem like a problem, but it makes the copy and non-copy buffers operate the same for matching purposes if the buffer variable is used in the conditions (probably not something which would typically be done). The alternative would be to actually create a copy of each chunk in the buffer set for the matching of a search-copy buffer, but since that name would be new it wouldn't be very useful to match it in the conditions of a production.

There are two ways for the module which owns the searchable buffer to affect the search and selection process. First, the module may specify the order in which to search the buffer set and possibly exclude some members. The module does that by specifying a function with the :search keyword in the module definition. The search function will be called once during each conflict-resolution event. It will be passed the module instance and the name of a searchable buffer of the module. It should return a list of chunks from the buffer set in the order that they are to be searched. Any chunks in the list returned which are not in the buffer set will be ignored in the search. If no search function is provided for the module then the whole buffer set will be searched in an arbitrary order.

The other thing the module can do is specify a preference for each of the chunks which have matched to offset the utilities of the productions which matched them. To do that the module must specify an offset function with the :offset keyword in the module definition. The offset function will be called once for each matched searchable buffer during each conflict-resolution event in which the conflict set is non-empty. The function will be passed three parameters: the module instance, the name of a search buffer of the module, and a list of the chunks from the buffer set of that buffer which were found as matches in some production. The return value from that function should be a list of

numbers of the same length as the list of chunks it was passed where each number will be the offset for the corresponding chunk's matching in a production. Those offset values will be added to the utility of a production which matched that chunk before determining which production to fire. To recommendation for offsets is to return 0 for a preferred chunk and negative values for non-preferred chunks.

To create a searchable buffer for a module one must specify a sixth parameter in the buffer definition similar to how a multi-buffer is specified. For search buffers there are actually two options available. The first is to specify the keyword :search. That will create a multi-buffer which has the search capability described above. The other option is to specify the value :search-copy. That will create a special variation of a multi-buffer. A buffer created with :search-copy will actually have the chunks from the buffer set copied into the buffer like a normal buffer does. Otherwise, the search-copy buffer operates just like a standard searchable buffer. The advantage of using a search-copy buffer is that the chunks in the buffer set are then protected from being unintentionally cleared from the buffer (and thus being removed from the buffer set) through strict harvesting or module requests and they will not be modified since only a copy is made avaliable through the module. This "copied" multi-buffer operation is also available for a normal multi-buffer by specifying a value of :multi-copy when creating it, but such a buffer would act the same as a normal buffer and that option is not recommended.

Multiple Models

In the <u>model section</u> it indicates that it is possible to run more than one model at a time, but it does not cover the details on how to do so. This section will describe how to create and use multiple models and show the commands that are available for working with them.

The first thing to discuss is the notion of the current model. That term was introduced in the model section above and most of the commands described in this manual indicate that they only work with respect to the current model. If more than one model is defined, which one is the current one will typically need to be specified by the user. When a model is initially defined and whenever the model is reset the code provided in the model's definition will be executed with that model set as the current one by the system. When each event is executed the meta-process will set the current model to be the model which generated that event before it performs the event's action. If there is more than one model defined, then after an event's action is complete the meta-process will return to not having a current model. It is possible for the code in an event's action to indicate that a different model is current if necessary, for example to send a notice to some other model.

Because the meta-process maintains the current model automatically based on the events, user defined modules (or other code) which generate events to perform their actions should not need to have any changes made to them to be able to work with multiple models. The only thing that would be important for a module is that if it has any internal state it would need to generate a unique instance for each model when it is created. Thus, as long as the creation function for the module returns a new "instance" (structure, class, vector, key, etc.) for each model and doesn't rely on globally defined module states it should work with multiple models without any modifications. All of the standard modules provided with the system will work as described in this manual whether there is only one model defined or if there are multiple models defined.

When multiple models are defined, any command which runs the system will run all of the models together synchronously from the same event queue. In some previous versions it was possible to also have multiple meta-process which allowed for running models asynchronously, but that is not currently supported in this version. Also, although most (if not all) of the internal components of the ACT-R software are "thread safe", when a meta-process is running multiple models they are all being run from the same thread (however commands called remotely will be run in a separate thread by the dispatcher to handle the communication). There are plans to explore allowing the meta-process to use multiple threads for handling multiple simultaneous events which are marked as safe for that

purpose, but that functionality is going to require significant design and testing before becoming available.

When working with multiple models one thing to be aware of is that the system does not come with any built in ways for those models to interact. Other than sharing the event queue and clock there is no interaction among the models. Each one has its own set of modules, chunk-types, chunks, and parameters and unless there is some interaction implemented by the user the models will run the same when they are run together as each would run on its own because they are not aware of the other models' existence. In particular, they are not sensitive the other models' events in the queue. Thus, events waiting to be scheduled will not be removed from the waiting queue until an appropriate trigger from the same model occurs.

To create synchronous models all one needs to do is define them. There is no special syntax needed, and the standard <u>define-model command</u> will create each model the same as it would if that were the only model being defined. An example of defining multiple synchronous models can be found in the examples directory of the distribution in the file called "unit-1-together-1-mp.lisp". That file contains the definitions for all three of the example models from unit 1 of the tutorial (count, addition, and semantic). Each of the model definitions is just copied from the corresponding tutorial model file. The only difference between loading that file with all three defined and loading the individual model files is that the individual model files each call <u>clear-all</u> when loaded which results in removing all existing models before defining the model in the file. The combined file only calls clear-all once to remove other models and then defines each of the models one after the other. That model file will be used to create some of the examples when describing the additional commands available for working with multiple models.

After loading that file one can run it just as one would have run any of the individual models by calling the run command. Here is the beginning of the trace of a run of those models:

```
> (run 10)
     0.000
            COUNT
                      GOAL
                                           SET-BUFFER-CHUNK GOAL FIRST-GOAL REQUESTED NIL
     0.000
            SEMANTIC
                      GOAL
                                           SET-BUFFER-CHUNK GOAL G1 REQUESTED NIL
     0.000
                                           SET-BUFFER-CHUNK GOAL SECOND-GOAL REQUESTED NIL
            ADDITION
                      GOAL
     0.000
            COUNT
                      PROCEDURAL
                                           CONFLICT-RESOLUTION
     0.000
            COUNT
                      PROCEDURAL
                                           PRODUCTION-SELECTED START
                      PROCEDURAL
     0.000
            COUNT
                                           BUFFER-READ-ACTION GOAL
     0.000
            SEMANTIC
                      PROCEDURAL
                                           CONFLICT-RESOLUTION
     0.000
            ADDITION
                      PROCEDURAL
                                           CONFLICT-RESOLUTION
            COUNT
                      PROCEDURAL
                                           PRODUCTION-FIRED START
     0.050
            COUNT
                                           MOD-BUFFER-CHUNK GOAL
     0.050
                      PROCEDURAL
                                           MODULE-REQUEST RETRIEVAL
     0.050
            COUNT
                      PROCEDURAL
     0.050
            COUNT
                      PROCEDURAL
                                           CLEAR-BUFFER RETRIEVAL
                                           PRODUCTION-FIRED INITIAL-RETRIEVE
     0.050
            SEMANTIC
                      PROCEDURAL
     0.050
            SEMANTIC
                      PROCEDURAL
                                           CLEAR-BUFFER RETRIEVAL
```

PRODUCTION-FIRED INITIALIZE-ADDITION CLEAR-BUFFER RETRIEVAL

0.050 ADDITION PROCEDURAL 0.050 ADDITION PROCEDURAL

. . .

When there are multiple models running there will be an additional column shown in the trace indicating which model is performing the action. In that trace we see actions from each of the count, semantic, and addition models occurring.

One final thing to note is that for commands called through the dispatcher the current model is always provided as part of the communication when the command is sent. That information is not maintained by the dispatcher, and thus commands related to the current model do not have a version available remotely because that information is not available from the ACT-R software itself – it must be maintained by the remote system directly.

Commands

current-model

Syntax:

current-model -> [name | nil]

Arguments and Values:

name ::= the name of the current model

Description:

The current-model command can be used to get the name of the current model. If there is a current model then that model's name will be returned. If there is no current model then **nil** will be returned.

This command is likely to be used when one has code which can be called for different models and it's important to know which model is the current one.

Examples:

```
1> (clear-all)
NIL

2> (current-model)
NIL

3> (define-model m1)
M1

4> (current-model)
M1
```

```
5> (define-model m2)
M2
6> (current-model)
NIL
7> (define-model m3 (format t "Current-model is: ~S~%" (current-model)))
Current-model is: M3
M3
8> (current-model)
NIL
```

mp-models

Syntax:

mp-models -> (name*)

Remote command name:

mp-models

Arguments and Values:

name ::= the name of a currently defined model

Description:

The mp-models command can be used to get the names of all of the models currently defined. It returns a list of those names in no particular order.

Examples:

```
1> (clear-all)
NIL

2> (mp-models)
NIL

3> (define-model m1)
M1

4> (mp-models)
(M1)

5> (define-model m2)
M2

6> (mp-models)
(M2 M1)
```

delete-model

Syntax:

```
delete-model {name} -> [ t | nil ]
delete-model-fct name -> [ t | nil ]
```

Arguments and Values:

name ::= the name of a model

Description:

The delete-model command can be used to remove a currently defined model. When a name is provided and there is a model with that name that model will be completely removed from the meta-process and **t** will be returned. If name does not name a model in the meta-process then a warning will be printed and **nil** will be returned.

If no name is provided to delete-model then the current model will be removed from the metaprocess. If there is a current model then that model is removed and **t** will be returned. If no name is provided and there is no current model then a warning will be printed and **nil** will be returned.

One should be careful with using delete-model because it is possible that external commands may still be "using" a model at any point, and the consequences of deleting it out from under it could lead to errors. Currently there is no provided mechanism to determine whether there are pending calls to commands through the dispatcher which were generated for a specific model so one should be certain the state of the system is "safe" before attempting to explicitly delete a model.

Examples:

```
1> (clear-all)
NIL

2> (define-model m1)
M1

3> (delete-model m1)
T

4> (define-model m2)
M2

5> (delete-model)
T

6> (define-model m3)
M3

7> (define-model m4)
M4

8> (define-model m5)
M5
```

```
9> (delete-model-fct 'm3)
T

10> (mp-models)
(M4 M5)

11E> (delete-model)
#|Warning: No current model to delete. |#
NIL

E> (delete-model foo)
#|Warning: No model named FOO in current meta-process. |#
NIL
```

with-model

Syntax:

```
with-model name form* -> [ result | nil ] with-model-eval name form* -> [ result | nil ] with-model-fct name (form*) -> [ result | nil ]
```

Arguments and Values:

```
name ::= the name of a model
form ::= a valid Lisp expression to evaluate
result ::= the value returned from the last form evaluated
```

Description:

The with-model commands are used to set a model to be the current model and then execute some commands. If the name provided is the name of a currently defined model then that model will be set as the current model before evaluating the forms provided. After those forms have been evaluated the current model will be returned to whichever model was the current one before with-model was called. The return value from the last form evaluated will be returned by with-model. If the name provided does not name a defined model then a warning will be printed and **nil** will be returned without evaluating any of the forms.

In addition to the usual macro and functional versions of the command there is an additional macro version for with-model – with-model-eval. That command is a hybrid of the functional and macro versions and probably the one which is most likely to be used in code. The difference between with-model and with-model-eval is that with-model-eval will evaluate the expression provided for the name position to determine the name of the model to use.

Examples:

These examples assume that the "unit-1-together-1-mp.cl" example file has been loaded.

```
> (dolist (model (mp-models))
    (format t "Model: ~s~%" model)
    (with-model-eval model
      (goal-focus)))
Model: COUNT
Will be a copy of FIRST-GOAL when the model runs
FIRST-GOAL
   START 2
   END 4
Model: SEMANTIC
Will be a copy of G1 when the model runs
   OBJECT CANARY
   CATEGORY BIRD
Model: ADDITION
Will be a copy of SECOND-GOAL when the model runs
SECOND-GOAL
   ARG1 5
   ARG2 2
NIL
1> (run 10)
    0.000
           COUNT
                     GOAL
                                         SET-BUFFER-CHUNK GOAL FIRST-GOAL REQUESTED NIL
           SEMANTIC
    0.000
                     GOAL
                                         SET-BUFFER-CHUNK GOAL G1 REQUESTED NIL
                                         SET-BUFFER-CHUNK GOAL SECOND-GOAL REQUESTED NIL
    0.000 ADDITION
                     GOAL
    0.500
                                         Stopped because no events left to process
0.5
147
NIL
2> (with-model semantic
     (goal-focus g2))
G2
3> (run 10)
    0.500
           SEMANTIC GOAL
                                            SET-BUFFER-CHUNK GOAL G2 REQUESTED NIL
           SEMANTIC PROCEDURAL
    0.500
                                            CONFLICT-RESOLUTION
    0.550 SEMANTIC PROCEDURAL
                                            PRODUCTION-FIRED INITIAL-RETRIEVE
    0.550 SEMANTIC PROCEDURAL
                                            CLEAR-BUFFER RETRIEVAL
    0.550 SEMANTIC DECLARATIVE
                                            START-RETRIEVAL
    0.550 SEMANTIC PROCEDURAL
                                            CONFLICT-RESOLUTION
    0.600 SEMANTIC DECLARATIVE
                                            RETRIEVED-CHUNK P14
    0.600 SEMANTIC DECLARATIVE
                                            SET-BUFFER-CHUNK RETRIEVAL P14
    0.600 SEMANTIC PROCEDURAL
                                            CONFLICT-RESOLUTION
    0.650 SEMANTIC PROCEDURAL
                                            PRODUCTION-FIRED CHAIN-CATEGORY
    0.650 SEMANTIC PROCEDURAL
                                            CLEAR-BUFFER RETRIEVAL
    0.650 SEMANTIC DECLARATIVE
                                            START-RETRIEVAL
    0.650
           SEMANTIC PROCEDURAL
                                            CONFLICT-RESOLUTION
    0.700
           SEMANTIC DECLARATIVE
                                            RETRIEVED-CHUNK P20
           SEMANTIC DECLARATIVE
                                            SET-BUFFER-CHUNK RETRIEVAL P20
    0.700
    0.700
           SEMANTIC
                     PROCEDURAL
                                            CONFLICT-RESOLUTION
           SEMANTIC PROCEDURAL
    0.750
                                            PRODUCTION-FIRED DIRECT-VERIFY
           SEMANTIC PROCEDURAL
    0.750
                                            CLEAR-BUFFER RETRIEVAL
    0.750 SEMANTIC PROCEDURAL
                                            CONFLICT-RESOLUTION
    0.750
                     -----
                                            Stopped because no events left to process
0.25
36
NIL
```

4> (with-model-fct 'count

```
'((goal-focus)))
Goal buffer is empty
NIL

E> (with-model foo (goal-focus))
#|Warning: F00 does not name a model in the current meta-process |#
```

Other multiple model examples

There are two other example models which define multiple synchronous models available in the examples directory. Each will be described briefly here and more details can be found in the comments in those files.

The "examples/multiple-models/multi-model-talking-models.lisp" file defines three very simple models which communicate by speaking. The corresponding "examples/multiple-models/multimodel-talking.lisp" and "examples/multiple-models/multi-model-talking.py" files contain the code which installs the microphone devices and monitors for the output-speech actions to handle that communication when running the models.

The "examples/other/game-of-life.lisp" file uses multiple models along with the AGI to display a set of cells following the rules of Conway's Game of Life. Each cell is controlled by a separate model which can see how many neighbors it has through a feature in the visicon, and indicates it current state each cycle through a speak action.

Configuring Real Time Operation

When a meta-process is run with the real-time flag set to a non-nil value the system is run in step with an external clock. By default, the clock used is the Lisp get-internal-real-time function, but the user can change that default behavior to specify an alternate clock as well as customize some other features of how the meta-process executes in real time mode. The command mp-real-time-management is the mechanism for changing the operation. Before describing that command, a more complete description of how the meta-process advances the clock in real time mode will be provided.

When a meta-process is not run in real time mode, as described in the <u>running section</u>, the scheduled events drive the clock directly and there is no delay between event executions regardless of the difference in time between them. When the meta-process runs in real time mode the "ACT-R time" is still determined by the events on the queue, but their execution is delayed, if necessary, so as to not run ahead of the real time clock provided. Here is some Lisp pseudo-code that describes the operation of the meta-process running in real time mode:

```
(defun process-real-time-events (real-time-scale)
  (setf act-r-start-time (mp-time))
  (setf starting-real-time (dispatch-apply real-time-function))
  (loop
    (when (run-end-conditions-satisfied) (return))
    (setf meta-p-time
      (min (evt-time (next-event))
           (case real-time-mode
              (absolute
                  (/ (dispatch-apply real-time-function) real-units-per-second))
              (interval
                  (+ act-r-start-time
                     (* real-time-scale
                        (/ (- (dispatch-apply real-time-function) starting-real-time)
                            real-units-per-second)))))))
    (if (<= (evt-time (next-event)) meta-p-time)</pre>
        (execute (next-event))
      (dispatch-apply real-time-slack meta-p-time (evt-time (next-event)))))))
```

The functions in blue are either not ACT-R commands or not described in this manual, and should be assumed to work as follows:

run-end-conditions-satisfied returns true when any condition(s) specified for the current run have been met.

next-event returns the next event from the event queue.

execute performs all the actions necessary to deal with an event (calling the event hooks, printing the trace, calling the action function, etc.).

dispatch-apply is like the Lisp apply function except that it works for both internal Lisp functions and ACT-R commands provided through the dispatcher (it is described in the remote file found in the docs directory).

The variables in red are items that can be set by the user to control how real time runs.

real-time-scale is the value passed to the run command to indicate it should be in real-time (where a value of t corresponds to 1.0).

real-time-function must be a function or command that takes no parameters. It should return a number which represents a time, and those numbers should be non-decreasing i.e. time can't move backwards but can stand still. How that time is used depends on the real-time-mode. The default function for this value is the Lisp function **get-internal-real-time**.

real-time-mode There are two options for providing a real time clock: absolute or interval. If it is absolute time mode then the real-time-function returns the current time for the system directly. If it is the interval time mode then the real-time-function is an interval timer used to pace the model -- it is the difference between its starting value and the current value plus the model's starting time that determines the "current" time. The default value is interval.

real-units-per-second is a number which is used to scale the return value from the real-time-function into seconds. The default value is the value of the Lisp variable **internal-time-units-per-second**.

real-time-slack this must be a function which accepts two parameters. It is called whenever the next model event is delayed because the real time has not yet advanced to that event's time. The first parameter it is passed is the current real time (in milliseconds) and the second parameter is the time of the next scheduled event (in milliseconds). The default function just calls bt:thread-yield to allow other threads an opportunity to run since a long wait may loop over this many times, but it could also be used to perform some external communication with a task or provide a cleaner 'wait' action if one

knows there are no asynchronous actions which could schedule new events before the one that's waiting.

Dynamic events

Because events can be scheduled asynchronously with the running of the model through the dispatcher it is possible in real-time mode for an event to be scheduled at a time that is earlier than the current next event when that next event is in the future and the system is waiting for time to pass. [Even with that however it is not possible to schedule an event for a time which has already passed. The ACT-R clock will only move forward and any event scheduled with a time that has already passed will be scheduled with the current real-time time instead.] Because some events are scheduled based on when other events occur (the schedule-event-after-* commands) it may be important to have those events sensitive to new events which occur earlier in time even if they have already been scheduled because of an event that was scheduled. That is the purpose of the :dynamic keyword parameter in those scheduling functions. If it is specified as t then such an event may be rescheduled for an earlier time if such a triggering event happens, and such events are referred to as dynamic events.

Of the events generated by the standard modules of the system, only the procedural module currently schedules any dynamic events. The conflict-resolution event of the procedural module is dynamic and will be rescheduled to occur after any newer model events which are generated relative to when it is initially scheduled. That is important so that the model can respond to external actions which occur (typically visual or aural percepts) when they happen instead of having to wait for the next internal action which may have already caused a conflict-resolution to be scheduled in the future (after a retrieval failure for example). That is very likely the only event which needs to be dynamic for most modeling purposes, but if one is creating new modules or tools which are scheduled using the after-* commands it it may be important to set the :dynamic flag for those events if they need to be sensitive to asynchronous events which occur.

One final note is that although dynamic events are described with respect to real-time running, it can also be an issue when running without real-time (when the events are the clock). That can happen if actions are scheduled out of order during an event i.e. if an action that occurs because of an event itself schedules multiple events and those events are not scheduled in chronological order. That can cause a waiting after-* event to be scheduled in response to an event further in the future than newer events that might also trigger it. The dynamic schedule mechanism still applies in that case, and will reschedule things appropriately if they are marked as dynamic.

Commands

mp-real-time-management

Syntax:

```
mp-real-time-management {:time-function timefct} {:units-per-second ups} {:slack-function slackfct} {:mode [ interval | absolute ] } -> [ t | nil ]
```

Arguments and Values:

timefct ::= a function or command to use as the real time clock (the real-time-function value) ups ::= a positive number specifying the number of units in a second for timefct (the real-units-per-second value)

slackfct ::= a function or command to call when the model has to wait for real time to pass (the real-time-slack value)

Description:

The mp-real-time-management command is used to modify how the meta-process operates when run in real-time mode. It sets the real time controls to the provided values and returns **t**. How those controls affect the operation of the system is described in the <u>Configuring Real Time Operation</u> section above.

If the model is currently running or any of the provided parameters are invalid then no changes will be made, there will be a warning printed, and the value **nil** will be returned.

Examples:

These examples only show the possible warnings.

```
E> (mp-real-time-management :mode 'other)
#|Warning: Mode OTHER not a valid value for mp-real-time-management. Must be absolute or
interval. |#
NIL

E> (mp-real-time-management :time-function nil)
#|Warning: Time-function NIL not a valid function for mp-real-time-management |#
NIL

E> (mp-real-time-management :units-per-second t)
#|Warning: Units-per-second T must be a positive number |#
NIL

E> (mp-real-time-management :slack-function 'not-function)
#|Warning: Slack-function NOT-FUNCTION not a valid function for mp-real-time-management |#
NIL

1> (schedule-event-now 'mp-real-time-management)
```

```
2E> (run 1)
#|Warning: Mp-real-time-management cannot adjust real-time operation while the model is running. |#

0.000 PROCEDURAL CONFLICT-RESOLUTION

0.000 ----- Stopped because no events left to process

0.0
3
NIL
```

Module Activity and Brain Predictions

The activity of the modules in ACT-R (as reported through their buffers) along with a mapping of those modules/buffers onto the brain can be used to make predictions from a model for data from various imaging methods like fMRI, EEG, PET, or MEG. The ACT-R software includes commands for getting a summary of the module activity as well as commands for producing a prediction of a blood-oxygen-level dependent (BOLD) response for comparison to fMRI data.

This section will describe how one can have the system record the module activity and ways to access that data, and the next one will describe the tools which use that data to produce a BOLD response. For information on mappings of modules to brain regions and additional details on predicting the BOLD response there are many papers available from the <u>ACT-R website</u> under the fMRI category, and a good place to start is the paper "<u>A central circuit of the mind</u>".

What counts as buffer activity?

Buffer activity is determined from the <u>buffer-trace data</u> which means only actions which occur as scheduled events will be considered. That covers all the normal actions of the provided modules and their use through the procedural module in a model, but any function calls made outside of the events which directly affect a buffer (for example set-buffer-chunk) will not be counted as buffer activity. Activity starts when one of three things occurs: a request (or modification request) is made to the buffer, a chunk is placed into the buffer, or a "state busy" query of the buffer is true. Once activity has started, the buffer will be considered active until one of three conditions occurs: the "state busy" query returns **nil**, the "state free" query returns true, or a new request (or modification request) is made to the buffer (which ends the current activity and also starts a new one).

Some buffers (in particular the goal buffer) may have activities which are instantaneous i.e. the start and stop times are the same. That activity is still recorded, and how that is treated by the different activity reporting mechanisms will be discussed with each one.

Recording module activity

The data used to determine module activity and produce a model's BOLD response is the buffer-trace history data as described in the <u>buffer trace module</u> section. Therefore one must record that history data along with the buffers for which the information is needed. That can be done directly by

recording the "buffer-trace" history, or by recording one of the processors described in this section or the next. Here's an example that records the data for four of the buffers from the included modules:

```
> (record-history "buffer-trace" "goal" "visual" "vocal" "manual")
```

Recording the module activity can be a costly operation over the course of a long model run, so it is recommended that one only record the information that's needed for efficiency purposes.

Getting module activity

There are three history data processors available to convert that buffer-trace data into module activity which provide different ways to report that data. All of these history processors report the activity at the buffer level i.e. if a module has more than one buffer each buffer is tracked separately. If one would like to process the module activity differently it is always possible to use buffer-trace history information directly. Each of the processors also accepts two optional parameters to restrict the times over which the data should be reported. It is important to note that restricting that range for the processor is not necessarily the same as processing a restricted range of the buffer-trace data i.e.

```
(get-history "module-demand-times" nil 3 14)
is not likely to be the same as:
(process-history-data "module-demand-times" nil nil (3 14))
```

The reason for the discrepancy happens when activity crosses one of the provided time boundaries. With the first approach the start signal would be lost for activity which began before the start time but had a stop time within the range and the stop signal would be lost for activity which began during the range but ended after. However the second approach will be able to accurately report the results for activity which overlaps with the range requested.

For each of the processors there is also a corresponding Lisp command which will get the processed data and then decode the JSON string into Lisp data.

module-demand-times

The module-demand-times processor will convert the buffer-trace history into a list of lists, where each sublist has two elements. The first element of a sublist is the name of a buffer and the second element is a list of two element lists indicating the start and stop time at which that buffer was active:

```
((buffer-name ((start-time stop-time)*)*)
```

Example:

```
1> (load "ACT-R:tutorial;lisp;zbrodoff.lisp")
2> (record-history "buffer-trace" "goal" "manual")
Т
3> (zbrodoff-set)
              2 (8)
                           3 (8)
                                       4 (8)
Block 1 2.295 (8) 2.807 (8)
                                   3.320 (8)
((2.2949998 2.8075 3.32) (8 8 8))
4> (get-history-data "module-demand-times")
"[[\"GOAL\",[[0.0,0.0],[2.735,2.735],[5.63,5.63],[8.375,8.375],[10.62,10.62],
[13.965,13.965],[17.31,17.31],[20.555,20.555],[22.9,22.9],[25.145,25.145],[27.99,27.99],
[30.835,30.835],[33.68,33.68],[37.025,37.025],[39.37,39.37],[42.215,42.215],[44.46,44.46],
[47.805,47.805],[50.65,50.65],[53.895,53.895],[56.24,56.24],[58.485,58.485],[61.73,61.73],
[64.075,64.075],[67.32,67.32]]],[\"MANUAL\",[[2.735,3.035],[5.63,5.78],[8.375,8.525],
[10.62,10.87],[13.965,14.215],[17.31,17.46],[20.555,20.805],[22.9,23.05],[25.145,25.395],
[27.99,28.24],[30.835,31.085],[33.68,33.93],[37.025,37.275],[39.37,39.62],[42.215,42.365],
[44.46,44.71],[47.805,48.055],[50.65,50.8],[53.895,54.145],[56.24,56.39],[58.485,58.635],
[61.73,61.98],[64.075,64.225],[67.32,67.47]]]]"
5> (process-history-data "module-demand-times" nil nil (3 14))
"[[\"GOAL\",[[5.63,5.63],[8.375,8.375],[10.62,10.62],[13.965,13.965]]],[\"MANUAL\",
[[2.735,3.035],[5.63,5.78],[8.375,8.525],[10.62,10.87],[13.965,14.215]]]]"
```

Lisp Command:

module-demand-times {:start start} {:end end} -> ((buffer-name ((start-time stop-time)*)*)

Arguments and Values:

start ::= a number indicating the starting time over which activity is to be reported in seconds end ::= a number indicating the end time over which activity is to be reported in seconds buffer-name ::= the name of a buffer start-time ::= a number indicating the starting time for an active period of the buffer stop-time ::= a number indicating the end time for an active period of the buffer

Description:

The module-demand-times command has two keyword parameters, :start and :end, which can be used to restrict the reported activity to the specified range. If no start time is provided then it starts at time 0, and if no end time is provided it ends at the current model time. It returns a list of lists of buffer activity times for all of the buffers for which the "buffer-trace" history is recorded.

If a start and/or end time is provided then only activities which overlap with that range will be reported. That may include activities which begin before the provided start time and persist past it as well as activities which begin before the provided end time and continue past it.

Examples:

```
1> (load "ACT-R:tutorial;lisp;zbrodoff.lisp")
T
2> (record-history "buffer-trace" "goal" "manual")
T
T
T
3> (zbrodoff-set)

2 ( 8) 3 ( 8) 4 ( 8)
Block 1 2.295 ( 8) 2.807 ( 8) 3.320 ( 8)
((2.2949998 2.8075 3.32) (8 8 8))

4> (module-demand-times)
((GOAL ((0.0 0.0) (2.735 2.735) (5.63 5.63) (8.375 8.375) (10.62 10.62) (13.965 13.965)
(17.31 17.31) (20.555 20.555) (22.9 22.9) (25.145 25.145) ...))
(MANUAL ((2.735 3.035) (5.63 5.78) (8.375 8.525) (10.62 10.87) (13.965 14.215) (17.31 17.46) (20.555 20.805) (22.9 23.05) (25.145 25.395) (27.99 28.24) ...)))

5> (module-demand-times :start 3 :end 14)
((GOAL ((5.63 5.63) (8.375 8.375) (10.62 10.62) (13.965 13.965))) (MANUAL ((2.735 3.035) (5.63 5.78) (8.375 8.375) (10.62 10.87) (13.965 14.215))))
```

module-demand-functions

$$n = \left\lceil \frac{end - start}{step} \right\rceil$$

Each of those elements, indexed by i, represents the activity recorded for the time (S,S,) where:

$$s_0 = start$$

 $s_i = s_{i-1} + step$

If a buffer has any activity within a time segment the corresponding element of the list will be 1 and if it has no activity the value will be 0. Note that if the end time of a buffer activity (as reported by module-demand-times) corresponds with the end time of a segment that will not count as activity

occurring at the start of the next segment i.e. if the step size is 2 and a buffer has reported activity of (0.0 . 2.0) that will only count as activity in the first step and not the second.

An activity that takes no time (the start and end times are the same) is still considered activity and will result in a 1 for the step in which it occurs.

There are four optional parameters for the module-demand-functions processor which are the start time, stop time, step length, and output flag respectively. The first three were described above. The output flag is a generalized boolean which indicates whether the table of data should also be sent to the command output trace.

Example:

```
1> (load "ACT-R:tutorial;lisp;zbrodoff.lisp")
2> (record-history "buffer-trace" "goal" "manual")
Т
Т
Т
3> (zbrodoff-set)
             2 (8)
                        3 (8)
Block 1 2.295 (8) 2.807 (8)
                               3.320 (8)
((2.2949998 \ 2.8075 \ 3.32) \ (8 \ 8 \ 8))
4> (get-history-data "module-demand-functions")
"[[\"GOAL\",1,1,1,0,1,1,1,0,1,1,1,1,0,1,1,0,1,1,0,1,1,0,1,1,0,1,1,1,0,1,1,1,0,1,1],
5> (process-history-data "module-demand-functions" nil nil (0 30 2 t))
   time
           GOAL
                MANUAL
  0.000
          1.000
                 0.000
  2.000
          1.000
                 1.000
  4.000
          1.000
                 1.000
  6.000
          0.000
                 0.000
          1.000
                 1.000
  8.000
 10.000
          1.000
                 1.000
 12.000
          1.000
                 1.000
 14.000
          0.000
                 1.000
 16.000
          1.000
                 1.000
 18.000
          0.000
                 0.000
 20.000
          1.000
                 1.000
 22.000
          1.000
                 1.000
 24.000
          1.000
                 1.000
 26.000
          1.000
                 1.000
 28.000
          0.000
                 1.000
"[[\"GOAL\",1,1,1,0,1,1,1,0,1,0,1,1,1,1,0],[\"MANUAL\",0,1,1,0,1,1,1,1,1,1,1,1,1,1,1,1,1]]"
```

Lisp Command:

module-demand-functions {:start start} {:end end} {:step step} {:output output} -> ((buffer [0 | 1]*)*)

Arguments and Values:

start ::= a number indicating the starting time for which activity is to be reported in seconds end ::= a number indicating the end time for which activity is to be reported in seconds step ::= a number indicating the granularity of the activity record to report in seconds output ::= a generalized boolean indicating whether to print the results to the command trace buffer ::= the name of a buffer

Description:

The module-demand-functions command has four keyword parameters. :start and :end can be used to restrict the reported activity to the specified range. If no start time is provided then it starts at time 0, and if no end time is provided it ends at the current model time. :step can be specified to indicate the length of the time intervals over which activity is reported, and if not provided defaults to the current value of the :bold-inc parameter. :output indicates whether or not the data should be shown in the command output trace. It returns a list of lists of buffer activity during the requested time in the indicated interval lengths for all of the buffers for which the "buffer-trace" history is recorded.

Examples:

```
1> (load "ACT-R:tutorial;lisp;zbrodoff.lisp")
   (record-history "buffer-trace" "goal" "manual")
Т
Т
3> (zbrodoff-set)
              2 (8)
                          3 (8)
Block 1 2.295 (8) 2.807 (8) 3.320 (8)
((2.2949998 2.8075 3.32) (8 8 8))
4> (module-demand-functions)
((GOAL 1 1 1 0 1 1 1 0 1 ...) (MANUAL 0 1 1 0 1 1 1 1 1 ...))
5> (module-demand-functions :start 0 :end 30 :step 2 :output t)
    time
            GOAL
                  MANUAL
   0.000
           1.000
                   0.000
   2.000
           1.000
                   1.000
   4.000
           1.000
                   1.000
   6.000
           0.000
                   0.000
   8.000
           1.000
                   1.000
  10.000
           1.000
                   1.000
  12.000
           1.000
                   1.000
  14.000
           0.000
                   1.000
           1.000
  16.000
                   1.000
           0.000
  18.000
                   0.000
  20.000
           1.000
                   1.000
  22.000
           1.000
                   1.000
  24,000
           1.000
                   1.000
  26.000
           1.000
                   1.000
  28.000
           0.000
                   1.000
((GOAL 1 1 1 0 1 1 1 0 1 ...) (MANUAL 0 1 1 0 1 1 1 1 1 ...))
```

module-demand-proportion

The module-demand-proportion processor works the same as <u>module-demand-functions</u> except that instead of zero or one to indicate activity it reports the proportion of the time during the interval when there was activity. If a module activity takes 0 time (the start and end times are the same) it is considered to take 1ms for computing the proportion.

Example:

```
1> (load "ACT-R:tutorial;lisp;zbrodoff.lisp")
      (record-history "buffer-trace" "goal" "manual")
Т
Τ
3> (zbrodoff-set)
                                                                    3 (8)
                                     2 (8)
Block 1 2.295 (8) 2.807 (8)
                                                                                         3.320 (8)
((2.2949998 2.8075 3.32) (8 8 8))
4> (get-history-data "module-demand-proportion")
"[[\"GOAL\",5.0e-4,5.0e-4,5.0e-4,0,5.0e-4,5.0e-4,5.0e-4,0,5.0e-4,0,5.0e-4,5.0e-4,5.0e-
4,5.0e-4,0,5.0e-4,5.0e-4,0,5.0e-4,5.0e-4,0,5.0e-4,5.0e-4,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-4,0,5.0e-5,0,
4,5.0e-4,5.0e-4,0,5.0e-4,5.0e-4],
[\"MANUAL\",0,0.15,0.075,0,0.075,0.125,0.0175,0.1075,0.075,0,0.125,0.075,0.125,0.005,0.12,
0.125,0.125,0,0.125,0.125,0.075,0.075,0.125,0.0975,0.0275,0.075,0.0525,0.0725,0.075,0.075,0.12
5,0,0.075001955,0.075]]
5> (process-history-data "module-demand-proportion" nil nil (0 30 2 t))
                               GOAL MANUAL
           time
        0.000
                             0.001
                                                 0.000
        2.000
                             0.001
                                                 0.150
       4.000
                             0.001
                                                 0.075
       6.000
                             0.000
                                                 0.000
       8.000
                             0.001
                                                 0.075
                                                 0.125
     10.000
                             0.001
                            0.001
     12.000
                                                 0.018
     14.000
                            0.000
                                                 0.108
     16.000
                            0.001
                                                 0.075
     18,000
                            0.000
                                                 0.000
     20.000
                             0.001
                                                 0.125
     22.000
                            0.001
                                                 0.075
     24.000
                            0.001
                                                  0.125
     26.000
                            0.001
                                                 0.005
     28.000
                             0.000
                                                 0.120
"[[\"GOAL\",5.0e-4,5.0e-4,5.0e-4,0,5.0e-4,5.0e-4,5.0e-4,0,5.0e-4,0,5.0e-4,5.0e-4,5.0e-
4,5.0e-4,0],
[\"MANUAL\",0,0.15,0.075,0,0.075,0.125,0.0175,0.1075,0.075,0,0.125,0.075,0.125,0.005,0.12]
```

Lisp Command:

module-demand-proportion {:start start} {:end end} {:step step} {:output output} -> ((buffer prop*)*)

Arguments and Values:

start ::= a number indicating the starting time for which activity is to be reported in seconds end ::= a number indicating the end time for which activity is to be reported in seconds step ::= a number indicating the granularity of the activity record to report in seconds output ::= a generalized boolean indicating whether to print the results to the command trace buffer ::= the name of a buffer prop ::= the proportion of time the bufer was busy during a time step

Description:

The module-demand-proportion command works the same as <u>module-demand-functions</u> except that it returns the proportion of time that a buffer was active during a time step instead of a simple zero or one flag. If the start and stop times are the same for an activity it is assumed to be 1ms long for computing the proportion.

Examples:

```
1> (load "ACT-R:tutorial;lisp;zbrodoff.lisp")
2> (record-history "buffer-trace" "goal" "manual")
Τ
Τ
3> (zbrodoff-set)
              2 (8)
                                       4 (8)
                          3 (8)
Block 1 2.295 (8) 2.807 (8)
                                  3.320 (8)
((2.2949998 2.8075 3.32) (8 8 8))
4> (module-demand-proportion)
((GOAL 5.0e-4 5.0e-4 5.0e-4 0 5.0e-4 5.0e-4 5.0e-4 0 5.0e-4 ...) (MANUAL 0 0.15 0.075 0
0.075 0.125 0.0175 0.1075 0.075 ...))
5> (module-demand-proportion :start 0 :end 30 :step 2 :output t)
    time
            GOAL MANUAL
   0.000
           0.001
                   0.000
                   0.150
   2.000
           0.001
   4.000
           0.001
                   0.075
   6.000
           0.000
                   0.000
   8.000
           0.001
                   0.075
  10.000
           0.001
                   0.125
  12.000
           0.001
                   0.018
  14.000
           0.000
                   0.108
  16.000
           0.001
                   0.075
  18.000
           0.000
                   0.000
  20.000
           0.001
                   0.125
                   0.075
  22.000
           0.001
  24,000
           0.001
                   0.125
  26.000
           0.001
                   0.005
  28.000
           0.000
                   0.120
((GOAL 5.0e-4 5.0e-4 5.0e-4 0 5.0e-4 5.0e-4 5.0e-4 0 5.0e-4 ...) (MANUAL 0 0.15 0.075 0
0.075 0.125 0.0175 0.1075 0.075 ...))
```

BOLD module

The BOLD module provides the modeler with a history strema processor and Lisp command for predicting blood-oxygen-level dependent (BOLD) response values from the activity of the buffers recorded through the buffer-trace history for comparison to fMRI data. This section will provide a general description of how that calculation is performed and then describe the parameters for configuring it and the processor and command to generate the data. This description assumes that one has read the previous section on module activity and brain predictions for an understanding of how the buffer activities are determined and that one has some understanding of what the BOLD response in fMRI data represents.


The basic concept used to create the BOLD response prediction for a model is that while a module is active it corresponds to an increased metabolic demand which produces a hemodynamic response that generates a BOLD response. Therefore, to compute the BOLD response for a model run we need two things. The first is the model's buffer activity which we will get from the module-demand-times data. We will use those times to create a demand function for the buffer activity where the value of the function is 1 when the buffer is active and 0 when it is not. We will call this function D(t). The other is a representation of the hemodynamic response. For that we will use a difference of two Gamma probability density functions which is used by many other researchers and also used in the SPM software package (Friston, Ashburner, Kiebel, Nichols, & Penny, 2011).

The Gamma probability density function is described in terms of two parameters, an exponent (or shape), **a** and a scale, **b**:

gammapdf
$$(x; a, b) = \frac{x^{a-1}e^{-x/b}}{b^a(a-1)!}$$

The default settings for the parameters in the BOLD module use the same exponent and scale parameters for the positive and negative curves as SPM (a=6,b=1 for positive and a=16,b=1 for the negative), but they are combined using a slightly different scaling in the ACT-R representation. How to set the parameters for specifying the positive and negative curves and the parameters to control the scale factors combining them are described below along with how one would change that to match the scaling used in SPM.

Here is what the default functions used by the BOLD module look like:




The green curve is the hemodynamic response function we will use and call H(t).

To produce the BOLD response at a given time, B(t), we need to compute the accumulated hemodynamic response over all of the activity of the module up to that time. That can be done using the convolution of the demand function with the hemodynamic response function:

$$B(t) = \int_{0}^{t} D(x)H(t-x)dx$$

Because our demand function only has values of 0 or 1 the B(t) value is the area under the reversed and shifted hemodynamic response function in the periods of module activity.

Here's an example showing the BOLD response for a module which has activity during the times 1-3, 15-16, 20-21, 26-28, and 31-33 and how the values were computed for three of those points:



Parameters

:bold-param-mode

This parameter determines how the exponent parameters for the Gamma distributions are set as well as how the scaling is determined for combining the positive and negative curves to generate the hemodynamic response function. It has two possible values: act-r and spm. The default value is act-r. The differences between those modes will be described with the affected parameters.

:bold-exp & :neg-bold-exp

These two parameters are used to set the exponent parameters (the ${\bf a}$ parameters) for the positive and

negative Gamma distributions which generate the hemodynamic response function, and the values

must be integers. If the :bold-param-mode value is spm then the :bold-exp and :neg-bold-exp values

should be set to the **a** values desired, which would be 6 and 16 respectively for the default function.

If the :bold-param-mode value is act-r then these parameters must be set to one less than the ${\bf a}$

parameters desired i.e. they would need to be set to 5 and 15 for the default function. Since act-r

mode is the default these parameters default values are 5 and 15. However, if one changes :bold-

param-mode to spm when both :bold-exp and :neg-bold-exp are set to their default values they will

be automatically changed to the corresponding spm values of 6 and 16.

:bold-scale & :neg-bold-scale

These parameters are used to set the scale parameters for the positive and negative Gamma

distributions which generate the hemodynamic response function. Their setting does not depend on

the :bold-param-mode value and both default to a value of 1.

:bold-positive & :bold-negative

These two parameters are the weights used when combining the positive and negative Gamma

distributions to generate the hemodynamic response function. The default values are 6 and 1

respectively.

When :bold-param-mode is set to act-r the weights are used as follows to combine the positive and

negative Gamma distributions:

 $H(t) = \left[\frac{bp}{bp - bn} positive(t)\right] - \left[\frac{bn}{bp - bn} negative(t)\right]$

where:

bp = :bold-positive value

bn = :bold-negative value

positive(t) = the positive Gamma distribution

negative(t)= the negative Gamma distribution

With this scaling method a module with a constant activity will have a BOLD value of 1, but the peak

BOLD value for a module may exceed a value of 1.

567

When :bold-param-mode is set to spm the weights are used as follows to combine the positive and negative Gamma distributions:

$$H(t) = \left[\frac{bp}{\max(bp,bn)} positive(t)\right] - \left[\frac{bn}{\max(bp,bn)} negative(t)\right]$$

where:

bp = :bold-positive value
bn = :bold-negative value
positive(t) = the positive Gamma distribution
negative(t)= the negative Gamma distribution

This is the scaling used in SPM to generate the default hemodynamic response function.

:bold-settle

This parameter is used to help with the efficiency of computing the BOLD response values. It can be set to a time in seconds beyond which H(t) can be considered as having a value of 0. Only activity which occurs within :bold-settle seconds of the current time is used in computing the BOLD response (essentially the integral is computed from t-:bold-settle to t instead of 0 to t). The default value is 40 (with the other default values H(40) = -.0000052).

:bold-inc

This parameter is used to set the interval, in seconds, at which the BOLD predictions are computed. The default value is 2 seconds.

:point-predict

This parameter is used to specify a list of buffer names for which the corresponding module activities occur instantaneously, but a BOLD prediction is still desired (since the standard calculation will result in values of 0 for instantaneous activity). For the buffers on this list the demand associated with each activity will be treated as an impulse function with an area of 1 occurring at the time of the activity. Thus, the B(t) value will be the sum of the H(x-t) values at the activity times. The default value is a list containing the buffer name goal.

History Processors

There are three history processors which can be used to get the BOLD prediction data from the buffer-trace history. They all use the same process described above for computing the results, but differ in how exactly the data is reported.

bold-prediction

The bold-prediction history processor computes the BOLD prediction as described above for each of the buffers in the current buffer-trace history. It has two optional parameters which can be used to specify a starting and ending time to limit the range over which the predictions are computed, and a third optional parameter which indicates whether the data should be printed to the command trace. It returns a list of lists of where the first item in a sublist is the name of a buffer and the rest of the list is the BOLD prediction data for each time step in the range of times requested (which is 0 to current time if none provided): ((buffer bold-value*)*).

Example:

```
1> (load "ACT-R:tutorial;lisp;zbrodoff.lisp")
2> (record-history "buffer-trace" "goal" "manual")
Т
Т
3> (zbrodoff-set)
              2 (8)
                           3 (8)
                                       4 (8)
Block 1 2.295 (8) 2.807 (8) 3.320 (8)
((2.2949998 2.8075 3.32) (8 8 8))
4> (get-history-data "bold-prediction")
"[[\"MANUAL\",0.0,7.116422e-7,0.015379674,0.059214685,0.07821559,0.074922346,0.07778276,
0.08459592, 0.084080234, 0.07669602, 0.06397217, 0.056394327, 0.06966068, 0.077085264, 0.08674426
4,0.09169287,0.091012,0.09067639,0.0911798,0.08056933,0.082401596,0.09309575,0.08512345,0.
079779565, 0.0789257, 0.077776566, 0.07488024, 0.062607914, 0.062190473, 0.073173605, 0.073846556
,0.06338371,0.06570311],
[\"GOAL\", 0.0036787947, 0.12099249, 0.27242562, 0.36315846, 0.40226096, 0.41133723, 0.4366023, 0.
41118938,0.36133355,0.30863062,0.30381384,0.29339045,0.33684182,0.39727795,0.42140335,0.40
263155, 0.3712272, 0.35467446, 0.3532136, 0.31072795, 0.32460716, 0.36801147, 0.37339666, 0.403027
53,0.37886032,0.34314317,0.33192348,0.32307497,0.3179245,0.36359704,0.41549307,0.39395335,
0.36075956]]"
5> (process-history-data "bold-prediction" nil nil (4 30))
"[[\"MANUAL\",0.015379674,0.059214685,0.07821559,0.074922346,0.07778276,0.08459592,0.08408
0234, 0.07669602, 0.06397217, 0.056394327, 0.06966068, 0.077085264, 0.086744264],
[\"GOAL\", 0.27242562, 0.36315846, 0.40226096, 0.41133723, 0.4366023, 0.41118938, 0.36133355, 0.30
863062, 0.30381384, 0.29339045, 0.33684182, 0.39727795, 0.42140335]]"
6> (process-history-data "bold-prediction" nil nil (4 30 t))
    time
            GOAL MANUAL
   5.000
           0.272
                   0.015
   7.000
           0.363
                   0.059
```

```
9.000
         0.402
                  0.078
11.000
         0.411
                  0.075
         0.437
13.000
                  0.078
15.000
         0.411
                  0.085
17.000
         0.361
                  0.084
19.000
         0.309
                  0.077
21.000
         0.304
                  0.064
23.000
         0.293
                  0.056
25.000
         0.337
                  0.070
27.000
         0.397
                  0.077
29.000
         0.421
                  0.087
```

"[[\"MANUAL\",0.015379674,0.059214685,0.07821559,0.074922346,0.07778276,0.08459592,0.08408 0234,0.07669602,0.06397217,0.056394327,0.06966068,0.077085264,0.086744264], [\"GOAL\",0.27242562,0.36315846,0.40226096,0.41133723,0.4366023,0.41118938,0.36133355,0.30 863062,0.30381384,0.29339045,0.33684182,0.39727795,0.42140335]]"

bold-prediction-with-time

The bold-prediction-with-time history processor operates like the bold-prediction processor above except for two small differences. The first is that it does not have an optional parameter for printing the results. The other is that there is an additional list of values as the first sublist in the results. That list starts with the name time and is followed by the values for the mid-points of the time intervals for which the BOLD predictions in the remaining lists are generated (the same as the first column which is printed in the output for the bold-prediction processor): ((time mid-point*)(buffer bold-value*)*).

Example:

```
1> (load "ACT-R:tutorial;lisp;zbrodoff.lisp")
      (record-history "buffer-trace" "goal" "manual")
Т
Т
3> (zbrodoff-set)
                                  2 (8)
                                                               3 (8)
Block 1 2.295 (8) 2.807 (8) 3.320 (8)
((2.2949998 2.8075 3.32) (8 8 8))
4> (get-history-data "bold-prediction-with-time")
"[[\"time\",1,3,5,7,9,11,13,15,17,19,21,23,25,27,29,31,33,35,37,39,41,43,45,47,49,51,53,55
 ,57,59,61,63,65,67],
[\"GOAL\",0.0036787947,0.12099249,0.27242562,0.36315846,0.40226096,0.41133723,0.4366023,0.
41118938, 0.36133355, 0.30863062, 0.30381384, 0.29339045, 0.33684182, 0.39727795, 0.42140335, 0.40
263155, 0.3712272, 0.35467446, 0.3532136, 0.31072795, 0.32460716, 0.36801147, 0.37339666, 0.403027, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 0.36801147, 
53,0.37886032,0.34314317,0.33192348,0.32307497,0.3179245,0.36359704,0.41549307,0.39395335,
0.36075956],[\"MANUAL\",0.0,7.116422e-
7,0.015379674,0.059214685,0.07821559,0.074922346,0.07778276,0.08459592,0.084080234,0.07669
39,0.0911798,0.08056933,0.082401596,0.09309575,0.08512345,0.079779565,0.0789257,0.07777656
6,0.07488024,0.062607914,0.062190473,0.073173605,0.073846556,0.06338371,0.06570311]
5> (process-history-data "bold-prediction-with-time" nil nil (4 30))
"[[\"time\",5,7,9,11,13,15,17,19,21,23,25,27,29],
[\"GOAL\", 0.27242562, 0.36315846, 0.40226096, 0.41133723, 0.4366023, 0.41118938, 0.36133355, 0.30
```

```
863062,0.30381384,0.29339045,0.33684182,0.39727795,0.42140335],
[\"MANUAL\",0.015379674,0.059214685,0.07821559,0.074922346,0.07778276,0.08459592,0.0840802
34,0.07669602,0.06397217,0.056394327,0.06966068,0.077085264,0.086744264]]"
```

bold-prediction-with-time-scaled

The bold-prediction-with-time-scaled history processor operates like the bold-prediction-with-time processor above except for one difference. The data for each of the buffers is scaled such that it is in the range [0.0,1.0].

Example:

```
1> (load "ACT-R:tutorial;lisp;zbrodoff.lisp")
2> (record-history "buffer-trace" "goal" "manual")
Т
Т
3> (zbrodoff-set)
                                 2 (8)
                                                             3 (8)
Block 1 2.295 (8) 2.807 (8)
                                                                                3.320 (8)
((2.2949998 2.8075 3.32) (8 8 8))
4> (get-history-data "bold-prediction-with-time-scaled")
"[[\"time\",1,3,5,7,9,11,13,15,17,19,21,23,25,27,29,31,33,35,37,39,41,43,45,47,49,51,53,55
,57,59,61,63,65,67],
[\"GOAL\",0.0,0.2709802,0.62077206,0.8303538,0.92067575,0.9416408,1.0,0.94129926,0.8261384
4,0.7044012,0.69327503,0.6691983,0.7695656,0.9091656,0.9648923,0.92153174,0.8489916,0.8107
568, 0.8073824, 0.70924574, 0.74130505, 0.84156364, 0.8540028, 0.9224464, 0.86662316, 0.7841209, 0.
7582048, 0.73776585, 0.7258689, 0.83136684, 0.9512403, 0.9014862, 0.8248126],
[\"MANUAL\", 0.0, 7.644197e-
6,0.16520275,0.6360622,0.8401629,0.80478805,0.83551353,0.90869796,0.90315866,0.8238402,0.6
8716526, 0.60576695, 0.74826914, 0.8280213, 0.9317747, 0.9849308, 0.97761714, 0.97401214, 0.979419
6, 0.8654458, 0.88512737, 1.0, 0.9143645, 0.8569625, 0.8477906, 0.835447, 0.8043358, 0.672511, 0.6688, 0.8654458, 0.8654458, 0.88512737, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.8854855, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.885485, 0.88548555, 0.8854855, 0.8854855, 0.88548555, 0.8854855, 0.8854855, 0.8854855, 0.8854855, 0.8854855, 0.88548555, 0.88548555, 0.885485550
027, 0.7860037, 0.7932323, 0.6808443, 0.7057584]]"
5> (process-history-data "bold-prediction-with-time-scaled" nil nil (4 30))
"[[\"time\",5,7,9,11,13,15,17,19,21,23,25,27,29],
[\"GOAL\", 0.0, 0.5526537, 0.790827, 0.84611046, 1.0, 0.84520996, 0.5415381, 0.2205246, 0.19118564,
0.12769677,0.39235902,0.76047546,0.90742326],
[\"MANUAL\",0.0,0.61424035,0.88049155,0.83434474,0.8744264,0.9698962,0.96267015,0.8591985,
0.6809048, 0.57471997, 0.76061535, 0.86465275, 1.0]]"
```

Commands

predict-bold-response

Syntax:

```
predict-bold-response {start {end {output}}} -> ((buffer bold-data*)*)
```

Arguments and Values:

```
start ::= a time in seconds
end ::= a time in seconds
output ::= a generalized boolean indicating whether to print the results
buffer ::= the name of a buffer
bold-data ::= the prediction for the BOLD response of a buffer during a time interval
```

Description:

The predict-bold-response function can be used to get the predictions for the BOLD response from the recorded buffer-trace history information. It has two optional parameters which can be used to specify a starting and ending time to limit the range over which the predictions are computed, and a third optional parameter which indicates whether the data should be printed to the command trace (the default is to print the data). It returns a list of lists of where the first item in a sublist is the name of a buffer and the rest of the list is the BOLD prediction data for each time step in the range of times requested (which is 0 to current time if neither is provided).

If there is no current model a warning will be printed and **nil** will be returned. If either start or end is not a number or the interval between start and end is less than :bold-inc seconds a warning will be printed to indicate the issue.

Examples:

```
1> (load "ACT-R:tutorial;lisp;zbrodoff.lisp")
2> (record-history "buffer-trace" "goal" "manual")
Т
Т
3> (zbrodoff-set)
                          3 (8)
              2 (8)
                                       4 (8)
Block 1 2.295 (8) 2.807 (8) 3.320 (8)
((2.2949998 2.8075 3.32) (8 8 8))
> (predict-bold-response)
    time
            GOAL MANUAL
                   0.000
   1.000
           0.004
           0.121
                   0.000
   3.000
   5.000
           0.272
                   0.015
   7.000
                   0.059
           0.363
   9.000
           0.402
                   0.078
  11.000
           0.411
                   0.075
  13.000
           0.437
                   0.078
  15.000
           0.411
                   0.085
  17.000
           0.361
                   0.084
  19.000
           0.309
                   0.077
  21.000
           0.304
                   0.064
  23.000
           0.293
                   0.056
```

```
25.000
          0.337
                  0.070
 27.000
          0.397
                  0.077
          0.421
 29.000
                  0.087
 31.000
          0.403
                  0.092
  33.000
          0.371
                  0.091
  35.000
          0.355
                  0.091
  37.000
          0.353
                  0.091
  39.000
          0.311
                  0.081
 41.000
                  0.082
          0.325
 43.000
          0.368
                  0.093
 45.000
          0.373
                  0.085
 47.000
          0.403
                  0.080
 49.000
          0.379
                  0.079
 51.000
          0.343
                  0.078
 53.000
          0.332
                  0.075
 55.000
          0.323
                  0.063
                  0.062
 57.000
          0.318
 59.000
          0.364
                  0.073
 61.000
          0.415
                  0.074
 63.000
          0.394
                  0.063
 65.000
          0.361
                  0.066
((MANUAL 0.0 7.116422e-7 0.015379674 0.059214685 0.07821559 0.074922346 0.07778276
0.08459592 0.084080234 ...)
 (GOAL 0.0036787947 0.12099249 0.27242562 0.36315846 0.40226096 0.41133723 0.4366023
0.41118938 0.36133355 ...))
> (predict-bold-response 0 (mp-time) nil)
((MANUAL 0.0 7.116422e-7 0.015379674 0.059214685 0.07821559 0.074922346 0.07778276
0.08459592 0.084080234 ...)
 (GOAL 0.0036787947 0.12099249 0.27242562 0.36315846 0.40226096 0.41133723 0.4366023
0.41118938 0.36133355 ...))
> (predict-bold-response 4 13 t)
           GOAL MANUAL
    time
   5.000
           0.272
                  0.015
   7.000
          0.363
                  0.059
  9.000
          0.402
                  0.078
          0.411
 11.000
                  0.075
((MANUAL 0.015379674 0.059214685 0.07821559 0.074922346) (GOAL 0.27242562 0.36315846
0.40226096 0.41133723))
E> (predict-bold-response 1 (mp-time) nil)
#|Warning: Start time should be a multiple of :bold-inc (2). Using start time of 0. |#
((MANUAL 0.0 7.116422e-7 0.015379674 0.059214685 0.07821559 0.074922346 0.07778276
0.08459592 0.084080234 ...)
(GOAL 0.0036787947 0.12099249 0.27242562 0.36315846 0.40226096 0.41133723 0.4366023
0.41118938 0.36133355 ...))
E> (predict-bold-response 'a (mp-time) nil)
#|Warning: Start time for predicting BOLD response must be a number, but A given. Using 0
instead. |#
((MANUAL 0.0 7.116422e-7 0.015379674 0.059214685 0.07821559 0.074922346 0.07778276
0.08459592 0.084080234 ...)
 (GOAL 0.0036787947 0.12099249 0.27242562 0.36315846 0.40226096 0.41133723 0.4366023
0.41118938 0.36133355 ...))
E> (predict-bold-response 50 'bad nil)
#|Warning: End time for predicting BOLD response must be a number, but BAD given. Using
current-time instead. |#
((MANUAL 0.077776566 0.07488024 0.062607914 0.062190473 0.073173605 0.073846556 0.06338371
0.06570311)
(GOAL 0.34314317 0.33192348 0.32307497 0.3179245 0.36359704 0.41549307 0.39395335
0.36075956))
E>(predict-bold-response 1 2 nil)
```

```
#|Warning: Sample time too short for BOLD predictions - must be at least :bold-inc seconds
(currently 2) |#
((MANUAL) (GOAL))

E> (predict-bold-response)
#|Warning: Predict-bold-response requires a current model. |#
NIL
```

Checking and testing version information

If one wants to access the ACT-R version in code there are a couple of ways, along with a command that can be added to a model file to compare the version for which the model was written to the current version and warn if they may be incompatible.

Feature tests

One option for testing the version is through the use of keywords on the Lisp *features* list. Two or three keywords will be added to the *features* list indicating the ACT-R version details when it is loaded. The first is :act-r-7 which will always be on the list. The second will include the major software version number like this :act-r-7.X where X is the major version number e.g. :act-r-7.0. If there is a minor version number then an additional keyword will be added indicating both the major and minor versions like this :act-r-7.X.Y where X is the major and Y the minor version numbers e.g. :act-r-7.0.1.

```
> *features*
(:ACTR-ENVIRONMENT :ACT-R-7.0.1 :ACT-R-7.0 :ACT-R-7 :ACT-R ...)
```

System parameters

The other way to test the version is through system parameters that hold the version information. There are four system parameters which hold the version details. None of those parameters can be changed using ssp, they are effectively read-only – it will output a warning indicating that they cannot be modified if they are attempted to be set.

:act-r-version

This parameter always returns the string with the complete version specification, and it cannot be changed:

```
> (ssp :act-r-version)
("7.0-<internal>")
> (ssp :act-r-version "1.1")
#|Warning: System parameter :ACT-R-VERSION cannot take value 1.1 because it must be unmodified. |#
(:INVALID-VALUE)
```

:act-r-architecture-version

This parameter always returns the current architecture version number, and it cannot be changed:

```
> (ssp :act-r-architecture-version)
(7)
> (ssp :act-r-architecture-version 8)
#|Warning: System parameter :ACT-R-ARCHITECTURE-VERSION cannot take value 8 because it must be unmodified. |#
(:INVALID-VALUE)
```

:act-r-major-version

This parameter always returns the current major version number, and it cannot be changed:

```
> (ssp :act-r-major-version)
(0)
> (ssp :act-r-major-version 2)
#|Warning: System parameter :ACT-R-MAJOR-VERSION cannot take value 2 because it must be unmodified. |#
(:INVALID-VALUE)
```

:act-r-minor-version

This parameter always returns the current minor version number, and it cannot be changed:

```
> (ssp :act-r-minor-version)
(1)
> (ssp :act-r-minor-version 4)
#|Warning: System parameter :ACT-R-MINOR-VERSION cannot take value 4 because it must be unmodified. |#
(:INVALID-VALUE)
```

Version test command

written-for-act-r-version

Syntax:

written-for-act-r-version version-string {description} -> [t | nil | :invalid-value]

Arguments and Values:

```
version-string ::= a string containing a valid ACT-R version which would be of the form: A\{.B\{.C\}\}\{-< tag>\} where A, B, and C are integers and tag is any text. description ::= a string containing additional text to display in the warning
```

Description:

The written-for-act-r-version command will test a specified version string against the version of the currently loaded ACT-R system and print a warning if the specified version may not be compatible with the current version and return the value **nil**. If they are compatible then no warning will be printed and it will return **t**. If an invalid version string is provided it will print a warning indicating that and return the keyword **:invalid-value**.

If a description string is provided then that will be shown in the warning when an incompatible version is detected.

The intention for this function is to use it at the top level of a model file, new module, or other extension code specifying the version of ACT-R in which it was written and run. That way if that code is made available to others (perhaps on a web site) and someone later tries to use it in a potentially incompatible version there will be a warning about that when it is loaded. Two recommended places to place this call would be immediately after the call to clear-all in a model file or just before the first call to define-model or define-module in a file.

Examples:

These examples were run with this version of ACT-R:

```
> (ssp :act-r-version)
("7.0.4-<internal>")
> (written-for-act-r-version "7.0.4-<internal>")
> (written-for-act-r-version "7")
> (written-for-act-r-version "7.0" "Test code")
> (written-for-act-r-version "7.0.1")
E> (written-for-act-r-version "8")
#|Warning: Current ACT-R architecture 7 is not the same as 8 specified in 8. |#
NIL
E> (written-for-act-r-version "7.1")
#|Warning: Current ACT-R major version 0 is older than major version 1 specified in 7.1.
           Some features may not be implemented. |#
NIL
E> (written-for-act-r-version "7.1" "Example model")
#|Warning: Current ACT-R major version 0 is older than major version 1 specified in 7.1
for Example model.
           Some features may not be implemented. |#
NIL
E> (written-for-act-r-version 7)
```

#|Warning: Invalid version specified in written-for-act-r-version: 7. Version must be an
ACT-R version string. |#
:INVALID-VALUE

E> (written-for-act-r-version "bad")
#|Warning: Invalid version specified in written-for-act-r-version: "bad". Version must be
an ACT-R version string. |#
:INVALID-VALUE

Loading Extra Components

Included with the ACT-R software are some optional extensions which have been written to extend or modify the operation of the software. These extensions can be found in the extras directory of the distribution. Each of the extras includes documentation which describes how to load and use it which typically requires explicitly loading files or moving them into other directories so that the ACT-R code will load them automatically. However, for convenience many of the extra components can also be loaded with a command called require-extra which can be added to a model file to have an extra automatically loaded instead of having to manually load the file(s). This can be useful when providing models to other users so that they do not have to load additional files or reconfigure their ACT-R code to be able to run the model.

Commands

require-extra

Syntax:

require-extra name -> [t | nil]

Arguments and Values:

name ::= a string which names an extra component that should be loaded if necessary

Description:

Require-extra can be used to compile and load the code necessary to use an extension to ACT-R found in the extras directory of the source code distribution. The name provided should be the name of the directroy in extras that contains the extension, but not all of the extras support the use of require-extra (see an extra's documentation for details). Require-extra can only be used when there are no current models defined. Thus, the recommended place to put it in a model file is directly following the call to <u>clear-all</u>. If the necessary componenets to use that extra have not already been loaded then they will be compiled and loaded. If that is successful **t** will be returned. If the extra has already been loaded then **nil** will be returned, and if there are any problems then a warning will be displayed and **nil** will be returned.

Examples:

```
1> (require-extra "blending")
```

```
T
2> (require-extra "blending")
NIL
E> (require-extra "blending")
#|Warning: Cannot require an extra when there is a current model. |#
NIL
E> (require-extra "bad-name")
#|Warning: Directory C:\actr7\extras\bad-name\ for specified extra bad-name not found. |#
NIL
E> (require-extra "chunk-tree-viewer")
#|Warning: Load file for extra chunk-tree-viewer at location
C:\actr7\extras\chunk-tree-viewer\chunk-tree-viewer.lisp not found. |#
NIL
```

Creating Visual Features

Instead of (or in addition to) using a device like the AGI to generate visual features for a model the modeler can also create custom visual features using the same commands that are used by the AGI. The commands described below allow one to create features, modify those features, and remove those features from the visicon. Those features may contain any information the modeler wants to provide to the model, and the only constraint is that each one must specify an x,y position (the z position will be set by the default viewing distance if not provided).

The features created using the add-visicon-features command map a location chunk to an object chunk for each feature. The result of creating a feature is three items: the visual feature (which is the combination of the location and object information), the visual location chunk, and the visual object chunk. There is no mechanism to support a single object having multiple location chunks or viceversa at this time, but a generalization of the scale ability that was possible for text features in prior versions is being planned for a future update. That said, there is a device which can be installed to allow the modeler to create the visual object chunks dynamically as described below.

Using any of these commands will cause the vision module to update the visicon information and reprocess the features for possibly stuffing a chunk into the visual-location buffer and/or re-encoding the currently attended location. That update is scheduled at the current time if there is not one already scheduled to occur and the vision module can safely update the visicon. If the module cannot safely update the information at the current time then the update will be delayed and scheduled to occur when it is safe to do so (it is unsafe to update the information during the firing of a production which is making a visual buffer request). All of the changes which have been made will be processed during that update — it does not process each one separately. The updating will generate two events. The first will have an action of proc-display and the second will be a signal which can be monitored called visicon-update. Here is how those will look in the trace (the visicon-update only displays in the high detail level):

0.000 VISION PROC-DISPLAY 0.000 VISION visicon-update

Object-creator device

There is a device called object-creator which can be installed for the vision interface that allows the modeler to provide a command for creating visual object chunks. When installing that device the

details of the device (the third element of the list) must be a valid command. That command will be called whenever the vision module needs to create a visual object chunk for a feature from the visicon. That command will be passed the feature id of the feature which is being attended by the model. If the command returns a chunk then that chunk will be used as the visual object that is attended, otherwise the original visual object from the feature will be used.

Examples

Examples of creating custom visual features and using an object-creator device can be found in the examples/vision-module directory of the distribution.

Commands

add-visicon-features

Syntax:

add-visicon-features feature-description* -> (feature-id*)

Remote command name:

add-visicon-features ' feature-description* '

Arguments and Values:

```
feature-description ::= (feature-spec*)
feature-spec ::= [ [slot | isa ] [value | (loc-value obj-value) ] | feat-param param-val ]
slot ::= the name of a slot for the feature
value ::= the value for the corresponding slot of the feature's location | nil ]
obj-value ::= [ the value for the corresponding slot of the feature's object | nil ]
feat-param ::= [:x-slot | :y-slot | :z-slot | :width-fn ]
param-val ::= the value for the corresponding feature parameter
feature-id ::= [feat-name | nil ]
feat-name ::= a name for referring to a created feature
```

Description:

The add-visicon-features command is used to create visual features for the current model. A visual feature is a combination of a visual location and a visual object. This command allows the modeler to specify a visual location and visual object for any number of features and it will create the feature information from each of those pairs to add to the visicon and return the ids for referring to those features for use with the modify-visicon-features and delete-visicon-features commands. When the

model finds a feature through a visual-location buffer request the visual location chunk from that feature will be placed into the visual-location buffer, and when that feature is attended through a move-attention request to the visual buffer (or the automatic re-encoding of an already attended feature) the visual object chunk will be placed into the visual buffer (unless the <u>object-creator</u> device is installed and provides an alternate object chunk).

The visual location and visual object chunks for a feature are specified in a format very similar to that of the <u>define-chunks</u> and <u>add-dm</u> commands – a list of slot value pairs with an optional chunk-type declaration specified with isa. The difference is that both chunks are specified in a single list. If a value for a slot (or the isa declaration) is specified with an atomic element (not a list) then that slot and value will appear in both the visual location and visual object unless it is one of the position slots (which are screen-y, screen-y, and distance by default) in which case it only belongs to the visual location chunk. If a slot is specified with a list of two values then the first of those values will be the value for the visual location chunk and the second will be the value for the visual object chunk. When specifying that list of two values a value of nil can be used to indicate that the corresponding chunk not have that slot. If the visual location for a feature does not contain an x and y position then the feature is not created. If the visual location does not have a z position then that slot will be added with a value of the <u>:viewing-distance</u> parameter. If the visual location does not have a value for the size slot then a size will be computed for it using the values from the height and width slots of the location chunk if it has them otherwise it will get the default size value of 1.0. Finally, if the visual location chunk does not have a value for a slot named kind and there was a chunk-type declared with isa for the visual object chunk then the visual location chunk will get a kind slot with a value that is the chunk-type declared for the visual object.

In addition to the slots for the visual location and visual object chunks there are four parameters which can be specified to indicate some configuration information about the feature. Three parameters :x-slot, :y-slot, and :z-slot allow one to change the names of the slots used to hold the position information in the visual location chunk. The default slot names are screen-x, screen-y, and distance, but the default values can be changed using set-default-vis-loc-slots if one does not want to set the parameters for every feature explicitly. A value for one of those parameters changes the name of the slot that will be used to hold the corresponding position value instead of the default slot for that position. The :width-fn parameter can be specified with a valid command as a value and that command will be called when the motor module needs to determine the effective width of the item for computing a time to move to it using Fitts law. That command will be passed four parameters: the feature id, the angle of the approach (in radians), and the x and y starting position for the

approach. If it returns a number then that will be used as the width of the item (in degrees of visual angle) otherwise the default calculation will be performed to compute a width.

The features which are available for the model to find using a visual-location buffer request are the union of the slots and values from the visual-location and visual-object chunks with the value from the visual object being used if both chunks have a value for the slot, and that is the information which is displayed by the print-visicon command.

If there is no current model then this command will print a warning and return **nil**. If there is a current model, then the return value from this command is a list with the same number of elements as there were feature descriptions provided. If the corresponding feature description resulted in a valid feature being created then the return list will contain an id for that feature, but if the feature could not be created then the value in the return list will be **nil** and a warning will be printed to indicate the invalid feature.

Examples:

Only examples of the warning messages are shown here. For actual examples of using the command see the examples/vision-module directory of the distribution.

```
E> (add-visicon-features '(screen-x 0 screen-y 0) '(bad-slot 0))
#|Warning: Extending chunks with slot named BAD-SLOT because of chunk definition (BAD-SLOT 0) |#
#|Warning: Visicon feature (BAD-SLOT 0) did not contain a valid feature and was not created. |#
(VISICON-ID2 NIL)

E> (add-visicon-features '(screen-x 10 screen-y 10))
#|Warning: get-module called with no current model. |#
NIL
```

modify-visicon-features

Syntax:

modify-visicon-features feature-modification* -> (mod-result*)

Remote command name:

modify-visicon-features ' feature-modification* '

Arguments and Values:

```
feature-modification ::= (mod-id mod*)
mod-id ::= the name of a feature that has been added to the visicon
mod ::= slot [ value | (loc-value obj-value) ]
```

```
slot ::= the name of a slot for the feature
value ::= the value for the corresponding slot of the feature
loc-value ::= [ the value for the corresponding slot of the feature's location | nil ]
obj-value ::= [ the value for the corresponding slot of the feature's object | nil ]
mod-result ::= [mod-id | nil ]
```

Description:

The modify-visicon-features command is used to modify visual features for the current model which were created with add-visicon-features. This command allows the modeler to modify both the visual location and visual object for a feature. The modifications for a feature are specified in a format very similar to that of add-visicon-features. The first element of a modification specification must be the name of a visicon feature which was previously added to the visicon, and the remainder is a set of slot value pairs to indicate the modifications. If a value for a slot is specified with a value that is not a list of 2 values then that slot of both the visual location and visual object chunks will be modified to contain the new value (unless it is one of the position slots in which case it is only modified for the visual location chunk). If a slot is specified with a list of two values then the first of those values will be the modified value for the visual location chunk and the second will be the modified value for the visual object chunk. When specifying that list of two values a value of **nil** can be used to indicate that the corresponding chunk should not have its slot modified.

If there is no current model then this command will print a warning and return **nil**. If there is a current model, then the return value from this command is a list with the same number of elements as there were modification lists provided. If the corresponding modification resulted in a valid modification then the return list will contain the id for that feature, but if the feature could not be modified then the value in the return list will be **nil** and a warning will be printed to indicate the invalid modification.

Examples:

Only examples of the warning messages are shown here. For actual examples of using the command see the examples/vision-module directory of the distribution.

```
E> (modify-visicon-features '(bad-feature screen-x 10))
#|Warning: Provided update (BAD-FEATURE SCREEN-X 10) does not contain a valid visual
feature modification. |#
(NIL)

E> (modify-visicon-features )
#|Warning: get-module called with no current model. |#
NIL
```

delete-visicon-features

Syntax:

delete-visicon-features feature-id* -> (del-result*)

Remote command name:

delete-visicon-features

Arguments and Values:

```
feature-id ::= the name of a feature that has been added to the visicon del-result ::= [feature-id | nil ]
```

Description:

The delete-visicon-features command is used to remove visual features from the current model which were created with add-visicon-features. It takes any number of parameters and for each one that is the name of a visual feature in the current model it will remove that feature from the visicon.

If there is no current model then this command will print a warning and return **nil**. If there is a current model, then the return value from this command is a list with the same number of elements as there were items provided. If a provided name was in the visicon and could be deleted then the return list will contain that name in the corresponding position, but if the item did not name a feature in the visicon then the value in the return list will be **nil** and a warning will be printed to indicate the invalid value.

Examples:

Only examples of the warning messages are shown here. For actual examples of using the command see the examples/vision-module directory of the distribution.

```
E> (delete-visicon-features 'bad-name)
#|Warning: Feature BAD-NAME is not a valid feature name and cannot be removed. |#
(NIL)
E> (delete-visicon-features)
#|Warning: get-module called with no current model. |#
NIL
```

delete-all-visicon-features

Syntax:

```
delete-all-visicon-features -> [t | nil ]
```

Remote command name:

delete-all-visicon-features

Description:

The delete-all-visicon-features command is used to remove all of the visual features from the current model which were created with add-visicon-features.

If there is no current model then this command will print a warning and return **nil**. If there is a current model, then the return value from this command will be **t**.

Examples:

```
> (delete-all-visicon-features)
T
E> (delete-all-visicon-features)
#|Warning: get-module called with no current model. |#
NIL
```

set-default-vis-loc-slots

Syntax:

```
set-default-vis-loc-slots x-slot y-slot z-slot -> [ t | nil ] set-default-vis-loc-slots-fct x-slot y-slot z-slot -> [ t | nil ]
```

Remote command name:

set-default-vis-loc-slots

Arguments and Values:

```
x-slot ::= the name of a slot to use for the x position coordinate y-slot ::= the name of a slot to use for the y position coordinate z-slot ::= the name of a slot to use for the z position coordinate
```

Description:

The set-default-vis-loc-slots command is used to change the default names for the position slots used in visual features for the current model. If the three names provided are valid slot names for chunks in the current model then those slots will be considered as the ones which represent the position information in visual-features created after that call.

If the values are all different valid slot names then those names will be used and it will return **t**. If there is no current model, the names do not name valid slots, or there are duplicates among them then this command will print a warning and return **nil**.

Examples:

Only examples of the warning messages are shown here. For actual examples of using the command see the examples/vision-module directory of the distribution.

```
E> (set-default-vis-loc-slots a b c)
#|Warning: get-module called with no current model. |#
#|Warning: No vision module available in call to set-default-vis-loc-slots. |#
NIL

E> (set-default-vis-loc-slots-fct 'screen-x 'screen-y 'bad-slot)
#|Warning: Slot BAD-SLOT is not valid in call to set-default-vis-loc-slots. |#
NIL

E> (set-default-vis-loc-slots screen-x screen-y)
#|Warning: Duplicate slot names provided for set-default-vis-loc-slots: SCREEN-X, SCREEN-X, SCREEN-Y |#
NIL
```

Adding new production compilation types

Not yet documented.

References

Anderson, J. R. (2007) *How Can the Human Mind Occur in the Physical Universe?* New York: Oxford University Press.

Anderson, J. R., Bothell, D., Byrne, M. D., Douglass, S., Lebiere, C., & Qin, Y. (2004). An integrated theory of the mind. *Psychological Review 111*, (4). 1036-1060.

Anderson, J.R., Fincham, J. M., Qin, Y., & Stocco, A. (2008). A central circuit of the mind. *Trends in Cognitive Science*. *12*(4), 136-143.

Anderson, J. R. & Lebiere, C. (1998). *The atomic components of thought*. Mahwah, NJ: Erlbaum.

Briggs, R., & Hocevar, D. J. (1975). A new distinctive feature theory for upper case letters. *Journal of General Psychology*, 93, 87-93.

Friston, K. J., Ashburner, J. T., Kiebel, S. J., Nichols, T. E., & Penny, W. D. (Eds.). (2011). Statistical parametric mapping: The analysis of functional brain images. Academic Press

Gibson, E. J. (1969). *Principles of perceptual learning and development*. New York: Appleton-Century-Crofts.

Kieras, D. E., & Meyer, D. E. (1996). *The EPIC architecture: Principles of operation*. Retrieved June 3, 2008, from University of Michigan, Department of Electrical Engineering and Computer Science Web site: ftp://www.eecs.umich.edu/people/kieras/EPIC/EPICPrinOp.pdf

Matsumoto, M. & Nishimura, T. (1998). Mersenne Twister: A 623-dimensionally equidistributed uniform pseudorandom number generator. *ACM Trans. on Modeling and Computer Simulation Vol.* 8, No. 1. 3-30.

McClelland, J. L., & Rumelhart, D. E. (1981). An interactive model of context effects in letter perception: I. An account of basic findings. *Psychological Review*, 88, 375-407.

Pylyshyn, Z. (1999). Is vision continuous with cognition? The case for cognitive impenetrability of visual perception. *Behavioral and Brain Sciences*, *22*, 341–423.

Salvucci, D. D. (2001). An integrated model of eye movements and visual encoding. *Cognitive Systems Research*, *1*, 201-220.

Salvucci, D. D., & Taatgen, N. A. (2008). Threaded cognition: An integrated theory of concurrent multitasking. *Psychological Review*, *115*(1), 101-130.

Taatgen, N. A., Rijn, H. v., & Anderson, J. R. (2007). An Integrated Theory of Prospective Time Interval Estimation: The Role of Cognition, Attention and Learning. *Psychological Review*, *114*(3), 577-598.

Tresiman, A.M., & Gelade, G. (1980). A feature-integration theory of attention. *Cognitive Psychology*, *1*, 97-136.